

DOCUMENT RESUME

ED 115 258

IR 002 802

AUTHOR Bellamy, Harold J.; And Others
TITLE Design of Training Systems. Program Maintenance Manual; Data Base, ETE, SCRR, and TPF Models. Report No. 29.
INSTITUTION Naval Training Equipment Center, Orlando, Fla. Training Analysis and Evaluation Group.
REPORT NO TAEG-R-29
PUB DATE Sep 75
NOTE 617p.; For a related document see IR 002 803; Not available in hard copy, due to print size of the original document

EDRS PRICE MF-\$1.08 Plus Postage. HC Not Available from EDRS.
DESCRIPTORS *Computer Programs; Data Bases; Educational Technology; Flow Charts; *Instructional Design; Job Analysis; *Job Training; *Management Systems; Military Training; Models; Occupational Information; On Line Systems; Program Descriptions; Skill Analysis; *Systems Approach; Time Sharing; Training; Training Objectives

IDENTIFIERS Program Documentation; *Training Analysis and Evaluation Group

ABSTRACT

This report contains detailed information on the three Design of Training Systems (DOTS) models and the DOTS data base. It consists of a single volume containing a description and macro flow, detailed logic flows and program listings for the Educational Technology Evaluation (ETE) model, the System Capabilities Requirements and Resources (SCRR) model, the Training Processes Flow (TPF) model, and the DOTS data base. Control logic, input/output record formats, the temporary and permanent data files are described for each subsystem (the three models and the data base). The information contained in this volume is intended for use by programmers given the task of installing and modifying the DOTS programs. (Author/EMH)

* Documents acquired by ERIC include many informal unpublished *
* materials not available from other sources. ERIC makes every effort *
* to obtain the best copy available. Nevertheless, items of marginal *
* reproducibility are often encountered and this affects the quality *
* of the microfiche and hardcopy reproductions ERIC makes available *
* via the ERIC Document Reproduction Service (EDRS). EDRS is not *
* responsible for the quality of the original document. Reproductions *
* supplied by EDRS are the best that can be made from the original. *

TAE G

TRAINING
ANALYSIS
AND
EVALUATION
GROUP

TAE G REPORT
NO. 29


DESIGN OF TRAINING SYSTEMS PROGRAM MAINTENANCE MANUAL

DATA BASE, ETE, SCRR, AND TPF MODELS

U.S. DEPARTMENT OF HEALTH,
EDUCATION & WELFARE
NATIONAL INSTITUTE OF
EDUCATION

THIS DOCUMENT HAS BEEN REPRODUCED EXACTLY AS RECEIVED FROM THE PERSON OR ORGANIZATION ORIGINATING IT. POINTS OF VIEW OR OPINIONS STATED DO NOT NECESSARILY REPRESENT OFFICIAL NATIONAL INSTITUTE OF EDUCATION POSITION OR POLICY.

FOCUS
ON
THE
TRAINED
MAN



BEST COPY AVAILABLE

2

SEPTEMBER 1975

TRAINING ANALYSIS AND EVALUATION GROUP
ORLANDO, FLORIDA 32813

IR002802

Technical Report: TAEG REPORT NO. 29

DESIGN OF TRAINING SYSTEMS

PROGRAM MAINTENANCE MANUAL

ABSTRACT

This report contains detailed information on the three Design of Training Systems (DOTS) models and the DOTS data base. It consists of a single volume containing a description and macro flow, detailed logic flows and program listings for the Educational Technology Evaluation model (ETE), the System Capabilities Requirements and Resources (SCRR) model, the Training Process Flow (TPF) model and the DOTS data base.

Control logic, input/output record formats, and temporary and permanent data files are described for each subsystem (the three models and the data base). The information contained in this volume is intended for use by programmers tasked with installing or modifying the DOTS programs.

The programs described in this manual were developed by IBM Corporation for the Training Analysis and Evaluation Group, Orlando, Florida (Contract No. N61339-73-C-0097).

Reproduction of this publication
in whole or in part is permitted
for any purpose of the United
States Government.

TAEG Report No. 29

DESIGN OF TRAINING SYSTEMS
PROGRAM MAINTENANCE MANUAL
DATA BASE, ETE, SCRR, AND TPF MODELS

Harold J. Beilamy
Kenneth V. Branch
James D. Staley
Ronald E. Yanko

This Report Was Prepared
by
International Business Machines Corporation
for the

Training Analysis and Evaluation Group

September 1975

BEST COPY AVAILABLE

Alfred F. Smode

ALFRED F. SMODE, Ph.D., Director,
Training Analysis and Evaluation Group

U.S. DEPARTMENT OF HEALTH,
EDUCATION & WELFARE
NATIONAL INSTITUTE OF
EDUCATION

THIS DOCUMENT HAS BEEN REPRODUCED EXACTLY AS RECEIVED FROM THE PERSON OR ORGANIZATION ORIGINATING IT. POINTS OF VIEW OR OPINIONS STATED DO NOT NECESSARILY REPRESENT OFFICIAL NATIONAL INSTITUTE OF EDUCATION POSITION OR POLICY.

TABLE OF CONTENTS

<u>SECTION</u>		<u>PAGE</u>
I	INTRODUCTION	
	PURPOSE	I-1
	ORGANIZATION	I-1
	SYSTEM APPLICATION	I-1
	EQUIPMENT ENVIRONMENT	I-3
	PROGRAM ENVIRONMENT	I-3
II	DATA BASE MAINTENANCE EXECUTIVES AND PROGRAMS	
	INTRODUCTION	II-1
	GENERAL SYSTEM PROCEDURES	II-2
	RAMIS FILE DESCRIPTION - FACILITIES FILE	II-3
	RAMIS FILE DESCRIPTION - INSTRUCTOR FILE	II-6
	RAMIS FILE DESCRIPTION - COURSE FILE	II-10
	EXECUTIVE SEQUENCE DOCUMENTATION	II-16
	DATA BASE EXECUTIVE INDEX	II-23
	FACILITY FILE EXECUTIVE SEQUENCES	II-25
	INSTRUCTOR FILE EXECUTIVE SEQUENCES	II-60
	COURSE FILE EXECUTIVE SEQUENCES	II-117
	PGM5	II-168
	PGM7	II-177
	PGM8	II-182
	PGM9B	II-196
	PGM16	II-202
	PGM19	II-212

TABLE OF CONTENTS

<u>SECTION</u>		<u>PAGE</u>
	PGM20	II-229
	PGM22	II-235
	PROMPTX	II-243
III	ETE MODEL	
	MODEL DESCRIPTION	III-1
	EXECUTIVE SUBSYSTEM	III-6
	MODEL GENERATION SUBSYSTEM	III-15
	MODEL UPDATE	III-38
	SIMULATION SUBSYSTEM	III-60
	SIMULATION OUTPUT	III-62
IV	SYSTEM CAPABILITIES/REQUIREMENTS AND RESOURCES MODEL	
	MODEL DESCRIPTION	IV-1
	SCRR EXEC DESCRIPTION	IV-5
	RAMSCRR EXEC DESCRIPTION	IV-8
	SCRR INST DESCRIPTION	IV-8
	SCRR FACIL DESCRIPTION	IV-8
	SCRR FAVAIL DESCRIPTION	IV-9
	SCRR IAVAIL DESCRIPTION	IV-9
	SCRR CRSE DESCRIPTION	IV-10
	BLANK EXEC DESCRIPTION	IV-14
	BLANK PLI DESCRIPTION	IV-14
	CONCAT PLI DESCRIPTION	IV-14
	INTERFACE (IF1, IF2, IF3, AND IF4) EXECS OVERVIEW	IV-20

TABLE OF CONTENTS

<u>SECTION</u>	<u>PAGE</u>
IF1 EXEC DESCRIPTION	IV-22
IF1 FORTRAN DESCRIPTION	IV-22
IF2 EXEC DESCRIPTION	IV-27
INTERFAC FORTRAN DESCRIPTION	IV-27
SCRRSORT EXEC DESCRIPTION	IV-35
IF3 EXEC DESCRIPTION	IV-36
IF3 FORTRAN DESCRIPTION	IV-36
IF4 EXEC DESCRIPTION	IV-41
IF4 FORTRAN DESCRIPTION	IV-41
COMB EXEC DESCRIPTION	IV-45
SCRR1 EXEC DESCRIPTION	IV-46
SCRR RUN DESCRIPTION	IV-46
SCRRFORM FORTRAN DESCRIPTION	IV-49
ASSIGN EXEC DESCRIPTION	IV-65
ASSIGN1 FORTRAN DESCRIPTION	IV-65
ASSIGN2 FORTRAN DESCRIPTION	IV-66
MODAVAIL EXEC DESCRIPTION	IV-75
MODIFY FORTRAN DESCRIPTION	IV-75
REQMT EXEC DESCRIPTION	IV-81
REQMT RUNEXEC DESCRIPTION	IV-81
REQMT1 RUNEXEC DESCRIPTION	IV-81
REQMT2 RUNEXEC DESCRIPTION	IV-82
SCRR2 EXEC DESCRIPTION	IV-87
FIXCONV EXEC DESCRIPTION	IV-88
MAXCONV EXEC DESCRIPTION	IV-89

TABLE OF CONTENTS

<u>SECTION</u>	<u>PAGE</u>
V	
TRAINING PROCESS FLOW MODEL	
MODEL DESCRIPTION	V-1
SUPPORT PROGRAMS	V-1
DATA BASE SUPPORT PROGRAMS	V-3
"WHAT IF" SUPPORT PROGRAMS	V-11
COURSE MODIFICATIONS	V-11
ACROSS THE BOARD MODIFICATIONS	V-15
DISPLAY SUPPORT PROGRAM	V-71
EXECUTIVE DISPLAY	V-71
PROGRAM DISPLAY	V-71
TPL LOGIC DESIGN	V-84
PROGRAM LOGIC DESIGN	V-84
TPF MODEL MODEL MAIN	V-84
SUBROUTINE CRSLS	V-87
SUBROUTINE PRERUN	V-87
SUBROUTINE CRSEND	V-87
SUBROUTINE QTREND	V-88
SUBROUTINE YEARND	V-88
SUBROUTINE CRTOUT	V-88
SUBROUTINE NPRINT	V-88

TAEG REPORT NO. 29

LIST OF FIGURES

<u>FIGURE NO.</u>	<u>TITLE</u>	<u>PAGE</u>
III-1	ETE Model Operation Procedure Overview	III-2
III-2	ETE Model Logic Overview	III-3
III-3	ETE Data File Summary	III-5
III-4	ETE2 and ETEPTR Executive Logic Flow	III-7
III-5	PROF Flowcharts	III-17
III-6	Input Card Specifications	III-37
III-8	MAD Flowcharts	III-40
III-9	System Generated GPSS Functions	III-61
IV-1	Overview of SCRR Executive Programs	IV-2
IV-2	SCRR EXEC Flowchart	IV-6
IV-3	RAMSCRR EXEC Flowchart	IV-11
IV-4	BLANK EXEC Flowcharts	IV-15
IV-5	Data Base INTERFACE EXEC Flowchart	IV-21
IV-6	IF1 Flowcharts	IV-23
IV-7	INTERFAC Flowcharts	IV-29
IV-8	IF3 Flowcharts	IV-37
IV-9	IF4 Flowcharts	IV-42
IV-10	SCRR EXEC Flowchart	IV-50
IV-11	ASSIGN EXEC Flowchart	IV-67
IV-12	MODAVAIL EXEC Flowchart	IV-76
IV-13	REQMNT EXEC Flowchart	IV-83
V-1	TPF Model Simplified System Flow	V-2
V-2	TPF Model Data Base Interface	V-4

LIST OF FIGURES

<u>FIGURE NO.</u>	<u>TITLE</u>	<u>PAGE</u>
V-3	TPF Input Formats	V-6
V-4	Flow Executive TPF COPY	V-7
V-5	TPF Model "WHAT IF" and Output Display	V-12
V-6	Flow Executive TPFMOD	V-17
V-7	Autoflow Program TPFMOD	V-19
V-8	Autoflow Subroutine DECODE	V-29
V-9	Autoflow Subroutine CONVRT	V-42
V-10	Autoflow Subroutine MSG	V-44
V-11	Autoflow Subroutine SHOW	V-46
V-12	Flow Executive TPF	V-50
V-13	Autoflow Program PARAM	V-51
V-14	Autoflow Program DISPLAY	V-76
V-15	Course Scheduler Matrix	V-89
V-16	Sample TPF Outputs	V-90
V-17	Autoflow Program KEND	V-91

TAEG REPORT NO. 29

LIST OF TABLES

<u>TABLE NO.</u>	<u>TITLE</u>	<u>PAGE</u>
III-1	ETE Programs and Executives	III-4
III-2	ETE Executive Listings	III-9
III-3	PROF Program Listings	III-33
III-4	Sample Edit Commands	III-39
III-5	MAD Program Listings	III-57
III-6	DUMMY GPSS Listing	III-65
IV-1	SCRR Executive Programs Description	IV-3
IV-2	SCRR Data File Summary	IV-4
IV-3	SCRR Program Listing	IV-7
IV-4	RAMSCRR Program Listings	IV-12
IV-5	Blank Program Listings	IV-18
IV-6	IF1 Program Listings	IV-25
IV-7	IF2 Program Listings	IV-33
IV-8	SCRRSORT Program Listing	IV-35
IV-9	IF3 Program Listings	IV-39
IV-10	IF4 Program Listings	IV-43
IV-11	COMB Program Listing	IV-45
IV-12	SCRR1 Program Listings	IV-51
IV-13	ASSIGN Program Listings	IV-73
IV-14	MODAVAIL Program Listings	IV-79
IV-15	REQMT Program Listings	IV-84
IV-16	SCRR2 Program Listings	IV-87
IV-17	FIXCONV Program Listing	IV-88
IV-18	MAXCONV Program Listing	IV-89

LIST OF TABLES

<u>TABLE NO.</u>	<u>TITLE</u>	<u>PAGE</u>
V-1	RAMIS Dump Format (Master or Scratch)	V-5
V-2	TPFCOPY DECODE	V-9
V-3	COPY FORTRAN	V-10
V-4	Listing Executive TPFMCD	V-57
V-5	Listing Program TPFMOD	V-58
V-6	Listing Subroutine DECODE	V-60
V-7	Listing Subroutine CONVRT	V-64
V-8	Listing Subroutine MSG	V-65
V-9	Listing Subroutine SHOW	V-66
V-10	Subroutine COMND Listing	V-67
V-11	Listing Executive TPF	V-68
V-12	Listing Program PARAM	V-69
V-13	Listing Display Executives	V-73
V-14	Listing Program DISPLAY	V-74
V-15	Listing Program KEND	V-148

SECTION I

INTRODUCTION

PURPOSE

This Program Maintenance Manual is intended to provide detailed information on the current level of the three Design of Training Systems (DOTS) models and the DOTS data base. The level of information presented should be sufficient to provide a base for programmers intending to install or modify the DOTS System.

ORGANIZATION

This manual is organized around the four major sections of the DOTS System: the DOTS data base, the Educational Technology Evaluation (ETE) model, the System Capabilities Requirements and Resources (SCRR) model and the Training Process Flow (TPF) model. The three models function independently and the data base (although it serves both the SCRR and TPF models) can also be considered as an independent subsystem. Therefore, each of the models and the data base is discussed in a separate section of the manual.

Within each section the subsystem being discussed is subdivided into its major components. Each section contains a subsystem description and macro level flow, detailed flows and program listings of the subsystem components. For FORTRAN and PL1 programs the detailed flow charts were generated using the Autoflow II* System.

SYSTEM APPLICATION

The DOTS system consists of three models supported by a data base. Each model is of a different type and addresses a different facet in the development and management of training courses and systems. Figure I-1 is functional level diagram of the DOTS system showing the interaction of the models and the data base.

The DOTS system is an interactive system. Each of the three models and the data base can be updated and executed via the terminal equipment in the Command and Control Center (CCC). A brief description of the models is presented here. Detailed information on the models is contained in the body of this report and in Volume II of TAEG Report No. 12-2, "Design of Training Systems Phase II Report."

- a) System Capabilities Requirements and Resources (SCRR) model. A linear programming model designed to determine the maximum student throughput for a training complex, based on an optimal mix of course convenings and available resources.

*Autoflow II is a product of Applied Data Research, Inc.




FIGURE I-1 DOTS SYSTEM DIAGRAM

- b) Training Process Flow (TPF) model. The TPF model is an aggregate flow model designed to project the effect, on training system output, of changes in demand, scheduling, course capacity, and utilization.
- c) Educational Technology Evaluation (ETE) model. A generalized entity flow simulation designed to project average time to complete and resource utilization for Individualized Learning Systems.
- d) The DOTS data base provides a common, direct access data source for both the SCRR and TPF models. The DOTS data base was constructed and is accessed via the RAMIS[®] system, a data base language developed by Mathematica, Inc.

EQUIPMENT ENVIRONMENT

All DOTS programs are designed to run, in an interactive mode, on a remote time-shared computer. Time sharing services and support were obtained on a lease basis from National CSS, Inc., Norwalk, Connecticut. The National CSS system is described further under Program Environment.

The only hardware required by the user is a standard remote terminal such as an IBM 2741, a Hazeltine 2000¹, or a Teleterm 1030². The terminal is connected to a dial-up telephone line via a modem. Further information on the different types of terminal equipment which can be employed in conjunction with the time-sharing support should be obtained from National CSS, Inc.

As currently configured, the DOTS system uses thirty-six cylinders of on-line disk storage and runs in a 320K byte partition of main memory.

PROGRAM ENVIRONMENT

In addition to the National CSS time-sharing software, the DOTS system employs several other program packages, all of which run under control of the VP/CSS³ system. The program packages are:

Mathematical Programming System III: MPS III⁴
Rapid Access Management Information System: RAMIS⁵
Norden General Purpose Simulation System V: NGPSSV⁶

-
- 1. Trademark of Hazeltine Corp.
 - 2. Trademark of Computer Devices, Inc.
 - 3. Trademark of National CSS, Inc.
 - 4. Trademark of Management Science Systems, Inc.
 - 5. Trademark of Mathematica, Inc.
 - 6. Trademark of Norden Division of United Aircraft Corporation

Information pertinent to DOTS operations can be found in the following publications:

A Guide to the National CSS Computer System for Application
Product Users (NCSS Form 991)

VP/CSS Edit Command (NCSS Form 108)

Report Generation VP/CSS RAMIS
(NCSS Form 961)

Installer's Guide VP/CSS RAMIS
(NCSS Form 963)

GPSS/Norden Simulation Language
(Reprinted by NCSS)

MPS III User Manual
(Reprinted by NCSS)

Basic system operations such as login, Initial Program Load, system interrupts, etc. are covered in NCSS Form 991 (see above) sections 1 and 7. Consequently, they will not be reproduced in this Program Maintenance Manual.

SECTION II

DATA BASE MAINTENANCE EXECUTIVES AND PROGRAMS

INTRODUCTION

Documentation relative to the software elements developed for creation and maintenance of the three DOTS data bases is included within this section. First, are the RAMIS data management system file descriptions, followed by Executive Sequence details. Program documentation completes the section.

The NCSS Executives contained herein are termed "Executive Sequences", since most are several individual VP/CSS Executives in sequence. Due to the interactive attributes of the DOTS system, Executives are documented herein by reference to the Root Executive, or that to be invoked by the User at the terminal.

Program documentation contains a functional description of the task to be performed, input/output data formats (where applicable), and machine-drawn flowcharts and program source code listings.

Interaction of the User with the data base maintenance Executive Sequences and programs is covered in detail in the DOTS USER'S MANUAL, and is not, in general, reproduced in any detail within this section.

GENERAL SYSTEM PROCEDURES

The implications associated with the following RAMIS file descriptions and VP/CSS Executive Sequences presupposes a rather detailed knowledge on the part of the User with basic services provided by the National CSS (NCSS) time-sharing vendor. These services are formally documented by NCSS and are not reproduced within this manual. To assist those who are unfamiliar with the NCSS documentation, the following references are mentioned:


<u>System Function</u>	<u>NCSS Reference</u>
Typing Conventions, Login, Logout	A Guide to the National CSS Computer System for Application Product Users (NCSS Form 991) Section 1
System Interruptions	A Guide to the National CSS Computer System for Application Product Users (NCSS Form 991) Section 7
CSS Commands Summary	A Guide to the National CSS Computer System for Application Product Users (NCSS Form 991) Appendix B
CSS File Creation and Maintenance	A Guide to the National CSS Computer System for Application Product Users (NCSS Form 991) Section 3
	VP/CSS Edit Command (NCSS Form 108)
Data Base Report Generation	Report Generation VP/CSS RAMIS (NCSS Form 961)
Data Base Maintenance - Scan Mode	Installer's Guide UP/CSS RAMIS (NCSS Form 963) pages 3-37 - 3-84
RAMIS System RUN PROCEDURES	RAMIS Users Guide to the RUN EXECUTIVE (A Publication of MATHEMATICA, Inc., Princeton Station Office Park, P. O. Box 2392, Princeton, N. J. 08540)
VP/CSS EXECUTIVE Language	VP/CSS EXECUTIVE Language (EXEC) (NCSS Form 109-5)

RAMIS FILE DESCRIPTION

DATA BASE (RAMIS NAME): Facilities Master (FACIL)

Facilities Scratch (MODFACIL)

The tree-structure of the DOTS Facilities data bases (Master and Scratch) is as illustrated in the following diagram:



DOTS FACILITIES FILE - HIERARCHIC STRUCTURE

The RAMIS Descriptions supporting the above structure for the Master and Scratch versions of the Facilities data bases are:

<u>Data Base</u>	<u>Description Filename</u>	<u>Description Filetype</u>
Facilities Master	FACIL	DESC
Facilities Scratch	MODFACIL	DESC

Listings of these two descriptions follow:

Listing of Filename = FACIL, Filetype = DESC

```
ERASE*
FILE FACIL
END
INPUT
FILE RAMASTER
1=FACIL,1,S,12,SCH,SCH,A,4,S
2=2,S,5,CDP,CDP,A,4,S
2=3,S,5,BLDG,BLDG,A,5,S
5=RM,RM,A,3,S
5=RMCAP,RMCAP,I,3,S
5=RMTP,RMTP,A,1,S
5=REQHRS,REQHRS,F,6.1,S
5=AVHRS,AVHRS,I,5,S
END
```

Listing of Filename = MODFACIL, Filetype = DESC

```
ERASE*
FILE MODFACIL
END
INPUT
FILE RAMASTER
1=MODFACIL,1,S,12,SCH,SCH,A,4,S
2=2,S,5,CDP,CDP,A,4,S
2=3,S,5,BLDG,BLDG,A,5,S
5=RM,RM,A,3,S
5=RMCAP,RMCAP,I,3,S
5=RMTP,RMTP,A,1,S
5=REQHRS,REQHRS,F,6.1,S
5=AVHRS,AVHRS,I,5,S
END
```

TAEG REPORT NO. 29


A sample output from the RAMIS procedure RAMINDEX is shown below for the Facilities Master data base (FACIL). (A RAMINDEX run for the Scratch version would have been identical.)

DESCRIPTION	FOR	RAMIS	FILE	NAMED	FACIL	09/18/75	
LIST	FIELD NAME	ALIAS	TYPE	LENGTH	LEVEL	SEGMENT	SORT FLAG
1	SCH	SCH	A	4	1	12	S
2	CDP	CDP	A	4	2	5	S
3	BLDG	BLDG	A	5	3	5	S
4	RM	RM	A	3	3	5	S
5	RMCAP	RMCAP	I	3	3	5	S
6	RMTP	RMTP	A	1	3	5	S
7	REQHRS	REQHRS	F	6.1	3	5	S
8	AVHRS	AVHRS	I	5	3	5	S

RAMIS FILE DESCRIPTION

DATA BASE (RAMIS NAME): Instructor Master (INST)
Instructor Scratch (MODINST)

The tree-structure of the DOTS Instructor data bases (Master and Scratch) is as illustrated in the following diagram:



DOTS INSTRUCTOR FILE - HIEARCHTIC STRUCTURE

The RAMIS Descriptions supporting the above structure for the Master and Scratch versions of the Instructor data bases are:

<u>Data Base</u>	<u>Description Filename</u>	<u>Description Filetype</u>
Instructor Master	INST	DESC
Instructor Scratch	MODINST	DESC

Listings of these two descriptions follow:

Listing of Filename = INST, Filetype = DESC

```

ERASE*
FILE INST
END
INPUT
FILE RAMASTER
1=INST,1,S,50,ID,ID,A,9,S
2=2,,1,NME,NME,A,16,S
5=IN,IN,A,2,S
5=RATE,RATE,A,5,S
5=SCH,SCH,A,4,S
5=REP,REP,I,4,S
5=ROT,ROT,I,4,S
5=PNEC,PNEC,A,4,S
5=SNEC,SNEC,A,4,S
2=3,S,5,CDP,CDP,A,4,S
5=TTL,TTL,A,16,S
5=ONB,ONB,A,1,S
5=LDTE,LDTE,I,6,S
2=4,,14,TT,TT,A,3,S
5=CW,CW,F,4,1,S
5=QTD,QTD,F,5,1,,,1,S
5=YTD,YTD,F,6,1,,,1,S
END

```


Listing of Filenames = MODINST, Filetype = DESC

```
ERASE*  
FILE MODINST  
END  
INPUT  
FILE RAMASTER  
1=MODINST,1,S,50,ID,ID,A,9,S  
2=2,,1,NME,NME,A,16,S  
5=IN,IN,A,2,S  
5=RATE,RATE,A,5,S  
5=SCH,SCH,A,4,S  
5=REP,REP,I,4,S  
5=ROT,ROT,I,4,S  
5=PNEC,PNEC,A,4,S  
5=SNEC,SNEC,A,4,S  
2=3,S,5,CDP,CDP,A,4,S  
5=TTL,TTL,A,16,S  
5=ONB,ONB,A,1,S  
5=LDTE,LDTE,I,6,S  
2=4,,14,TT,TT,A,3,S  
5=CW,CW,F,4.1,S  
5=QTD,QTD,F,5.1,,,1,S  
5=YTD,YTD,F,6.1,,,1,S  
END
```

TAEG REPORT NO. 29

A sample output from the RAMIS procedure RAMINDEX is shown below for the Instructor Master data base (INST). (A RAMINDEX run for the Scratch version would have been identical.)


DESCRIPTION	FOR	RAMIS	FILE	NAMED	INST	09/18/75	
LIST	FIELD NAME	ALIAS	TYPE	LENGTH	LEVEL	SEGMENT	SORT FLAG
1	ID	ID	A	9	1	50	S
2	NME	NME	A	16	2	1	
3	IN	IN	A	2	2	1	
4	RATE	RATE	A	5	2	1	
5	SCH	SCH	A	4	2	1	
6	REP	REP	I	4	2	1	
7	ROT	ROT	I	4	2	1	
8	PNEC	PNEC	A	4	2	1	
9	SNEC	SNEC	A	4	2	1	
10	CDP	CDP	A	4	3	5	S
11	TTL	TTL	A	16	3	5	S
12	ONB	ONB	A	1	3	5	S
13	LDTE	LDTE	I	6	3	5	S
14	TT	TT	A	3	4	14	
15	CW	CW	F	4.1	4	14	
16	QTD	QTD	F	5.1	4	14	
17	YTD	YTD	F	6.1	4	14	

RAMIS FILE DESCRIPTION

DATA BASE (RAMIS NAME): Course Master (COURSE)

Course Scratch (MODCOURSE)

The tree-structure of the DOTS Course data bases (Master and Scratch) is as illustrated in the following diagram:



The RAMIS Descriptions supporting the above structure for the Master and Scratch versions of the Course data bases are:

<u>Data Base</u>	<u>Description Filename</u>	<u>Description Filetype</u>
Course Master	COURSE	DESC
Course Scratch	MODCOURSE	DESC

Listing of Filename = COURSE, Filetype = DESC

```

ERASE*
FILE COURSE
END
INPUT
FILE RAMASTER
1=COURSE,1,S,12,SCH,SCH,A,4,S
2=2,S,5,CDP,CDP,A,4,S
2=3,,1,DEL,DEL,A,1,S
5=CTLG,CTLG,A,10,S
5=CRS,CRS,A,16,S
5=CONV1,CONV1,I,3,S
5=LEN1,LEN1,F,4.1,S
5=CAP1,CAP1,I,3,S
5=BCAP1,BCAP1,I,3,S
5=DMD1,DMD1,I,5,S
5=BDMD1,BDMD1,I,5,S
5=OFST,OFST,I,2,S
5=PFAIL,PFAIL,F,5.3,S
5=NADIS,NADIS,F,5.3,S
5=NOSHOW,NOSHOW,F,5.3,S
5=SETB,SETB,F,5.3,S
5=BKLG,BKLG,I,4,S
5=JNO,JNO,A,4,S
5=CONV2,CONV2,I,3,S
5=LEN2,LEN2,F,4.1,S
5=CAP2,CAP2,I,3,S
5=BCAP2,BCAP2,I,3,S
5=DMD2,DMD2,I,5,S
5=BDMD2,BDMD2,I,5,S
5=CHWK2,CHWK2,I,3,S
5=CONV3,CONV3,I,3,S
5=LEN3,LEN3,F,4.1,S
5=CAP3,CAP3,I,3,S
5=BCAP3,BCAP3,I,3,S
5=DMD3,DMD3,I,5,S
5=BDMD3,BDMD3,I,5,S
5=CHWK3,CHWK3,I,3,S
5=PAOB,PAOB,I,4,S
5=AFAIL,AFAIL,F,5.3,S
5=PRTY,PRTY,I,2,S
5=CTYPE,CTYPE,A,2,S
5=PNEC,PNEC,A,4,S
5=UCAP,UCAP,I,3,S
5=UDEM,UDEM,I,3,S
5=FPRTY,FPRTY,I,2,S
5=RDTE,RDTE,I,6,S
5=HSETB,HSETB,F,5.3,S
5=TINSTR,TINSTR,F,4.1,S
5=SUIC,SUIC,A,5,S
5=CCMM,CCMM,A,10,S
2=4,,2,SIR,SIR,F,4.1,S
5=CHRS,CHRS,F,5.1,S
5=CTYP,CTYP,A,1,S
2=5,,3,ID,ID,A,9,S
5=QUAL,QUAL,A,3,S

```

Listing of Filename = MODCOURSE, Filetype = DESC

```

ERASE*
FILE MODCOURSE
END
INPUT
FILE RAMASTER
1=MODCOURSE,1,S,12,SCH,SCH,A,4,S
2=2,S,5,CDP,CDP,A,4,S
2=3,,1,DEL,DEL,A,1,S
5=CTLG,CTLG,A,10,S
5=CRS,CRS,A,16,S
5=CONV1,CONV1,I,3,S
5=LEN1,LEN1,F,4,1,S
5=CAP1,CAP1,I,3,S
5=BCAP1,BCAP1,I,3,S
5=DMD1,DMD1,I,5,S
5=BDMD1,BDMD1,I,5,S
5=OFST,OFST,I,2,S
5=PFAIL,PFAIL,F,5,3,S
5=NADIS,NADIS,F,5,3,S
5=NOSHOW,NOSHOW,F,5,3,S
5=SETB,SETB,F,5,3,S
5=BKLG,BKLG,I,4,S
5=JNO,JNO,A,4,S
5=CONV2,CONV2,I,3,S
5=LEN2,LEN2,F,4,1,S
5=CAP2,CAP2,I,3,S
5=BCAP2,BCAP2,I,3,S
5=DMD2,DMD2,I,5,S
5=BDMD2,BDMD2,I,5,S
5=CHWK2,CHWK2,I,3,S
5=CONV3,CONV3,I,3,S
5=LEN3,LEN3,F,4,1,S

```

Listing of Filename = MODCOURSE, Filetype = DESC (Continued)

5=CAP3,CAP3,I,3,\$
 5=BCAP3,BCAP3,I,3,\$
 5=DMD3,DMD3,I,5,\$
 5=BDMD3,BDMD3,I,5,\$
 5=CHWK3,CHWK3,I,3,\$
 5=PAOB,PAOB,I,4,\$
 5=AFAIL,AFAIL,F,5,3,\$
 5=PRTY,PRTY,I,2,\$
 5=CTYPE,CTYPE,A,2,\$
 5=PNEC,PNEC,A,4,\$
 5=UCAP,UCAP,I,3,\$
 5=UDEM,UDEM,I,3,\$
 5=FPRTY,FPRTY,I,2,\$
 5=RDTE,RDTE,I,6,\$
 5=HSETB,HSETB,F,5,3,\$
 5=TINSTR,TINSTR,F,4,1,\$
 5=SUIC,SUIC,A,5,\$
 5=CCMM,CCMM,A,10,\$
 2=4,,2,SIR,SIR,F,4,1,\$
 5=CHRS,CHRS,F,5,1,\$
 5=CTYP,CTYP,A,1,\$
 2=5,,3,ID,ID,A,9,\$
 5=QUAL,QUAL,A,3,\$
 5=ASN,ASN,I,1,\$
 2=6,V,1,NME,NME,A,16,,ID,MODINST,,1 2,\$
 END

TAEG REPORT NO. 29


A sample output from the RAMIS procedure RAMINDEX is shown below for the Course Master data base (COURSE). (A RAMINDEX run for the Scratch version would have been identical.)

DESCRIPTION FOR RAMIS FILE NAMED COURSE 09/18/75


LIST	FIELD NAME	ALIAS	TYPE	LENGTH	LEVEL	SEGMENT	SORT FLAG
1	SCH	SCH	A	4	1	12	S
2	CDP	CDP	A	4	2	5	S
3	DEL	DEL	A	1	3	1	
4	CTLG	CTLG	A	10	3	1	
5	CRS	CRS	A	16	3	1	
6	CONV1	CONV1	I	3	3	1	
7	LEN1	LEN1	F	4.1	3	1	
8	CAP1	CAP1	I	3	3	1	
9	BCAP1	BCAP1	I	3	3	1	
10	DMD1	DMD1	I	5	3	1	
11	BDMD1	BDMD1	I	5	3	1	
12	OFST	OFST	I	2	3	1	
13	PFAIL	PFAIL	F	5.3	3	1	
14	NADIS	NADIS	F	5.3	3	1	
15	NOSHOW	NOSHOW	F	5.3	3	1	
16	SETB	SETB	F	5.3	3	1	
17	BKLG	BKLG	I	4	3	1	
18	JNO	JNO	A	4	3	1	
19	CONV2	CONV2	I	3	3	1	
20	LEN2	LEN2	F	4.1	3	1	
21	CAP2	CAP2	I	3	3	1	
22	BCAP2	BCAP2	I	3	3	1	
23	DMD2	DMD2	I	5	3	1	
24	BDMD2	BDMD2	I	5	3	1	
25	CHWK2	CHWK2	I	3	3	1	
26	CONV3	CONV3	I	3	3	1	
27	LEN3	LEN3	F	4.1	3	1	
28	CAP3	CAP3	I	3	3	1	
29	BCAP3	BCAP3	I	3	3	1	
30	DMD3	DMD3	I	5	3	1	
31	BDMD3	BDMD3	I	5	3	1	
32	CHWK3	CHWK3	I	3	3	1	
33	PAOB	PAOB	I	4	3	1	
34	AFAIL	AFAIL	F	5.3	3	1	
35	PRTY	PRTY	I	2	3	1	
36	CTYPE	CTYPE	A	2	3	1	
37	PNEC	PNEC	A	4	3	1	
38	UCAP	UCAP	I	3	3	1	
39	UDEM	UDEM	I	3	3	1	
40	FPRTY	FPRTY	I	2	3	1	
41	RDTE	RDTE	I	6	3	1	
42	HSETB	HSETB	F	5.3	3	1	
43	TINSTR	TINSTR	F	4.1	3	1	
44	SUIC	SUIC	A	5	3	1	
45	CCMM	CCMM	A	10	3	1	
46	SIR	SIR	F	4.1	4	2	
47	CHRS	CHRS	F	5.1	4	2	
48	CTYP	CTYP	A	1	4	2	
49	ID	ID	A	9	5	3	
50	QUAL	QUAL	A	3	5	3	
51	ASN	ASN	I	1	5	3	

EXECUTIVE SEQUENCE DOCUMENTATION


For each of the three DOTS data bases (Facilities, Instructor, and Course), diagrams follow which pictorially depict the action and utility of the Executive Sequences to be provided for data maintenance. These diagrams are the same that appear in the initial portion of the DOTS User's Manual. The order of appearance of the Executive Sequences within this section parallels that of the diagrams. An index titled "Data Base Executive Sequence and Program Index" follows the initial diagrams. This Index includes an alphabetic listing of the Root Executives and programs by name, and their page location within this section.




FACILITIES DATA BASE MAINTENANCE




INSTRUCTOR DATA BASE MAINTENANCE



INSTRUCTOR DATA BASE MAINTENANCE





INSTRUCTOR DATA BASE REPORTS

FOR EACH INSTRUCTOR SELECTED, LIST ID, NAME, AND CDP NUMBERS OF EACH COURSE ASSIGNED.


OUTPUTS WHOLE INSTRUCTOR FILE LISTING BY SCHOOL: INSTRUCTOR ID, NAME, ASSIGNED COURSE CDP NUMBERS.

OUTPUTS, FOR THE SCHOOL SELECTED: INSTRUCTOR ID, NAME, AND SUM OF EACH INSTRUCTOR'S TIME EXPENDED DURING THE CURRENT WEEK.

FOR THE INSTRUCTOR SELECTED, LISTED ARE NAMES, ID, AND EACH OF THE COURSES' TIME TYPE, AND TIMES THAT HE HAS CHARGED DURING THE CURRENT WEEK.

FOR ALL SCHOOLS OF FTC, THE ROTATION DATES (MONTH/YEAR) AND THE NUMBERS OF INSTRUCTORS SCHEDULED TO ROTATE ON THOSE DATES ARE LISTED. ONLY THOSE ROTATIONS THAT WILL OCCUR IN THE NEXT 6 MONTHS ARE CONSIDERED.

ESSENTIALLY THE SAME USE AS REPORT R5, ABOVE, EXCEPT THAT THE NAME AND ID OF EACH INSTRUCTOR INVOLVED ARE INCLUDED.



COURSE DATA BASE MAINTENANCE

DATA BASE EXECUTIVE INDEX

<u>EXECUTIVE SEQUENCE</u>	<u>PAGE NO.</u>	<u>EXECUTIVE SEQUENCE</u>	<u>PAGE NO.</u>	<u>EXECUTIVE SEQUENCE</u>	<u>PAGE NO.</u>
E1	II-25	E24	II-72	E64	II-130
E2	II-27	E27	II-88	E65	II-132
E3	II-38	E30	II-90	R5	II-113
E4	II-41	E32	II-85	R6	II-115
E9	II-45	E34	II-141	W1	II-47
E15	II-31	E35	II-93	W2	II-49
E16	II-33	E36	II-42	W15	II-52
E17	II-36	E37	II-150	W16	II-54
E18	II-30	E38	II-59	W17	II-57
E20	II-60	E40	II-117	W18	II-51
E21	II-62	E41	II-121	W20	II-75
E22A.	II-96	E42	II-123	W21	II-79
E22B.	II-97	E43	II-134	W40	II-151
E22C.	II-98	E44	II-138	W41	II-155
E22D.	II-100	E50	II-147	W42	II-157
E22E.	II-101	E51	II-144	W53	II-77
E22F.	II-104	E53	II-65	W54	II-82
E22G.	II-105	E54	II-67	W55	II-84
E22R1	II-106	E55	II-64	W61	II-159
E22R2	II-108	E58	II-149	W62	II-160
E22R3	II-109	E61	II-125	W63	II-162
E22R4	II-111	E62	II-126	W64	II-164
E23	II-69	E63	II-128	W65	II-165

DATA BASE EXECUTIVE INDEX (Cont'd)

<u>PROGRAMS</u>	<u>PAGE NO.</u>
PGM5	II-168
PGM7	II-177
PGM8	II-182
PGM9B	II-196
PGM16	II-202
PGM19	II-212
PGM20	II-229
PGM22	II-235
PROMPTX . . .	II-243

ROOT EXECUTIVE: E1

DATA BASE: Facilities Master

FUNCTION: (1) Add a new Course to an existing School,/or/
(2) Add a new School and Course

The sequence described below forms a CLASS A Prompting Type Executive. The file PD1/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD1/DATA is described fully in the documentation associated with the PL/1 program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E1 Logic

The components of Executive Sequence E1 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E1	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/1 Program)
(4)	RE1	RAM	

Listing of Filename = E1, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 PD1 RE1
```

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE1, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,5,3,3,1,6,5
KEY 1,2
INCLUDE 1
FILE FACIL
END
```

Listing of Filename = PD1, Filetype = DATA

```
1* THIS IS EXECUTIVE NUMBER E1
1* FILE - FACILITIES
1* FUNCTION - ADD A NEW COURSE...
2SCH      11 4      1      1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP      21 4      1      5 4
3* ENTER COURSE CDP (CDP), A4
```

ROOT EXECUTIVE: E2

DATA BASE: Facilities Master

FUNCTION: Add a new Facility to an existing Course

The sequence described below forms a CLASS A Prompting Type Executive. The file PD2/DATA contains both the textual character strings to be used in prompting the user and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD2/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E2 Logic

The components of Executive Sequence E2 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E2	EXEC
(2)	ESUB1	EXEC
(3)	PROMPT	PLI (PL/I Program)
(4)	RE2	RAM

Listing of Filename = E2, Filetype = EXEC

```
&TYPE OFF  
EXEC ESUB1 PD2 RE2  
&EXIT
```


Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE2, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,5,3,3,1,6,5
KEY 1,2,3,4
INCLUDE 3
FILE FACIL
END
```

Listing of Filename = PD2, Filetype = DATA

```

1* THIS IS EXECUTIVE NUMBER E2
1* FILE - FACILITIES
1* FUNCTION - ADD NEW FACILITY TO AN
1*      EXISTING COURSE...
2SCH      11 4      1      1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP      21 4      1      5 4
3* ENTER COURSE CDP (CDP), A4
2BLDG     31 5      1      9 5
3* ENTER BUILDING NUMBER (BLDG), A5
2RM       41 3      1      14 3
3* ENTER ROOM NUMBER (RM), A3
2RMCAP    52 000    220.0    200.0    17 3
3* ENTER ROOM CAPACITY (RMCAP), I3
2RMTP     61 1      2      20 1
3* ENTER ROOM TYPE (RMTP), A1
3*      1 = LECTURE, 2 = LAB, 3 = BOTH
2REQHRS   73 0000.0  220.0    3000.0    1 21 6
3* ENTER REQUIRED HOURS (REQHRS), F6.1
2AVHRS    82 0      220.0    3000.0    27 5
3* ENTER AVAILABLE HOURS (AVHRS), I5

```

ROOT EXECUTIVE: E18

DATA BASE: Facilities Master

FUNCTION: Change an existing Field

This single executive serves to force entry to the SCAN mode of the RAMIS data management system. After SCAN mode has been successfully entered, the User may direct change of existing field(s) interactively through his terminal.

Terminal entry requirements of the RAMIS SCAN mode are fully covered in the NCSS vendor's documentation.

The DOTS User's Manual lists the data field names and identification numbers as appropriate for the Facilities Master Data Base. This list will not be repeated in this document.

Listing of Executive E18 (SCAN Mode Entry)

&TYPE OFF
&STACK KT
&STACK SCAN
&STACK FILE FACIL
ATTACH RAMIS ALL BR
&STACK RT
RAMIS
DETACH RAMIS BR
&EXIT

ROOT EXECUTIVE: E15

DATA BASE: Facilities Master

FUNCTION: Delete a Course

The components of Executive Sequence E15 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E15	EXEC
(2)	X15	RUNPROC

Listing of Filename = E15, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER E15
&PRI * FILE - FACILITIES
&PRI * FUNCTION - DELETE A COURSE
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &GOTO -OUT
&SAV1 = &1
-LP2 &PRI *
&PRI * ENTER COURSE CDP (CDP), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK2
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP2
-CK2 &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC X15 &SAV1 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```


Listing of Filename = X15, Filetype = RUNPROC

```
DELETE  
FILE RAMEXEC  
1=OUT=X15.S  
END  
CATALOG X15  
DELETE  
FORM 4,X4,4  
SET 2  
FILE FACIL  
&1  
END  
END CATALOG
```

ROOT EXECUTIVE: E16

DATA BASE: Facilities Master

FUNCTION: Delete a Facility

The components of Executive Sequence E16 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E16	EXEC
(2)	X16	RUNPROC

Listing of Filename = E16, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER E16
&PRI * FILE - FACILITIES
&PRI * FUNCTION - DELETE A FACILITY FROM A COURSE
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &GOTO -OUT
&SAV1 = &1
-LP2 &PRI *
&PRI * ENTER COURSE CDP (CDP), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK2
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP2
-CK2 &IF &1 EQ OUT &GOTO -OUT
&SAV2 = &1
-LP3 &PRI *
&PRI * ENTER BUILDING NO (BLDG), A5
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK3
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP3
-CK3 &IF &1 EQ OUT &GOTO -OUT
&SAV3 = &1
-LP4 &PRI *
&PRI * ENTER ROOM NO (RM), A3
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK4
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP4
-CK4 &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC X16 &SAV1 &SAV2 &SAV3 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = X16, Filetype = RUNPROC

```
DELETE  
FILE RAMEXEC  
1=OUT=X16,S  
END  
CATALOG X16  
DELETE  
FORM 4,X4,4,X4,5,X3,3  
SET 3  
FILE FACIL  
&1  
END  
END CATALOG
```


ROOT EXECUTIVE: E17

DATA BASE: Facilities Master

FUNCTION: Delete an entire School

The components of Executive Sequence E17 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E17	EXEC
(2)	X17	RUNPROC

Listing of Filename = E17, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER E17
&PRI * FILE - FACILITIES
&PRI * FUNCTION - DELETE A SCHOOL
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC X17 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = X17, Filetype = RUNPROC

```
DELETE  
FILE RAMEXEC  
1=OUT=X17.S  
END  
CATALOG X17  
DELETE  
FORM 4  
SET 1  
FILE FACIL  
&1  
END  
END CATALOG
```

ROOT EXECUTIVE: E3

DATA BASE: Facilities Master

FUNCTION: Load the Facilities Master data base from card input

This Executive Sequence is used to create the Facilities Master data base in its entirety.

This sequence commences operation by causing the erase of any existing copy of the Facilities Master data base

User interface with this Executive Sequence is covered in the DOTS User's Manual.

The format of the card input data set used as an input to Executive Sequence E3 is illustrated in the diagram of this section entitled "Facilities Data Base Load Card Format."

Executive Sequence E3 Logic

The components of Executive Sequence E3 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E3	EXEC
(2)	RE3	RAM

Listing of Filename = E3, Filetype = EXEC

```

&TYPE OFF
STATE E3 DATA
&IF &INDEX0 NE 0 &GOTO -ERR1
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE3 RAM
DETACH RAMIS BR
ERASE E3 DATA
&EXIT
-ERR1 &PRINT NO FACILITIES LOAD CARDS FOUND - FUNCTION TERMINATING

```

Listing of Filename = RE3, Filetype = RAM

ERASE
FILE FACIL
END
INPUT
READ E3 DATA
RECORD 80
SET 1
FORM 4,4,5,3,3,1,6,5
FILE FACIL
END

80-Column Card Punch Layout

[illegible]

SCH		COP		BLDG		RM		RM CAP		REOHS		AVHRS																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																											
1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34	35	36	37	38	39	40	41	42	43	44	45	46	47	48	49	50	51	52	53	54	55	56	57	58	59	60	61	62	63	64	65	66	67	68	69	70	71	72	73	74	75	76	77	78	79	80	81	82	83	84	85	86	87	88	89	90	91	92	93	94	95	96	97	98	99	100																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																																				

935-1115-0

ROOT EXECUTIVE: E4

DATA BASE: Facilities Master

FUNCTION: Dump Facilities Master data base

This Executive sequence produces a formatted dump to the User's terminal of all of the records of the Facilities Master data base.

Executive Sequence E4 Logic

The components of Executive Sequence E4 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E4	EXEC
(2)	RE4	RAM

Listing of Filename = E4, Filetype = EXEC

```
&TYPE OFF
&STACK KT
ATTACH RAMIS ALL BRIEF
&STACK RT
EXEC RAMISIN RE4 RAM
DETACH RAMIS BRIEF
&EXIT
```

Listing of Filename = RE4, Filetype = RAM

```
TABLE
FILE FACIL
PRINT BLDG AND RM AND RMCAP AND RMTP AND REQHRS AND AVHRS
BY SCH BY CDP
ON SCH PAGE-BREAK
END
```

ROOT EXECUTIVE: E36

DATA BASE: Facilities Master
Facilities Scratch

FUNCTION: Recreate the Scratch data base using the records from
one User-selected school in the Master data base

The first step in the recreation of the Scratch data base is the erase of the existing Scratch copy.

After being prompted, the User must supply the 4-character name of the school of interest.

The Master data base is then dumped into card-image format onto a temporary file, selecting only those records associated with the school chosen by the User. The temporary file is then used as input to recreate the Scratch data base in its entirety.

At the successful conclusion of this Executive Sequence the contents of the Master data base are unchanged. The new Scratch data base will contain only the records associated with the selected school.

Executive Sequence E36 Logic

The components of Executive Sequence E36 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E36	EXEC
(2)	E56	EXEC
(3)	X56	RUNPROC
(4)	E6	EXEC
(5)	RE6	RAM

Listing of Filename = E36, Filetype = EXEC

&TYPE OFF
EXEC E56
EXEC E6

Listing of Filename = E56, Filetype = EXEC

```

&TYPE OFF
&PRINT * FILE FACILITIES
&PRINT * FUNCTION - SELECT SCHOOL FOR MODEL INPUT
&PRINT * ENTER OUT FOR PREMATURE EXIT
-LP1 &PRI *
&PRINT * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &EXIT
FILEDEF RAMUTIL1 DSK FACIL DUMP LR 80 RE FB BL 800
&STACK KT
&STACK EXEC X56 &1
&STACK FIN
ATTACH RAMIS ALL BR
FILEDEF 6 MSG KILL
RAMIS
DETACH RAMIS BR
&STACK RT
FILEDEF RAMUTIL1 CLEAR
FILEDEF 6 CONO
&STACK KT
&STACK L /D=/
&STACK Q
EDIT MSG KILL
&PRI * &1 SCHOOL DUMPED TO DISK FILE
    
```

Listing of Filename = X56, Filetype = RUNPROC

```

DELETE
FILE RAMEXEC
1=OUT=X56.
END
CATALOG X56
DUMP
FILE FACIL
PRINT AVHRS AND SAVE
IF SCH IS &1
END
END CATALOG
    
```


Listing of Filename = E6, Filetype = EXEC

&TYPE OFF
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN RE6 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
&EXIT

Listing of Filename = RE6, Filetype = RAM

ERASE
FILE MODFACIL
END
INPUT
READ FACIL DUMP
RECORD 80
FORM 4,4,5,3,3,1,6,5
SET 1
SEARCH FORWARD
FILE MODFACIL
END

ROOT EXECUTIVE: E9

DATA BASE: Facilities Master
Facilities Scratch

FUNCTION: Recreate the Scratch data base using the records
from all Schools in the Master data base

The first step in the recreation of the Scratch data base is the erase of the existing Scratch copy.

The Master is then dumped into card-image format onto a temporary dataset. This file is then used as input to recreate the Scratch data base in its entirety.

Executive Sequence E9 Logic

The components of Executive Sequence E9 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E9	EXEC
(2)	E5	EXEC
(3)	RE5	RAM
(4)	E6	EXEC
(5)	RE6	RAM

Listing of Filename = E9, Filetype = EXEC

```
&TYPE OFF
EXEC E5
EXEC E6
&EXIT
```

Listing of Filename = E5, Filetype = EXEC

```
&TYPE OFF
FILEDEF RAMUTIL1 DSK FACIL DUMP LR 80 RE FB BL 800
&STACK KT
ATTACH RAMIS ALL BRIEF
EXEC RAMISIN RES RAM
DETACH RAMIS BRIEF
FILEDEF RAMUTIL1 CLEAR
&STACK RT
&PRINT ALL SCHOOLS DUMPED FROM FACILITIES FILE
```

Listing of Filename = RE5, Filetype = RAM

```
DUMP
FILE FACIL
PRINT AVHRS AND SAVE
END
```

Listing of Filename = E6, Filetype = EXEC

```
&TYPE OFF
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN RE6 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
&EXIT
```

Listing of Filename = RE6, Filetype = RAM

```
ERASE
FILE MODFACIL
END
INPUT
READ FACIL DUMP
RECORD 80
FORM 4,4,5,3,3,1,6,5
SET 1
SEARCH FORWARD
FILE MODFACIL
END
```

ROOT EXECUTIVE: W1

DATA BASE: Facilities Scratch

FUNCTION: (1) Add a new Course to an existing School, /or/
(2) Add a new School and Course

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD1/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD1/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W1 Logic

The components of Executive Sequence W1 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W1	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RW1	RAM	

Listing of Filename = W1, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 WPD1 RW1
```


Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RW1, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,5,3,3,1,6,5
KEY 1,2
INCLUDE 1
FILE MODFACTL
END
```

Listing of Filename = WPD1, Filetype = DATA

```
1* THIS IS EXECUTIVE NUMBER W1
1* FILE - FACILITIES SCRATCH DATA BASE
1* FUNCTION - ADD A NEW COURSE...
2SCH      11 4      1      1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP      21 4      1      5 4
3* ENTER COURSE CDP (CDP), A4
```

ROOT EXECUTIVE: W2

DATA BASE: Facilities Scratch

FUNCTION: Add a new Facility to an existing Course

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD2/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD2/DATA is described fully in the documentation associated with the PL/1 program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W2 Logic

The components of Executive Sequence W2 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W2	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/1 Program)
(4)	RW2	RAM	

Listing of Filename = W2, Filetype = EXEC

```
&TYPE OFF  
EXEC ESUB1 WPD2 RW2  
&EXIT
```

Listing of Filename = ESUB1, Filetype = EXEC

```

&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT

```

Listing of Filename = RW2, Filetype = RAM

```

REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,5,3,3,1,6,5
KEY 1,2,3,4
INCLUDE 3
FILE MODFACIL
END

```

Listing of Filename = WPD2, Filetype = DATA

```

1* THIS IS EXECUTIVE NUMBER W2
1* FILE - FACILITIES SCRATCH DATA BASE
1* FUNCTION - ADD NEW FACILITY TO AN
1*      EXISTING COURSE...
2SCH      11 4      1      1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP      21 4      1      5 4
3* ENTER COURSE CDP (CDP), A4
2BLDG      31 5      1      9 5
3* ENTER BUILDING NUMBER (BLDG), A5
2RM      41 3      1      14 3
3* ENTER ROOM NUMBER (RM), A3
2RMCAP      52      000      220.0      200.0      17 3
3* ENTER ROOM CAPACITY (RMCAP), I3
2RMTP      61 1      2      20 1
3* ENTER ROOM TYPE (RMTP), A1
3*      1 = LECTURE, 2 = LAB, 3 = BOTH
2REQHRS      73      0000.0      220.0      3000.0      1 21 6
3* ENTER REQUIRED HOURS (REQHRS), F6.1
2AVHRS      82      0      220.0      3000.0      27 5
3* ENTER AVAILABLE HOURS (AVHRS), I5

```

ROOT EXECUTIVE: W18

DATA BASE: Facilities Scratch

FUNCTION: Change an existing Field

This single executive serves to force entry to the SCAN mode of the RAMIS data management system. After SCAN mode has been successfully entered, the User may direct change of existing field(s) interactively through his terminal.

Terminal entry requirements of the RAMIS SCAN mode are fully covered in the NCSS vendor's documentation.

The DOTS User's Manual lists the data field names and identification numbers as appropriate for the Facilities Scratch data base. This list will not be repeated in this document.

Listing of Executive W18 (SCAN Mode Entry)

&TYPE OFF
&STACK KT
&STACK SCAN
&STACK FILE MODFACIL
ATTACH RAMIS ALL BR
&STACK RT
RAMIS
DETACH RAMIS BR

ROOT EXECUTIVE: W15

DATA BASE: Facilities Scratch

FUNCTION: Delete a Course

The components of Executive Sequence W15 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	W15	EXEC
(2)	WX15	RUNPROC

Listing of Filename = W15, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER W15
&PRI * FILE - MODFACIL
&PRI * FUNCTION - DELETE A COURSE
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &GOTO -OUT
&SAV1 = &1
-LP2 &PRI *
&PRI * ENTER COURSE CDP (CDP), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK2
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP2
-CK2 &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC WX15 &SAV1 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = WX15, Filetype = RUNPROC

```
DELETE  
FILE RAMEXEC  
1=OUT=WX15,S  
END  
CATALOG WX15  
DELETE  
FORM 4,X4,4  
SET 2  
FILE MODFACIL  
61  
END  
END CATALOG
```

ROOT EXECUTIVE: W16

DATA BASE: Facilities Scratch

FUNCTION: Delete a Facility

The components of Executive Sequence W16 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	W16	EXEC
(2)	WX16	RUNPROC

Listing of Filename = W16, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER W16
&PRI * FILE - MODFACIL
&PRI * FUNCTION - DELETE A FACILITY FROM A COURSE
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &GOTO -OUT
&SAV1 = &1
-LP2 &PRI *
&PRI * ENTER COURSE CDP (CDP), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK2
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP2
-CK2 &IF &1 EQ OUT &GOTO -OUT
&SAV2 = &1
-LP3 &PRI *
&PRI * ENTER BUILDING NO (BLDG), A5
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK3
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP3
-CK3 &IF &1 EQ OUT &GOTO -OUT
&SAV3 = &1
-LP4 &PRI *
&PRI * ENTER ROOM NO (RM), A3
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK4
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP4
-CK4 &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC WX16 &SAV1 &SAV2 &SAV3 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```


Listing of Filename = WX16, Filetype = RUNPROC

```
DELETE
FILE RAMEXEC
1=OUT=WX16.S
END
CATALOG WX16
DELETE
FORM 4,X4,4,X4,5,X3,3
SET 3
FILE MODFACIL
&1
END
END CATALOG
```

ROOT EXECUTIVE: W17

DATA BASE: Facilities Scratch

FUNCTION: Delete an entire School

The components of Executive Sequence W17 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	W17	EXEC
(2)	WX17	RUNPROC

Listing of Filename = W17, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER W17
&PRI * FILE - MODFACIL
&PRI * FUNCTION - DELETE A SCHOOL
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC WX17 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = WX17, Filetype = RUNPROC

```
DELETE  
FILE RAMEXEC  
1=OUT=WX17.S  
END  
CATALOG WX17  
DELETE  
FORM 4  
SET 1  
FILE MODFACIL  
&1  
END  
END CATALOG
```

ROOT EXECUTIVE: E38

DATA BASE: Facilities Scratch

FUNCTION: Dump Scratch data base to User's terminal

This Executive sequence produces a formatted dump to the User's terminal of all of the records of the Facilities Scratch data base.

Executive Sequence E38 Logic

The components of Executive Sequence E38 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E38	EXEC
(2)	RE38	RAM

Listing of Filename = E38, Filetype = EXEC

```
&TYPE OFF
&STACK KT
ATTACH RAMIS ALL BRIEF
&STACK RT
EXEC RAMISIN RE38 RAM
DETACH RAMIS BRIEF
&EXIT
```

Listing of Filename = RE38, Filetype = RAM

```
TABLE
FILE MODFACIL
PRINT BLDG AND RM AND RMCAP AND RMTP AND REQHRS AND AVHRS
BY SCH BY CDP
ON SCH SKIP-LINE
END
```


ROOT EXECUTIVE: E20

DATA BASE: Instructor Master

FUNCTION: Add a new Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file PD20/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD20/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E20 Logic

The components of Executive Sequence E20 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E20	EXEC
(2)	ESUB1	EXEC
(3)	PROMPT	PLI (PL/I Program)
(4)	RE20	RAM

Listing of Filename = E20, Filetype = EXEC

&TYPE OFF
EXEC ESUB1 PD20 RE20

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE20, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 9,16,2,5,4,4,4,4,4
INCLUDE 1
FILE INST
END
```

Listing of Filename = PD20, Filetype = DATA

```
OACTION 1 1 0      ** SPECIAL PROCESSING CARD FOR INSTRUCTOR FILE **
1*
1* FUNCTION - ADD A NEW INSTRUCTOR
1*
2ID          11 9              1              1 9
3* ENTER INSTRUCTOR SOC SEC # (ID), A9
2NME          2116              1              1016
3* ENTER INSTRUCTOR SURNAME (NME), A16
2IN           31 2              1              26 2
3* ENTER INSTRUCTOR INITIALS (IN), A2
2RATE          41 5              2              28 5
3* ENTER RATE/RATING (RATE), A5
2SCH           51 4              1              33 4
3* ENTER SCHOOL (SCH), A4
2REP           61 4              2              37 4
3* ENTER REPORTING DATE (REP), A4, YYMM
2ROT           71 4              2              41 4
3* ENTER ROTATION DATE (ROT), A4, YYMM
2PNEC          81 4              2              45 4
3* ENTER PRIMARY NEC (PNEC), A4
2SNEC          91 4              2              49 4
3* ENTER SECONDARY NEC (SNEC), A4
```

ROOT EXECUTIVE: E21

DATA BASE: Instructor Master

FUNCTION: Add a new Course to an existing Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file PD21/DATA contains both the textual character strings to be used in prompting the user and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD21/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E21 Logic

The components of Executive Sequence E21 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E21	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RE21	RAM	

Listing of Filename = E21, Filetype = EXEC

```

&TYPE OFF
EXEC ESUB1 PD21 RE21
&EXIT

```

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE21, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 9,16,X27,4,X17,6,3,C3,C3,C3,C3,C3,C3
FORM C3,C3,C3,C3,C3,C3,C3,4,5,6
ORDER 1,2,10,13,14,14,14,14,14,14,14
ORDER 14,14,14,14,14,14,14,15,16,17
KEY 1,2,10,14
INCLUDE 10
FILE INST
END
```

Listing of Filename = PD21, Filetype = DATA

```
0ACTION 1 1 0      ** SPECIAL PROCESSING CARD FOR INSTRUCTOR FILE **
1* FUNCTION - ASSIGN A NEW COURSE
2ID          11 9          1          1 9
3* ENTER INSTRUCTOR SOC SEC # (ID), A9
2NME          2116          1          1016
3* ENTER INSTRUCTOR SURNAME (NME), A16
2CDP          101 4 XXXX          2          53 4
3* ENTER ASSIGNED COURSE CDP (CDP), A4
```


ROOT EXECUTIVE: E55

DATA BASE: Instructor Master

FUNCTION: Change an existing Field

This single executive serves to force entry to the SCAN mode of the RAMIS data management system. After SCAN mode has been successfully entered, the User may direct change of existing field(s) interactively through his terminal.

Terminal entry requirements of the RAMIS SCAN mode are fully covered in the NCSS vendor's documentation.

The DOTS User's Manual lists the data field names and identification numbers as appropriate for the Instructor Master Data Base. This list will not be repeated in this document.

Listing of Executive E55 (SCAN Mode Entry)

```
&TYPE OFF
&STACK SCAN
&STACK FILE INST
ATTACH RAMIS ALL BR
RAMIS
DETACH RAMIS BR
&EXIT
```

ROOT EXECUTIVE: E53

DATA BASE: Instructor Master

FUNCTION: Delete a Course from an Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file PD53/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD53/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E53 Logic

The components of Executive Sequence E53 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E53	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RE53	RAM	

Listing of Filename = E53, Filetype = EXEC

```
&TYPE OFF  
EXEC ESUB1 PD53 RE53  
&EXIT
```

Listing of Filename = ESUB1, Filetype = EXEC

```

&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT

```

Listing of Filename = RE53, Filetype = RAM

```

DELETE
READ TRANS FILE
RECORD 250
FORM 9,16,2,X5,4,X16,4
ORDER 1,2,3,5,10
SET 10
FILE INST
END

```

Listing of Filename = PD53, Filetype = DATA

```

0ACTION 1 1 0      ** SPECIAL PROCESSING CARD FOR INSTRUCTOR FILE **
1* THIS IS EXECUTIVE NUMBER E53
1* FILE - INSTRUCTOR
1* FUNCTION - DELETE A COURSE FROM AN
1*      INSTRUCTOR THAT ALREADY EXISTS
1*      IN THE FILE...
2ID      11 9      1      1 9
3* ENTER INSTRUCTOR SOC SEC # (ID), A9
2NME      2116      1      1016
3* ENTER INSTRUCTOR SURNAME (NME), A16
2IN      31 2      1      26 2
3* ENTER INSTRUCTOR INITIALS (IN), A2
2SCH      51 4      1      33 4
3* ENTER SCHOOL (SCH), A4
2CDP      101 4 XXXX      1      53 4
3* ENTER ASSIGNED COURSE CDP (CDP), A4

```

ROOT EXECUTIVE: E54

DATA BASE: Instructor Master

FUNCTION: Delete an Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file PD54/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD54/DATA is described fully in the documentation associated with the PL/1 program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E54 Logic

The components of Executive Sequence E54 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E54	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/1 Program)
(4)	RE54	RAM	

Listing of Filename = E54, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 PD54 RE54
&EXIT
```


Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE54, Filetype = RAM

```
DELETE
READ TRANS FILE
RECORD 250
FORM 9,16,2
SET 1
FILE INST
END
```

Listing of Filename = PD54, Filetype = DATA

```
0ACTION 1 1 0      ** SPECIAL PROCESSING CARD FOR INSTRUCTOR FILE **
1* THIS IS EXECUTIVE NUMBER E54
1* FILE - INSTRUCTOR
1* FUNCTION - DELETE AN INSTRUCTOR
1*      THAT ALREADY EXISTS
1*      IN THE FILE...
2ID          11 9              1              1 9
3* ENTER INSTRUCTOR SOC SEC # (ID), A9
2NME          2116              1              1016
3* ENTER INSTRUCTOR SURNAME (NME), A16
2IN           31 2              1              26 2
3* ENTER INSTRUCTOR INITIALS (IN), A2
2SCH          51 4              1              33 4
3* ENTER SCHOOL (SCH), A4
```

ROOT EXECUTIVE: E23

DATA BASE: Instructor Master

FUNCTION: Load the Instructor Master data base from card input

The Instructor Master data base is loaded from scratch by using the following Executive Sequences:

<u>Executive Sequence</u>	<u>Input Card Format</u>	<u>Input Data Contents</u>
E23	Instructor File, TYPE -1- Input Card	Instructor Fixed Data
E24	Instructor File, TYPE -2- Input Card	Instructor Assignment Data

In the normal loading sequence, Executive E23 must have been successfully executed before attempting Executive E24 operations.

The format of the card input data set associated with Executive Sequence E23 is illustrated in the diagram following entitled "Instructor Data Base Type -1- Input Card Format".

Executive Sequence E23 Logic

The components of Executive Sequence E23 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E23	EXEC
(2)	RE23	RAM

Listing of Filename = E23, Filetype = EXEC

```

&TYPE OFF
STATE E23 DATA
&IF &INDEX0 NE 0 &GOTO -NODATA
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE23 RAM
DETACH RAMIS BR
ERASE E23 DATA
&EXIT
-NODATA &PRINT NO TYPE1 CARDS PROVIDED -- FUNCTION TERMINATING

```

Listing of Filename = RE23, Filetype = RAM

```
ERASE  
FILE INST  
END  
REVISE  
READ E23 DATA  
RECORD 80  
FORM 9,16,2,5,4,4,4,4,4  
KEY 1  
INCLUDE 1  
FILE INST  
END
```

II-71

[illegible]

ROOT EXECUTIVE: E24

DATA BASE: Instructor Master

FUNCTION: Load the Instructor Master data base from card input

The Instructor Master data base is loaded from scratch by using the following Executive Sequences:

<u>Executive Sequence</u>	<u>Input Card Format</u>	<u>Input Data Contents</u>
E23	Instructor File, TYPE -1- Input Card	Instructor Fixed Data
E24	Instructor File, TYPE -2- Input Card	Instructor Assignment Data

In the normal loading sequence, Executive E23 must have been successfully executed before attempting Executive E24 operations.

The format of the card input data set associated with Executive Sequence E24 is illustrated in the diagram following entitled "Instructor Data Base TYPE -2- Input Card Format".

Executive Sequence E24 Logic

The components of Executive Sequence E24 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E24	EXEC	
(2)	PGM9B	PLI	(PL/I Program)
(3)	RE24	RAM	

Listing of Filename = E24, Filetype = EXEC

```
&TYPE OFF
STATE E24 DATA
&IF &INDEX0 NE 0 &GOTO -NOCDS
FILEDEF CARDS DSK E24 DATA
FILEDEF TRANS DSK TYPE2 DATA LR 250 RE F
LOAD PGM98 (CLEAR LIBE) PL1LIB
START (BRIEF)
FILEDEF CARDS CLEAR
FILEDEF TRANS CLEAR
ERASE E24 DATA
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE24 RAM
DETACH RAMIS BR
&EXIT
-NOCDS &PRINT NO TYPE2 CARDS FOUND -- FUNCTION TERMINATING
&EXIT
```

Listing of Filename = RE24, Filetype = RAM

```
REVISE
READ TYPE2 DATA
RECORD 250
FORM 9,16,2,4,4,16,3,C3,C3,C3,C3,C3,C3,C3,C3,C3,C3,C3,C3,4,5,6
ORDER 1,2,3,5,10,11,14,14,14,14,14,14,14,14,14,14,14,14,15,16,17
KEY 1,2,3,5,10,14
INCLUDE 10
FILE INST
END
```

INSTRUCTOR (COURSE) DATA BASE TYPE -2- INPUT CARD FORMAT

80 Column Card Punch Layout

INSTRUCTOR FILE										CARD PUNCH PRINT										VERIFY										DATE AND TIME									
TYPE 2 CARD										WRITTEN AS										PUNCHED AS																			



ID	NAME	IN	SCH	CDP	TTL	YR	PR	QUAL	EUR	CHRS
1										
2										
3										
4										
5										
6										
7										
8										
9										
10										
11										
12										
13										
14										
15										
16										
17										
18										
19										
20										
21										
22										
23										
24										
25										
26										
27										
28										
29										
30										
31										
32										
33										
34										
35										
36										
37										
38										
39										
40										
41										
42										
43										
44										
45										
46										
47										
48										
49										
50										
51										
52										
53										
54										
55										
56										
57										
58										
59										
60										
61										
62										
63										
64										
65										
66										
67										
68										
69										
70										
71										
72										
73										
74										
75										
76										
77										
78										
79										
80										

ROOT EXECUTIVE: W20

DATA BASE: Instructor Scratch

FUNCTION: Add a new Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD20/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD20/DATA is described fully in the documentation associated with the PL/I program, called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W20 Logic

The components of Executive Sequence W20 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W20	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RW20	RAM	

Listing of Filename = W20, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 WPD20 RW20
```


TAEG REPORT NO. 29

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RW20, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 9,16,2,5,4,4,4,4,4
INCLUDE 1
FILE MODINST
END
```

Listing of Filename = WPD20, Filetype = DATA

```
0ACTION 1 1 0      ** SPECIAL PROCESSING CARD FOR INSTRUCTOR FILE *
1* THIS IS EXECUTIVE NUMBER W20
1* FILE - INSTRUCTOR SCRATCH DATA BASE
1* FUNCTION - ADD A NEW INSTRUCTOR PLUS
1*      INSTRUCTOR FIXED DATA...
2ID      11 9      1      1 9
3* ENTER INSTRUCTOR SOC SEC # (ID), A9
2NME      2116      1      1016
3* ENTER INSTRUCTOR SURNAME (NME), A16
2IN      31 2      1      26 2
3* ENTER INSTRUCTOR INITIALS (IN), A2
2RATE      41 5      2      28 5
3* ENTER RATE/RATING (RATE), A5
2SCH      51 4      1      33 4
3* ENTER SCHOOL (SCH), A4
2REP      61 4      2      37 4
3* ENTER REPORTING DATE (REP), A4, YYMM
2ROT      71 4      2      41 4
3* ENTER ROTATION DATE (ROT), A4, YYMM
2PNEC      81 4      2      45 4
3* ENTER PRIMARY NEC (PNEC), A4
2SNEC      91 4      2      49 4
3* ENTER SECONDARY NEC (SNEC), A4
```

ROOT EXECUTIVE: W53

DATA BASE: Instructor Scratch

FUNCTION: Delete a Course from an Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD53/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD53/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W53 Logic

The components of Executive Sequence W53 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W53	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RW53	RAM	

Listing of Filename = W53, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 WPD53 RW53
&EXIT
```

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RW53, Filetype = RAM

```
DELETE
READ TRANS FILE
RECORD 250
FORM 9,16,2,X5,4,X16,4
ORDER 1,2,3,5,10
SET 10
FILE MODINST
END
```

Listing of Filename = WPD53, Filetype = DATA

```
0ACTION 1 1 0      ** SPECIAL PROCESSING CARD FOR INSTRUCTOR FILE **
1* THIS IS EXECUTIVE NUMBER W53
1* FILE - INSTRUCTOR SCRATCH DATA BASE
1* FUNCTION - DELETE A COURSE FROM AN
1*      INSTRUCTOR THAT ALREADY EXISTS
1*      IN THE FILE...
2ID      11 9      1      1 9
3* ENTER INSTRUCTOR SOC SEC # (ID), A9
2NME      2116      1      1016
3* ENTER INSTRUCTOR SURNAME (NME), A16
2IN      31 2      1      26 2
3* ENTER INSTRUCTOR INITIALS (IN), A2
2SCH      51 4      1      33 4
3* ENTER SCHOOL (SCH), A4
2CDP      101 4 XXXX      1      53 4
3* ENTER ASSIGNED COURSE CDP (CDP), A4
```

ROOT EXECUTIVE: W21

DATA BASE: Instructor Scratch

FUNCTION: Add a new Course to an existing Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD21/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD21/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W21 Logic

The components of Executive Sequence W21 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W21	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RW21	RAM	

Listing of Filename = W21, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 WPD21 RW21
&EXIT
```


Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RW21, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 9,16,2,X5,4,X16,4,16,1,6,3,C3,C3,C3,C3,C3,C3
FORM C3,C3,C3,C3,C3,C3,C3,4,5,6
ORDER 1,2,3,5,10,11,12,13,14,14,14,14,14,14,14
ORDER 14,14,14,14,14,14,14,15,16,17
KEY 1,2,3,5,10,14
INCLUDE 10
FILE MODINST
END
```

Listing of Filename = WPD21, Filetype = DATA

```

0ACTION 1 1 0      ** SPECIAL PROCESSING CARD FOR INSTRUCTOR FILE **
1* THIS IS EXECUTIVE NUMBER W21
1* FILE - INSTRUCTOR SCRATCH DATA BASE
1* FUNCTION - ASSIGN A NEW COURSE TO AN
  *      INSTRUCTOR THAT ALREADY EXISTS
1*      IN THE FILE...
2ID      11 9      1      1 9
3* ENTER INSTRUCTOR SOC SEC # (ID), A9
2NME      2116      1      1016
3* ENTER INSTRUCTOR SURNAME (NME), A16
2IN      31 2      1      26 2
3* ENTER INSTRUCTOR INITIALS (IN), A2
2SCH      51 4      1      33 4
3* ENTER SCHOOL (SCH), A4
2CDP      101 4 XXXX 2      53 4
3* ENTER ASSIGNED COURSE CDP (CDP), A4
2TTL      11116     2      5716
3* ENTER COURSE TITLE (TTL), A16
2ONB      121 1 1   2      73 1
3* ENTER ONBOARD FLAG (ONB), A1
1 = YES, 2 = NO

```

ROOT EXECUTIVE: W54

DATA BASE: Instructor Scratch

FUNCTION: Delete an Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD54/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD54/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W54 Logic

The components of Executive Sequence W54 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W54	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RW54	RAM	

Listing of Filename = W54, Filetype = EXEC

```
&TYPE OFF  
EXEC ESUB1 WPD54 RW54  
&EXIT
```

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RW54, Filetype = RAM

```
DELETE
READ TRANS FILE
RECORD 250
FORM 9,16,2
SET 1
FILE MODINST
END
```

Listing of Filename = WPD54, Filetype = DATA

```
0ACTION 1 1 0      ** SPECIAL PROCESSING CARD FOR INSTRUCTOR FILE **
1* THIS IS EXECUTIVE NUMBER W54
1* FILE - INSTRUCTOR SCRATCH DATA BASE
1* FUNCTION - DELETE AN INSTRUCTOR
1*      THAT ALREADY EXISTS
1*      IN THE FILE...
2ID      11 9      1      1 9
3* ENTER INSTRUCTOR SOC SEC # (ID), A9
2NME      2116      1      1016
3* ENTER INSTRUCTOR SURNAME (NME), A16
2IN      31 2      1      26 2
3* ENTER INSTRUCTOR INITIALS (IN), A2
2SCH      51 4      1      33 4
3* ENTER SCHOOL (SCH), A4
```


ROOT EXECUTIVE: W55

DATA BASE: Instructor Scratch

FUNCTION: Change an existing Field

This single executive serves to force entry to the SCAN mode of the RAMIS data management system. After SCAN mode has been successfully entered, the user may direct change of existing field(s) interactively through his terminal.

Terminal entry requirements of the RAMIS SCAN mode are fully covered in the NCSS vendor's documentation.

The DOTS User's Manual lists the data field names and identification numbers as appropriate for the Instructor Scratch Data Base. This list will not be repeated in this document.

Listing of Executive W55 (SCAN Mode Entry)

```
&TYPE OFF
&STACK KT
&STACK SCAN
&STACK FILE MODINST
ATTACH RAMIS ALL BR
&STACK RT
RAMIS
DETACH RAMIS BR
&EXIT
```

ROOT EXECUTIVE: E32

DATA BASE: Instructor Master
Instructor Scratch

FUNCTION: Recreate the Scratch data base using the records from
one User-selected school in the Master data base

The first step in the recreation of the Scratch data base is the erase of the existing Scratch copy.

After being prompted, the User must supply the 4-character name of the school of interest.

The Master data base is then dumped into card-image format onto a temporary file, selecting only those records associated with the school chosen by the User. The temporary file is then used as input to recreate the Scratch data base in its entirety.

At the successful conclusion of this Executive Sequence the contents of the Master data base are unchanged. The new Scratch data base will contain only the records associated with the selected school.

Executive Sequence E32 Logic

The components of Executive Sequence E32 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E32	EXEC	
(2)	E57	EXEC	
(3)	X57	RUNPROC	
(4)	E29	EXEC	
(5)	PGM7	PLI	(PL/I Program)
(6)	RE29	RAM	

Listing of Filename = E32, Filetype = EXEC

```
&TYPE OFF
EXEC E57
EXEC E29
```

Listing of Filename = E57, Filetype = EXEC

```
&TYPE OFF
&PRINT * FILE - INSTRUCTOR
&PRINT * FUNCTION - SELECT INSTRUCTORS BY SCHOOL
&PRINT * ENTER OUT FOR PREMATURE EXIT
-LP1 &PRINT *
&PRINT * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &EXIT
FILEDEF RAMUTIL1 DSK INST DUMP LR 80 RE FB BL 800
&STACK KT
&STACK EXEC X57 &1
&STACK FIN
ATTACH RAMIS ALL BR
FILEDEF 6 MSG KILL
EXEC RAMIS
DETACH RAMIS BR
&STACK RT
FILEDEF RAMUTIL1 CLEAR
FILEDEF 6 CONO
&STACK KT
&STACK L /D=/
&STACK Q
EDIT MSG KILL
&PRI &1 SCHOOL DUMPED TO DISK FILE
&EXIT
-ERR1 &PRINT *** INVALID ENTRY -- FUNCTION TERMINATING
```

Listing of Filename = X57, Filetype = RUNPROC

```
DELETE
FILE RAMEXEC
1=OUT=X57,$
END
CATALOG X57
DUMP
FILE INST
PRINT YTD AND SAVE
IF SCH IS &1
END
END CATALOG
```

Listing of Filename = E29, Filetype = EXEC

```
&TYPE OFF
FILEDEF TRANS DSK REFOR INST LR 97 RE F
FILEDEF DUMP DSK INST DUMP
LOAD PGM7 (CLEAR LIBE) PLILIB
START (BRIEF)
FILEDEF TRANS CLEAR
FILEDEF DUMP CLEAR
&STACK KT
ATTACH RAMIS ALL BR
FILEDEF 6 MSG KILL
EXEC RAMISIN RE29 RAM
DETACH RAMIS BR
EXEC RAMOUT
&EXIT
```

Listing of Filename = RE29, Filetype = RAM

```
ERASE
FILE MODINST
END
INPUT
READ REFOR INST
RECORD 97
FORM 9,16,2,5,4,4,4,4,4,4,16,1,6,3,4,5,6
SET 1
SEARCH FORWARD
FILE MODINST
END
```


ROOT EXECUTIVE: E27

DATA BASE: Instructor Master
Instructor Scratch

FUNCTION: Recreate the Scratch data base using the records
from all Schools in the Master data base

The first step in the recreation of the Scratch data base is the erase of the existing Scratch copy.

The Master is then dumped into card-image format onto a temporary dataset. This file is then used as input to recreate the Scratch data base in its entirety.

Executive Sequence E27 Logic

The components of Executive Sequence E27 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E27	EXEC	
(2)	RE25	RAM	
(3)	PGM7	PLI	(PL/I Program)
(4)	RE27	RAM	

Listing of Filename = E27, Filetype = EXEC

```
&TYPE OFF
ATTACH TEMP20 AS 193 B
FILEDEF RAMUTIL1 DSK UINST DUMP U LR 80 RE FB BL 800
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE25 RAM
DETACH RAMIS BR
FILEDEF RAMUTIL1 CLEAR
FILEDEF TRANS DSK UREFOR INST U LR 97 RE FB BL 776
FILEDEF DUMP DSK UINST DUMP U
LOAD PGM7 (CLEAR LIBE) PLILIB
START (BRIEF)
FILEDEF TRANS CLEAR
FILEDEF DUMP CLEAR
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE27 RAM
DETACH RAMIS BR
DETACH 193
```

Listing of Filename = RE25, Filetype = RAM

```
DUMP
FILE INST
PRINT YTD AND SAVE
END
```

Listing of Filename = RE27, Filetype = RAM

```
ERASE
FILE MODINST
END
INPUT
READ UREFOR INST
RECORD 97
FORM 9,16,2,5,4,4,4,4,4,4,16,1,6,3,4,5,6
SET 1
SEARCH FORWARD
FILE MODINST
END
```

ROOT EXECUTIVE: E30

DATA BASE: Instructor Master

FUNCTION: Dump the records of one (1) School to the User's terminal

This Executive sequence forces a formatted dump to the User's terminal of all of the records of the Instructor Master data base associated with one school. The Executive will prompt the User for the selection of the desired school.

Executive Sequence E30 Logic

The components of Executive Sequence E30 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E30	EXEC	
(2)	E57	EXEC	
(3)	X57	RUNPROC	
(4)	E60	EXEC	
(5)	PGM8	PLI	(PL/I Program)

Listing of Filename = E30, Filetype = EXEC

&TYPE OFF
EXEC E57
EXEC E60

Listing of Filename = E57, Filetype = EXEC

```

&TYPE OFF
&PRINT * FILE - INSTRUCTOR
&PRINT * FUNCTION - SELECT INSTRUCTORS BY SCHOOL
&PRINT * ENTER OUT FOR PREMATURE EXIT
-LP1 &PRINT *
&PRINT * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &EXIT
FILEDEF RAMUTIL1 DSK INST DUMP LR 80 RE FB BL 800
&STACK KT
&STACK EXEC X57 &1
&STACK FIN
ATTACH RAMIS ALL BR
FILEDEF 6 MSG KILL
EXEC RAMIS
DETACH RAMIS BR
&STACK RT
FILEDEF RAMUTIL1 CLEAR
FILEDEF 6 CONO
&STACK KT
&STACK L /D=/
&STACK Q
EDIT MSG KILL
&PRI &1 SCHOOL DUMPED TO DISK FILE
&EXIT
-ERR1 &PRINT *** INVALID ENTRY -- FUNCTION TERMINATING
    
```

Listing of Filename = X57, Filetype = RUNPROC

```

DELETE
FILE RAMEXEC
1=OUT=X57.$
END
CATALOG X57
DUMP
FILE INST
PRINT YTD AND SAVE
IF SCH IS &1
END
END CATALOG
    
```


Listing of Filename = E60, Filetype = EXEC

```
&TYPE OFF  
FILEDEF DUMP DSK INST DUMP LR 80 RE F  
LOAD PGMB (CLEAR LIBE) PLILIB  
START (BRIEF)  
FILEDEF DUMP CLEAR  
&EXIT
```

ROOT EXECUTIVE: E35

DATA BASE: Instructor Scratch

FUNCTION: Dump Records of one School to User's terminal

This Executive sequence forces a formatted dump to the User's terminal of all of the records of the Instructor Scratch data base associated with one school. The Executive will prompt the User for the selection of the desired school.

Executive Sequence E35 Logic

The components of Executive Sequence E35 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E35	EXEC	
(2)	E28	EXEC	
(3)	X28	RUNPROC	
(4)	E60	EXEC	
(5)	PGM8	PLI	(PL/I Program)

Listing of Filename = E35, Filetype = EXEC

&TYPE OFF
EXEC E28
EXEC E60

Listing of Filename = E28, Filetype = EXEC

```
&TYPE OFF
&PRINT * FILE - INSTRUCTOR SCRATCH DATA BASE
&PRINT * FUNCTION - SELECT INSTRUCTORS BY SCHOOL
&PRINT * ENTER OUT FOR PREMATURE EXIT
-LP1 &PRINT *
&PRINT * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 /GOTO -CK1
&PR1 * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &EXIT
FILEDEF RAMUTIL1 DSK INST DUMP LR 80 RE FB BL 800
&STACK KT
&STACK EXEC X28 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
FILEDEF RAMUTIL1 CLEAR
&EXIT
-ERR1 &PRINT *** INVALID ENTRY -- FUNCTION TERMINATING
```

Listing of Filename = X28, Filetype = RUNPROC

```
DELETE
FILE RAMEXEC
1=OUT=X28.$
END
CATALOG X28
DUMP
FILE MODINST
PRINT YTD AND SAVE
IF SCH IS &1
END
END CATALOG
```

Listing of Filename = E60, Filetype = EXEC

&TYPE OFF
FILEDEF DUMP DSK INST DUMP LR 80 RE F
LOAD PGM8 (CLEAR LIBE) PLILIB
START (BRIEF)
FILEDEF DUMP CLEAR
&EXIT

ROOT EXECUTIVE: E22A

DATA BASE: Instructor

• FUNCTION: Sort the Instructor time card file

All Root Executives with names containing the E22-prefix are used in conjunction with the processing of the weekly Instructor Time Cards.

The User will be prompted for the date of the time card file desired. This date takes the format Wyyymmdd; in this date 'yy' is the year, 'mm' the month, and 'dd' the day. The entry will be a total of seven (7) characters in length; provide a leading zero on the month and/or day, if applicable, e.g., W750911. This keyboard entry becomes the "filetype" for the time card file desired, i.e., the input file to the sort is filename = TCARDS, filetype = Wyyymmdd.

The sorted output file of this Executive is filename = E22, filetype = SORT.

The components of Executive Sequence E22A and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22A	EXEC

Listing of Filename = E22A, Filetype = EXEC

```
&TYPE OFF
&PRINT * ENTER OUT TO ABORT
-STEP1 &PRINT *
&PRINT * ENTER FILE-TYPE (FT) OF THE TIME CARD FILE
&PRINT *          TO BE PROCESSED; FORMAT IS WYYMMDD
&PRINT *
&READ ARGS
&IF &INDEX EQ 1 &GOTO -STEP2
&PRINT * WRONG NUMBER ARGUMENTS ????? TRY AGAIN
&GOTO -STEP1
-STEP2 &IF &1 EQ OUT &EXIT
&PARM = &1
STATE TCARDS &PARM P
&IF &INDEX0 EQ 0 &GOTO -STEP3
&PRINT * FILE TCARDS &PARM DOES NOT EXIST
&PRINT * EXECUTIVE E22A TERMINATING
&EXIT
-STEP3 ATTACH TEMP5 AS 193 B
ERASE E22 SORT P
FILEDEF SORTOUT DSK E22 SORT LR 80 RE FB BL 800
OSSORT SRT TCARDS &PARM P E22 SORT P (WMODE=U MSG CC)
&PRINT * SORT RETURN CODE WAS &INDEX0
DETACH 193 BR
FILEDEF SORTOUT CLEAR
ERASE TCARDS &PARM P
COMBINE TCARDS &PARM P E22 SORT P
```

ROOT EXECUTIVE: E22B

DATA BASE: Instructor

FUNCTION: Makeup the Instructor data base reference file,
Filename = SPIN, Filetype = DATA

All Root Executives with names containing the E22-prefix are used in conjunction with the processing of the weekly Instructor Time Cards.

The components of Executive Sequence E22B and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22B	EXEC

Listing of Filename = E22B, Filetype = EXEC

```
&TYPE OFF
&STACK KT
ERASE SPIN DATA
FILEDEF FT04F001 DSK FILE FT04F001 LR 17 RE FP BL 799
&BEGSTACK
TABLEF
FILE INST
PRINT ID AND SCH AND CDP AND SAVE
END
FIN
&ENDSTACK
ATTACH RAMIS ALL BR
RAMIS
DETACH RAMIS BR
FILEDEF FT04F001 CLEAR
ALTER FILE FT04F001 P SPIN DATA P
&PRINT *
&PRINT * FILE SPIN DATA NOW EXISTS
```

ROOT EXECUTIVE: E22C

DATA BASE: Instructor

FUNCTION: Compare the Instructor Time Card input file with the,
Instructor data base reference file

All Root Executives with names containing the E22-prefix are used in conjunction with the processing of the weekly Instructor Time Cards.

In this sequence, the sorted file containing the weekly Instructor Time Cards (E22/SORT) is compared with the Instructor data base reference file (SPIN/DATA). Any discrepancies are noted in the form of messages in output file (E22/EMSG). Time cards that contain no errors are passed to output file E22/DATA. Time cards with errors are placed in the file E22/BUST.

The input files E22/SORT and SPIN/DATA remain unchanged as a result of the operation of this Executive Sequence.

The components of Executive Sequence E22C and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E22C	EXEC	
(2)	PGM22	PLI	(PL/I Program)

Listing of Filename = E22C, Filetype = EXEC

```

&TYPE OFF
ERASE E22 DATA
ERASE E22 BUST
ERASE E22 EMSG
FILEDEF CARDS DSK E22 SORT LR 80 RE FB BL 800
FILEDEF SPIN DSK SPIN DATA LR 17 RE FB BL 799
FILEDEF GOOD DSK E22 DATA LR 80 RE FB BL 800
FILEDEF ETRANS DSK E22 BUST LR 80 RE FB BL 800
FILEDEF EMSG DSK E22 EMSG LR 61 RE FB BL 793
LOAD PGM22 (CLEAR LIBL) PLILIR
START (BRIEF)
&PRINT *
STATE E22 EMSG
&IF &INDEX0 NE 0 &GOTO -STEP1
&PRINT * E22 EMSG FILE EXISTS...
&GOTO -STEP2
-STEP1 &PRINT *E22 EMSG ERROR FILE DOES NOT EXIST...
-STEP2 &PRINT *
STATE E22 DATA
&IF &INDEX0 NE 0 &GOTO -STEP3
&PRINT * E22 DATA FILE NOW EXISTS...
&GOTO -STEP4
-STEP3 &PRINT * E22 DATA FILE DOES NOT EXIST...
-STEP4 FILEDEF CARDS CLEAR
FILEDEF SPIN CLEAR
FILEDEF GOOD CLEAR
FILEDEF ETRANS CLEAR
FILEDEF EMSG CLEAR
    
```


ROOT EXECUTIVE: E22D

DATA BASE: Instructor

FUNCTION: Zero the Current Week (CW) time fields within the Instructor data base

All Root Executives with names containing the E22-prefix are used in conjunction with the processing of the weekly Instructor Time Cards.

This Executive Sequence clears the time entries to the Current Week (CW) fields (previous weeks' entries) for all Instructors.

The components of Executive Sequence E22D and the chronological order of execution are indicated in the table presented below. A listing of these files follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22D	EXEC

Listing of Filename = E22D, Filetype = EXEC

```

&TYPE OFF
&STACK KT
FILEDEF 6 MSG KILL
&BEGSTACK
SCAN
FILE INST
SHOW. 15
CHANGE. 15=>0.5*
END
FIN
&ENDSTACK
ATTACH RAMIS ALL BR
EXEC RAMIS
DETACH RAMIS ALL BR
FILEDEF 6 CONO
  
```

ROOT EXECUTIVE: E22E

DATA BASE: Instructor

Function: Load the Current Week's Instructor Time Cards into
the Instructor data base

All Root Executives with names containing the E22-prefix are used in conjunction with the processing of the weekly Instructor Time Cards.

Input time card file to this Executive Sequence is filename = E22, filetype = DATA.

The components of Executive Sequence E22E and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E22E	EXEC	
(2)	PGM5	PL1	(PL/1 Program)
(3)	RE22	RAM	

Listing of Filename = E22E, Filetype = EXEC

```

&TYPE OFF
STATE E22 DATA
&IF &INDEX0 NE 0 &GOTO -NOCDS
ERASE TIME REJECTS
FILEDEF CARDS DSK E22 DATA
FILEDEF TRANS DSK TIME FILE LR 121 RE F
FILEDEF ETRANS DSK TIME REJECTS LR 80 RE FB BL 800
LOAD PGMS (CLEAR LIBE) PLILIB
START (BRIEF)
FILEDEF CARDS CLEAR
FILEDEF TRANS CLEAR
FILEDEF ETRANS CLEAR
ERASE REJECT FILE
FILEDEF 09 DSK REJECT FILE LR 121 RE F
&STACK KT
ATTACH RAMIS ALL BR
FILEDEF 6 MSG KILL
EXEC RAMISIN RE22 RAM
DETACH RAMIS BR
EXEC RAMOUT
FILEDEF 09 CLEAR
STATE REJECT FILE
&IF &INDEX0 EQ 0 &GOTO -STP1
&PRINT * REJECT FILE DOES NOT EXIST
ERASE E22 SORT
ERASE E22 DATA
&EXIT
-STP1 &PRINT * REJECT FILE EXISTS; ERRORS TO BE RESOLVED
&EXIT

```

Listing of Filename = RE22, Filetype = RAM

```

UPDATE
READ TIME FILE
RECORD 121
SET 13,15,16,17
NO-KEY 09
FORM 9,4,4,6,3,4,X-4,4,X-4,4,C3,C4,X-4,C4,X-4,C4,C3,C4,X-4,C4,X-4,C4
FORM C3,C4,X-4,C4,X-4,C4,C3,C4,X-4,C4,X-4,C4,C3,C4,X-4,C4,X-4,C4
FORM C3,C4,X-4,C4,X-4,C4,C3,C4,X-4,C4,X-4,C4,C3,C4,X-4,C4,X-4,C4
FORM C3,C4,X-4,C4,X-4,C4,C3,C4,X-4,C4,X-4,C4,C3,C4,X-4,C4,X-4,C4
FORM C3,C4,X-4,C4,X-4,C4,C3,C4,X-4,C4,X-4,C4
ORDER 1,5,10,13,14,15,16,17,14,15,16,17,14,15,16,17,14,15,16,17
ORDER 14,15,16,17,14,15,16,17,14,15,16,17,14,15,16,17,14,15,16,17
ORDER 14,15,16,17,14,15,16,17,14,15,16,17,14,15,16,17,14,15,16,17
FILE INST
END
    
```


ROOT EXECUTIVE: E22F

DATA BASE: Instructor

FUNCTION: Clear all Quarter-to-Date (QTD) time field entries for
all Instructors

All Root Executives with names containing the E22-prefix are used in conjunction with the processing of the weekly Instructor Time Cards.

After processing any desired quarterly reports, this Executive Sequence serves to zero all accumulated quarterly times.

The components of Executive Sequence E22F and the chronological order of execution are indicated in the table presented below. A listing of this file follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22F	EXEC

Listing of Filename = E22F, Filetype = EXEC

```
&TYPE OFF
&STACK KT
FILEDEF 6 MSG KILL
&BEGSTACK
SCAN
FILE INST
SHOW. 16
CHANGE. 16=>0,S*
END
FIN
&ENDSTACK
ATTACH RAMIS ALL BR
EXEC RAMIS
DETACH RAMIS ALL BR
FILEDEF 6 CONO
```

ROOT EXECUTIVE: E22G

DATA BASE: Instructor

FUNCTION: Zero (Clear all Year-to-Date (YTD) time field entries
for all Instructors

All Root Executives with names containing the E22-prefix are used in conjunction with the processing of the weekly Instructor Time Cards.

After processing any desired quarterly and yearly reports, this Executive Sequence serves to zero all accumulated yearly times.

The components of Executive Sequence E22G and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22G	EXEC

Listing of Filename = E22G, Filetype = EXEC

```
&TYPE OFF
&STACK KT
FILEDEF 6 MSG KILL
&BEGSTACK
SCAN
FILE INST
SHOW. 17
CHANGE. 17=>0,S*
END
FIN
&ENDSTACK
ATTACH RAMIS ALL BR
EXEC RAMIS
DETACH RAMIS ALL BR
FILEDEF 6 CONO
```

ROOT EXECUTIVE: E22R1

DATA BASE: Instructor

FUNCTION: Produce a standard report from data within the Instructor data base

The components of Executive Sequence E22R1 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22R1	EXEC
(2)	RE22R1	RUNPROC

Listing of Filename = E22R1, Filetype = EXEC

```
&TYPE OFF  
&STACK KT  
&STACK EXEC RE22R1  
ATTACH RAMIS ALL BR  
RAMIS  
DETACH RAMIS BR  
&STACK RT  
&EXIT
```

Listing of Filename = RE22R1, Filetype = RUNPROC

```

DELETE
FILE RAMEXEC
1=OUT=RE22R1,S
END
CATALOG RE22R1
&& PRINT * ENTER OUT TO ABORT
&&STEP1
&& PRINT *
&& PRINT * ENTER INSTRUCTOR ID (ID), A9
&& READ ARGS
&& IF &NARGS EQ 1 GOTO STEP2 ;
&& PRINT * ???? WRONG NUMBER ARGUMENTS - TRY AGAIN
&& GOTO STEP1
&&STEP2
&& IF &1 NE 'OUT' GOTO STEP3 ;
&& EXIT
&&STEP3
TABLE
HEADING
    GENERAL QUERY OF INSTRUCTOR ASSIGNMENTS
    AGAINST FOLLOWING INSTRUCTOR ID(S):
    &1
FILE INST
PRINT CDP
    BY SCH BY ID BY IN BY NME
ON ID SKIP-LINE
IF CDP IS-NOT ' '
IF ID IS &1
END
FIN
END CATALOG

```


ROOT EXECUTIVE: E22R2

DATA BASE: Instructor

FUNCTION: Produce a standard report from data within the Instructor data base

The components of Executive Sequence E22R2 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22R2	EXEC
(2)	E22T1	TABLE

Listing of Filename = E22R2, Filetype = EXEC

```
&TYPE OFF
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN E22T1 TABLE
DETACH RAMIS BR
&EXIT
```

Listing of Filename = E22T1, Filetype = TABLE

```
TABLE
HEADING
    GENERAL-PURPOSE INSTRUCTOR ASSIGNMENT
    LISTING FOR TIME-CARD VALIDATION...
FILE INST
PRINT NME AND CDP
BY SCH BY ID
IF CDP IS-NOT ' '
IF SCH IS DCFF
ON ID SKIP-LINE
END
```

ROOT EXECUTIVE: E22R3

DATA BASE: Instructor

FUNCTION: Produce a standard report from data within the Instructor data base

The components of Executive Sequence E22R3 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22R3	EXEC
(2)	SELSCH	EXEC
(3)	RE22R3	RUNPROC

Listing of Filename = E22R3, Filetype = EXEC

```
&TYPE OFF
EXEC SELSCH RE22R3
&EXIT
```

Listing of Filename = SELSCH, Filetype = EXEC

```
&TYPE OFF
&WHICH = &1
&PRINT *
&PRINT * ENTER OUT TO ABORT
-LP1 &PRINT *
&PRINT * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRINT * ???? WRONG NUMBER PARMS - TRY AGAIN
&GOTO -LP1
-CK1 &IF &1 EQ OUT &EXIT
&STACK RT
&STACK EXEC &WHICH &1
&STACK FIN
ATTACH RAMIS ALL BR
RAMIS
DETACH RAMIS BR
&STACK RT
&EXIT
```

Listing of Filename = RE22R3, Filetype = RUNPROC

```

DELETE
FILE RAMEXEC
1=OUT=RE22R3,S
END
CATALOG RE22R3
DEFINE
FILE INST
SCH/FB.1 = CW ;
END
TABLE
HEADING
    WEEKLY INSTRUCTOR TIME SUMMARY FOR
    TIME-CARD VALIDATION...
FILE INST
SUM SCH AS 'EXPENDED,TIME'
    BY SCH AS SCHOOL
    BY ID
    BY IN
    BY NME AS NAME
IF TT IS-NOT ' '
IF CDP IS-NOT ' '
IF SCH IS &1
ON ID SKIP-LINE
END
END CATALOG

```

ROOT EXECUTIVE: E22R4

DATA BASE: Instructor

FUNCTION: Produce a standard report from data within the Instructor data base

The components of Executive Sequence E22R4 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E22R4	EXEC
(2)	RE22R4	RUNPROC

Listing of Filename = E22R4, Filetype = EXEC

```

&TYPE OFF
&STACK KT
&STACK EXEC RE22R4
ATTACH RAMIS ALL BR
RAMIS
DETACH RAMIS BR
&STACK RT
&EXIT
    
```


Listing of Filename = RE22R4, Filetype = RUNPROC

```

DELETE
FILE RAMEXEC
1=OUT=RE22R4,S
END
CATALOG RE22R4
&& PRINT * ENTER OUT TO ABORT
&&STEP1
&& PRINT *
&& PRINT * ENTER INSTRUCTOR ID (ID), A9
&& READ ARGS
&& IF &NARGS EQ 1 GOTO STEP2 ;
&& PRINT * ???? WRONG NUMBER ARGUMENTS - TRY AGAIN
&& GOTO STEP1
&&STEP2
&& IF &1 NE 'OUT' GOTO STEP3 ;
&& EXIT
&&STEP3
DEFINE
FILE INST
SCW/F8.1 = CW ;
END
TABLE
HEADING
      WEEKLY INSTRUCTOR INDIVIDUAL TIME
      DISTRIBUTION AMONG COURSES...
FILE INST
SUM SCW AS 'EXPENDED,TIME'
      BY SCH AS SCHOOL
      BY ID SUB-TOTAL
      BY IN
      BY NME AS NAME
      BY CDP
      BY TT AS 'TIME,TYPE'
IF ID IS &1
IF TT IS-NOT ' '
IF CDP IS-NOT ' '
IF SCW IS-NOT 0
END
FIN
END CATALOG

```

ROOT EXECUTIVE: R5

DATA BASE: Instructor

FUNCTION: Produce a standard report from data within the Instructor data base

The components of Executive Sequence R5 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	R5	EXEC
(2)	R5	RUNPROC

Listing of Filename = R5, Filetype = EXEC

```
&TYPE OFF
&STACK KT
&STACK EXEC R5
&STACK FIN
ATTACH RAMIS ALL BR
RAMIS
DETACH RAMIS BR
&STACK RT
&EXIT
```

Listing of Filename = R5, Filetype = RUNPROC

```

-DELETE .
FILE RAMEXEC
1=OUT=R5,S
END
CATALOG R5
DEFINE
FILE INST
IF ROT EQ 0 GOTO NONE ;
LEFT/I4 = INT ( ROT / 100 ) ;
IF LEFT GT 70 GOTO NOWYYMM ;
PDATE/A5 = EDIT (ROT, '99/99') ;
RIGHT/I4 = ROT - ( LEFT * 100 ) ;
TEST/I6 = (RIGHT * 10000) + (LEFT * 100) + 30 ;
GOTO GETDUR ;
NOWYYMM ;
PDATE/A5 = EDIT(ROT,'$$99')||'/'||EDIT(ROT,'99$$') ;
TEST/I6 = (ROT * 100) + 30 ;
GETDUR ;
DURATION/I4 = YMD ( TEST, &YMD ) ;
GOTO END ;
NONE ;
DURATION/I4 = 0 ;
PDATE/A5 = '00/00' ;
END
TABLE
HEADING
    *** DATE THIS REPORT : &DATE ***
FILE INST
COUNT ENTRIES
    BY SCH AS 'SCHOOL'
    BY PDATE AS 'PRD'
IF DURATION IS-FROM 0 TO 180
ON SCH SUB-TOTAL
END
END CATALOG

```

ROOT EXECUTIVE: R6

DATA BASE: Instructor

FUNCTION: Produce ~~standard~~ report from data within the Instructor data base

The components of Executive Sequence R6 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	R6	EXEC
(2)	R6 \	RUNPROC

Listing of Filename = R6, Filetype = EXEC

```
&TYPE OFF
&STACK KT
&STACK EXEC R6
&STACK FIN
ATTACH RAMIS ALL BR
RAMIS
DETACH RAMIS BR
&STACK RT
&EXIT
```


Listing of Filename = R6, Filetype = RUNPROC

```

DELETE
FILE RAMEXEC
1=OUT=R6.$
END
CATALOG R6
DEFINE
FILE INST
IF ROT EQ 0 GOTO NONE ;
LEFT/I4 = INT ( ROT / 100 ) ;
IF LEFT GT 70 GOTO NOWYYMM ;
PDATE/A5 = EDIT (ROT, '99/99') ;
RIGHT/I4 = ROT - ( LEFT * 100 ) ;
TEST/I6 = (RIGHT * 10000) + (LEFT * 100) + 30 ;
GOTO GETDUR ;
NOWYYMM ;
PDATE/A5 = EDIT(ROT, '$$99') || '/' || EDIT(ROT, '99$$') ;
TEST/I6 = (ROT * 100) + 30 ;
GETDUR ;
DURATION/I4 = YMD ( TEST, &YMD ) ;
GOTO END ;
NONE ;
DURATION/I4 = 0 ;
PDATE/A5 = '00/00' ;
END
TABLE
HEADING
      *** DATE THIS REPORT : &DATE ***
FILE INST
LIST ID AS SSN
AND NME AS NAME
AND IN
      BY SCH AS 'SCHOOL'
      BY PDATE AS 'PRD'
IF DURATION IS-FROM 0 TO 180
ON SCH SKIP-LINE
END
END CATALOG

```

ROOT EXECUTIVE: E40

DATA BASE: Course Master

FUNCTION: (1) Add a Course to an existing School, /or/
(2) Add a new School and Course

The sequence described below forms a CLASS A Prompting Type Executive. The file PD40/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD40/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E40 Logic

The components of Executive Sequence E40 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E40	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RE40	RAM	

Listing of Filename = E40, Filetype = EXEC

```

&TYPE OFF
EXEC ESUB1 PD40 RE40
  
```

Listing of Filename = PD40, Filetype = DATA

```

1* THIS IS EXECUTIVE NUMBER E40
1* FILE - COURSE
1* FUNCTION - ADD A NEW SCHOOL,
1*           AND/OR ADD A NEW COURSE
1*           TO AN EXISTING SCHOOL...
2SCH      11 4      1      1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP      21 4      1      5 4
3* ENTER COURSE CDP (CDP), A4
2DEL      31 1 1    2      9 1
3* ENTER DELETE FLAG (DEL), A1
3* 1 = COURSE ACTIVE
3* 2 = COURSE HAS BEEN DELETED
2CTLG     4110      2      1010
3* ENTER COURSE CATALOG NUMBER, A4
2CRS      5116      2      2016
3* ENTER COURSE TITLE (CRS), A16
2CONV1    62 0.0    240.0    36 3
3* ENTER CONVENINGS NUMBER1 (CONV1), I3
2LEN1     73 0.0    240.0    4 39 4
3* ENTER COURSE LENGTH #1 (LEN1), F4.1
2CAP1     82 0.0    240.0    43 3
3* ENTER COURSE CAPACITY #1 (CAP1), I3
2BCAP1    92 0.0    240.0    46 3
3* ENTER BUPERS CAPACITY #1 (BCAP1), I3
2DMD1     102 0.0    240.0    49 5
3* ENTER COURSE DEMAND #1 (DMD1), I5
2BDMD1    112 0.0    240.0    54 5
3* ENTER BUPERS DEMAND #1 (BDMD1), I5
2OFST     112 0.0    240.0    59 2
3* ENTER SCHEDULE OFFSET (OFST), I2
2PFail    133 0.0    240.0    5 61 5
3* ENTER % FAILURE RATE (PFail), F5.3
2NADIS    143 0.0    240.0    5 66 5
3* ENTER % NONAC DISENROLL (NADIS), F5.3
2NOSHOW   153 0.0    240.0    5 71 5
3* ENTER % NO-SHOW (NOSHOW), F5.3
2SETB     163 0.0    240.0    5 76 5
3* ENTER % SETBACKS (SETB), F5.3
2BKLG     172 0.0    240.0    81 4
3* ENTER NUMBER OF BACKLOGS (BKLG), I4
2JNO      181 4      85 4
3* COURSE J-NUMBER (JNO), A4
2CONV2    192 0.0    240.0    89 3
3* ENTER CONVENINGS NUMBER2 (CONV2), I3
2LEN2     203 0.0    240.0    4 92 4
3* ENTER COURSE LENGTH #2 (LEN2), F4.1
2CAP2     212 0.0    240.0    96 3
3* ENTER COURSE CAPACITY #2 (CAP2), I3
2BCAP2    222 0.0    240.0    99 3
3* ENTER BUPERS CAPACITY #2 (BCAP2), I3
2DMD2     232 0.0    240.0    102 5
3* ENTER COURSE DEMAND #2 (DMD2), I5
2BDMD2    242 0.0    240.0    107 5
3* ENTER BUPERS DEMAND #2 (BDMD2), I5

```


Listing of Filename = PD40, Filetype = DATA (Continued)

2CHWK2	252	0.0	240.0	112 3
3* ENTER CHANGE WEEK #2 (CHWK2), I3				
2CONV3	262	0.0	240.0	115 3
3* ENTER CONVENINGS NUMBER3 (CONV3), I3				
2LEN3	272	0.0	240.0	118 4
3* ENTER COURSE LENGTH #3 (LEN3), F4.1				
2CAP3	282	0.0	240.0	122 3
3* ENTER COURSE CAPACITY #3 (CAP3), I3				
2BCAP3	292	0.0	240.0	125 3
3* ENTER BUPERS CAPACITY #3 (BCAP3), I3				
2DMD3	302	0.0	240.0	128 5
3* ENTER COURSE DEMAND #3 (DMD3), I5				
2BDMD3	312	0.0	240.0	133 5
3* ENTER BUPERS DEMAND #3 (BDMD3), I5				
2CHWK3	322	0.0	240.0	138 3
3* ENTER CHANGE WEEK #3 (CHWK3), I3				
2PAOB	332	0.0	240.0	141 4
3* ENTER PLANNED AOB (PAOB), I4				
2AFAIL	343	0.0	240.0	145 5
3* ENTER % ACAD FAILURES (AFAIL), F5.3				
2PRTY	352	0.0	240.0	150 2
3* ENTER COURSE PRIORITY (PRTY), I2				
2CTYPE	361	2		152 2
3* ENTER COURSE TYPE (CTYPE), A2				
2PNEC	371	4	2	154 4
3* ENTER PRIMARY NEC (PNEC), A4				
2UCAP	382	0.0	240.0	158 3
3* ENTER % CAPACITY UTILIZED (UCAP), I3				
2UDEM	392	0.0	240.0	161 3
3* ENTER % DEMAND UTILIZED (UDEM), I3				
2FPRTY	402	0.0	240.0	164 2
3* ENTER FTC PRIORITY (FPRTY), I2				
2RDTE	412	0.0	240.0	166 6
3* ENTER REVISION DATE (RDTE),				
2HSETB	423	0.0	240.0	5171 5
3* ENTER HIST. SETBACK (HSETB), F5.3				
2TINSTR	433	0.0	240.0	4177 4
3* ENTER TOT INSTRS REQD (TINSTR), F4.1				
2SUIC	441	5	2	181 5
3* ENTER STUDENT UIC (SUIC), A5				
2CCMM	45110		2	18610
3* ENTER CCMM, A10				

Listing of Filename = ESUB1, Filetype =EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE40, Filetype =RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,1,10,16,3,4,3,3,5,5,2,5,5,5,5,4,4,3,4,3,3,5,5,3,3
FORM 4,3,3,5,5,3,4,5,2,2,4,3,3,2,6,5,4,5,10
KEY 1,2
INCLUDE 1
FILE COURSE
END
```

ROOT EXECUTIVE: E41

DATA BASE: Course Master

FUNCTION: Add a new Student Instructor Ratio (SIR) and a new Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file PD41/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD41/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E41 Logic

The components of Executive Sequence E41 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E41	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RE41	RAM	

Listing of Filename = E41, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 PD41 RE41
```

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE41, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,X187,4,5,1,9,3,1
ORDER 1,2,46,47,48,49,50,51
KEY 1,2,46
INCLUDE 46
FILE COURSE
END
```

Listing of Filename = PD41, Filetype = DATA

```
1* THIS IS EXECUTIVE NUMBER E41
1* FILE - COURSE
1* FUNCTION - ADD A STUDENT/INSTR RATIO
1*          AND AN INSTRUCTOR TO AN
1*          EXISTING COURSE...
2SCH      11 4      1      1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP      21 4      1      5 4
3* ENTER COURSE CDP (CDP), A4
2SIR      463      0.0      140.0      4196 4
3* ENTER STUDENT/INSTR RATIO (SIR), F4.1
2CHRS      473      0.0      240.0      2200 5
3* ENTER INSTR CONTACT HRS (CHRS), F5.1
2CTYP      481 1      1      205 1
3* ENTER COURSE TYPE (CTYP), A1
2ID        491 9      1      206 9
3* ENTER INSTRUCTOR ID (ID), A9
2QUAL      501 3      2      215 3
3* ENTER INSTR % QUALIFIED (QUAL), A3
2ASN      512 1 0.0      140.0      218 1
3* ENTER ASSIGNED FLAG (ASN), I1
```

ROOT EXECUTIVE: E42

DATA BASE: Course Master

FUNCTION: Add a new Instructor to an existing Student
Instructor Ratio (SIR)

The sequence described below forms a CLASS A Prompting Type Executive. The file PD42/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD42/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E42 Logic

The components of Executive Sequence E42 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E42	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RE42	RAM	

Listing of Filename = E42, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 PD42 RE42
&EXIT
```


Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE42, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,X187,4,X6,9,3,1
ORDER 1,2,46,49,50,51
KEY 1,2,46,49
INCLUDE 49
FILE COURSE
END
```

Listing of Filename = PD42, Filetype = DATA

2SCH	11 4	1	1 4
3* ENTER SCHOOL CODE (SCH), A4			
2CDP	21 4	1	5 4
3* ENTER COURSE CDP (CDP), A4			
2SIR	463 0.0	140.0	4196 4
3* ENTER STUDENT/INSTR RATIO (SIR), F4.1			
2ID	491 9	1	206 9
3* ENTER INSTRUCTOR ID (ID), A9			
2QUAL	501 3	2	215 3
3* ENTER INSTR % QUALIFIED (QUAL), A3			
2ASN	512 1 0.0	140.0	218 1
3* ENTER ASSIGNED FLAG (ASN), I1			

ROOT EXECUTIVE: E61

DATA BASE: Course Master

Function: Change an existing Field

This single executive serves to force entry to the SCAN mode of the RAMIS data management system. After SCAN mode has been successfully entered, the User may direct change of existing field(s) interactively through his terminal.

Terminal entry requirements of the RAMIS SCAN mode are fully covered in the NCSS vendor's documentation.

The DOTS User's Manual lists the data field names and identification numbers as appropriate for the Course Master data base. This list will not be repeated in this document.

Listing of Executive E61 (SCAN Mode Entry)

```
&TYPE OFF
&STACK KT
&STACK SCAN
&STACK FILE COURSE
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
&EXIT
```

ROOT EXECUTIVE: E62

DATA BASE: Course Master

FUNCTION: Delete a School

The components of Executive Sequence E62 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E62	EXEC
(2)	X62	RUNPROC

Listing of Filename = E62, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE E62
&PRI * FILE - COURSE
&PRI * FUNCTION - DELETE AN ENTIRE SCHOOL
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -OK
&PRI * WRONG NUMBER OF ARGUMENTS - RETRY
&GOTO -LP1
-OK &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC X62 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = X62, Filetype = RUNPROC

DELETE
FILE RAMEXEC
1=OUT=X62.S
END
CATALOG X62
DELETE
FORM 4
SET 1
FILE COURSE
&1
END
END CATALOG

ROOT EXECUTIVE: E63

DATA BASE: Course Master

FUNCTION: Delete a Course

The components of Executive Sequence E63 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E63	EXEC
(2)	X63	RUNPROC

Listing of Filename = E63, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER E63
&PRI * FILE - COURSE
&PRI * FUNCTION - DELETE A COURSE
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK &IF &1 EQ OUT &GOTO -OUT
&SAV1 = &1
-LP2 &PRI *
&PRI * ENTER COURSE CDP (CDP), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -OK
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP2
-OK &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC X63 &SAV1 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = X63, Filetype = RUNPROC

DELETE
FILE RAMEXEC
1=OUT=X63,\$
END
CATALOG X63
DELETE
FORM 4,X4.4
SET 2
FILE COURSE
&1
END
END CATALOG

ROOT EXECUTIVE: E64

DATA BASE: Course Master

FUNCTION: Delete an existing Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file PD64/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file PD64/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence E64 Logic

The components of Executive Sequence E64 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E64	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RE64	RAM	

Listing of Filename = E64, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 PD64 RE64
&EXIT
```

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RE64, Filetype = RAM

```
DELETE
READ TRANS FILE
RECORD 250
FORM 4,4,X187,4,X6,9
ORDER 1,2,46,49
SET 49
FILE COURSE
END
```

Listing of Filename = PD64, Filetype = DATA

2SCH	11 4	1	1 4
3* ENTER SCHOOL CODE (SCH), A4			
2CDP	21 4	1	5 4
3* ENTER COURSE CDP (CDP), A4			
2SIR	463 0.0	140.0	4196 4
3* ENTER STUDENT/INSTR RATIO (SIR), F4.1			
2ID	491 9	1	206 9
3* ENTER INSTRUCTOR ID (ID), A9			

ROOT EXECUTIVE: E65

DATA BASE: Course Master

FUNCTION: Delete an Instructor

The components of Executive Sequence E65 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E65	EXEC
(2)	X65	RUNPROC

Listing of Filename = E65, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER E65
&PRI * FILE - COURSE
&PRI * FUNCTION - DELETE A STUDENT/INSTRUCTOR RATIO FROM A COURSE
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &GOTO -OUT
&SAV1 = &1
-LP2 &PRI *
&PRI * ENTER COURSE CDP (CDP), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK2
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP2
-CK2 &IF &1 EQ OUT &GOTO -OUT
&SAV2 = &1
-LP3 &PRI *
&PRI * ENTER STUDENT/INSTRUCTOR RATIO (SIR), F4.1
&READ ARGS
&IF &INDEX EQ 1 &GOTO -OK
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP3
-OK &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC X65 &SAV1 &SAV2 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = X65, Filetype = RUNPROC

```
DELETE  
FILE RAMEXEC  
1=OUT=X65.S  
END  
CATALOG X65  
DELETE  
FORM 4.X4.4.X4.4  
ORDER 1.2.46  
SET 46  
FILE COURSE  
&1  
END  
END CATALOG
```

ROOT EXECUTIVE: E43
 DATA BASE: Course Master
 FUNCTION: Load the Course Master data base From card input

The Course Master data base is loaded from scratch via the following Executive Sequences:

<u>Executive Sequence</u>	<u>Input Card Format</u>	<u>Input Data Contents</u>
E43	Course File, TYPE -1- and TYPE -2-	Fixed data relative to individual Courses
E44	Course File, TYPE -3-	Extension of individual Course data
E34	Instructor File, TYPE -2-	Assignment of individual Instructors to relevant Courses

In the creation of a new Course Master data set, the Executive Sequences should be executed in the order listed above.

If no TYPE -3- Course file data cards are available, they may be omitted from the load sequence and Executive Sequence E44 may then be run at the convenience of the User.

If Executive Sequences E43 and E34 are to be run, the order must be E43; then, E34. E43 must run successfully, if error-free operation of the E34 Sequence is anticipated.

The format of the card input data sets associated with Executive Sequence E43 is illustrated in the diagram following entitled "Course Data Base Type -1- Input Card Format", and "Course Data Base Type -2- Input Card Format". These card formats must be merged with the Type -1- and Type -2- cards for each course placed adjacent in the input; a Type -1- card precedes the related Type -2- card for the same Course.

Executive Sequence E43 Logic

The components of Executive Sequence E43 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E43	EXEC
(2)	PGM15	PLI (PL/I Program)
(3)	RE43	RAM

150

Listing of Filename = E43, Filetype = EXEC

```

&TYPE OFF
STATE E43 DATA
&IF &INDEX0 NE 0 &GOTO -NODATA
FILEDEF CARDS DSK E43 DATA
FILEDEF TRANS DSK COURSE INPUT LR 250 RE F
LOAD PGM16 (CLEAR LIBE) PLILIB
START (BRIEF)
FILEDEF CARDS CLEAR
FILEDEF TRANS CLEAR
ERASE E43 DATA
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE43 RAM
DETACH RAMIS BR
&EXIT
-NODATA &PRINT NO COURSE CARDS PROVIDED -- FUNCTION TERMINATING

```

Listing of Filename = RE43, Filetype = RAM

```

ERASE
FILE COURSE
END
INPUT
READ COURSE INPUT
RECORD 250
SET 1
FORM 4,4,1,10,16,3,4,3,3,5,5,2,5,5,5,5,4,4,3,4,3,3,5,5,3,3,4,3,3,5,5,3
FORM 4,5,2,2,4,3,3,2,6,5,4,5,10,4,5,1,9,3,1
FILE COURSE
END

```


[illegible]

CDP	UCAP	UDEM	T	RDTE	NSETB	TINSTR	COMM
1	2	3	4	5	6	7	8
9	10	11	12	13	14	15	16
17	18	19	20	21	22	23	24
25	26	27	28	29	30	31	32
33	34	35	36	37	38	39	40
41	42	43	44	45	46	47	48
49	50	51	52	53	54	55	56
57	58	59	60	61	62	63	64
65	66	67	68	69	70	71	72
73	74	75	76	77	78	79	80
81	82	83	84	85	86	87	88
89	90	91	92	93	94	95	96
97	98	99	100	101	102	103	104
105	106	107	108	109	110	111	112
113	114	115	116	117	118	119	120
121	122	123	124	125	126	127	128
129	130	131	132	133	134	135	136
137	138	139	140	141	142	143	144
145	146	147	148	149	150	151	152
153	154	155	156	157	158	159	160
161	162	163	164	165	166	167	168
169	170	171	172	173	174	175	176
177	178	179	180	181	182	183	184
185	186	187	188	189	190	191	192
193	194	195	196	197	198	199	200
201	202	203	204	205	206	207	208
209	210	211	212	213	214	215	216
217	218	219	220	221	222	223	224
225	226	227	228	229	230	231	232
233	234	235	236	237	238	239	240
241	242	243	244	245	246	247	248
249	250	251	252	253	254	255	256
257	258	259	260	261	262	263	264
265	266	267	268	269	270	271	272
273	274	275	276	277	278	279	280
281	282	283	284	285	286	287	288
289	290	291	292	293	294	295	296
297	298	299	300	301	302	303	304
305	306	307	308	309	310	311	312
313	314	315	316	317	318	319	320
321	322	323	324	325	326	327	328
329	330	331	332	333	334	335	336
337	338	339	340	341	342	343	344
345	346	347	348	349	350	351	352
353	354	355	356	357	358	359	360
361	362	363	364	365	366	367	368
369	370	371	372	373	374	375	376
377	378	379	380	381	382	383	384
385	386	387	388	389	390	391	392
393	394	395	396	397	398	399	400
401	402	403	404	405	406	407	408
409	410	411	412	413	414	415	416
417							

955-1115-0

959-1115-0

ROOT EXECUTIVE: E44

DATA BASE: Course Master

FUNCTION: Load the Course Master data base From card input

The Course Master data base is loaded from scratch via the following Executive Sequences:

<u>Executive Sequence</u>	<u>Input Card Format</u>	<u>Input Data Contents</u>
E43	Course File, TYPE -1- and TYPE -2-	Fixed data relative to individual Courses
E44	Course File, TYPE -3-	Extension of individual Course data
E34	Instructor File, TYPE -2-	Assignment of individual Instructors to relevant Courses

In the creation of a new Course Master data set, the Executive Sequences should be executed in the order listed above.

If no TYPE -3- Course file data cards are available, they may be omitted from the load sequence and Executive Sequence E44 may then be run at the convenience of the User.

If Executive Sequences E43 and E34 are to be run, the order must be E43; then, E34. E43 must run successfully, if error-free operation of the E34 Sequence is anticipated.

The format of the card input data set associated with Executive Sequence E44 is illustrated in the diagram following entitled "Course Data Base Type -3- Input Card Format".

Executive Sequence E44 Logic

The components of Executive Sequence E44 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E44	EXEC
(2)	RE44	RAM

COURSE DATA BASE TYPE -3- INPUT CARD FORMAT

IBM		COURSE FILE		80 Column Card Punch Layout	
TYPE 3- INPUT CARD NAME UNIT		CARD PUNCH UNIT MODEL SERIAL		DATE TIME	

CDP	LCAP	UCDEM	T	RDTE	MSETS	TIMETR	COMM
1	2	3	4	5	6	7	8
9	10	11	12	13	14	15	16
17	18	19	20	21	22	23	24
25	26	27	28	29	30	31	32
33	34	35	36	37	38	39	40
41	42	43	44	45	46	47	48
49	50	51	52	53	54	55	56
57	58	59	60	61	62	63	64
65	66	67	68	69	70	71	72
73	74	75	76	77	78	79	80
81	82	83	84	85	86	87	88
89	90	91	92	93	94	95	96
97	98	99	100	101	102	103	104
105	106	107	108	109	110	111	112
113	114	115	116	117	118	119	120
121	122	123	124	125	126	127	128
129	130	131	132	133	134	135	136
137	138	139	140	141	142	143	144
145	146	147	148	149	150	151	152
153	154	155	156	157	158	159	160
161	162	163	164	165	166	167	168
169	170	171	172	173	174	175	176
177	178	179	180	181	182	183	184
185	186	187	188	189	190	191	192
193	194	195	196	197	198	199	200
201	202	203	204	205	206	207	208
209	210	211	212	213	214	215	216
217	218	219	220	221	222	223	224
225	226	227	228	229	230	231	232
233	234	235	236	237	238	239	240
241	242	243	244	245	246	247	248
249	250	251	252	253	254	255	256
257	258	259	260	261	262	263	264
265	266	267	268	269	270	271	272
273	274	275	276	277	278	279	280
281	282	283	284	285	286	287	288
289	290	291	292	293	294	295	296
297	298	299	300	301	302	303	304
305	306	307	308	309	310	311	312
313	314	315	316	317	318	319	320
321	322	323	324	325	326	327	328
329	330	331	332	333	334	335	336
337	338	339	340	341	342	343	344
345	346	347	348	349	350	351	352
353	354	355	356	357	358	359	360
361	362	363	364	365	366	367	368
369	370	371	372	373	374	375	376
377	378	379	380	381	382	383	384
385	386	387	388	389	390	391	392
393	394	395	396	397	398	399	400
401	402	403	404	405	406	407	408
409	410	411	412	413	414	415	416
417	418	419	420	421	422	423	424
425	426	427	428	429	430	431	432
433	434	435	436	437	438	439	440
441	442	443	444	445	446	447	448
449	450	451	452	453	454	455	456
457	458	459	460	461	462	463	464
465	466	467	468	469	470	471	472
473	474	475	476	477	478	479	480
481	482	483	484	485	486	487	488
489	490	491	492	493	494	495	496
497	498	499	500	501	502	503	504
505	506	507	508	509	510	511	512
513	514	515	516	517	518	519	520
521	522	523	524	525	526	527	528
529	530	531	532	533	534	535	536
537	538	539	540	541	542	543	544
545	546	547	548	549	550	551	552
553	554	555	556	557	558	559	560
561	562	563	564	565	566	567	568
569	570	571	572	573	574	575	576
577	578	579	580	581	582	583	584
585	586	587	588	589	590	591	592
593	594	595	596	597	598	599	600
601	602	603	604	605	606	607	608
609	610	611	612	613	614	615	616
617	618	619	620	621	622	623	624
625	626	627	628	629	630	631	632
633	634	635	636	637	638	639	640
641	642	643	644	645	646	647	648
649	650	651	652	653	654	655	656
657	658	659	660	661	662	663	664
665	666	667	668	669	670	671	672
673	674	675	676	677	678	679	680
681	682	683	684	685	686	687	688
689	690	691	692	693	694	695	696
697	698	699	700	701	702	703	704
705	706	707	708	709	710	711	712
713	714	715	716	717	718	719	720
721	722	723	724	725	726	727	728
729	730	731	732	733	734	735	736
737	738	739	740	741	742	743	744
745	746	747	748	749	750	751	752
753	754	755	756	757	758	759	760
761	762	763	764	765	766	767	768
769	770	771	772	773	774	775	776
777	778	779	780	781	782	783	784
785	786	787	788	789	790	791	792
793	794	795	796	797	798	799	800
801	802	803	804	805	806	807	808
809	810	811	812	813	814	815	816
817	818	819	820	821	822	823	824
825	826	827	828	829	830	831	832
833	834	835	836	837	838	839	840
841	842	843	844	845	846	847	848
849	850	851	852	853	854	855	856
857	858	859	860	861	862	863	864
865	866	867	868	869	870	871	872
873	874	875	876	877	878	879	880
881	882	883	884	885	886	887	888
889	890	891	892	893	894	895	896
897	898	899	900	901	902	903	904
905	906	907	908	909	910	911	912
913	914	915	916	917	918	919	920
921	922	923	924	925	926	927	928
929	930	931	932	933	934	935	936
937	938	939	940	941	942	943	944
945	946	947	948	949	950	951	952
953	954	955	956	957	958	959	960
961	962	963	964	965	966	967	968
969	970	971	972	973	974	975	976
977	978	979	980	981	982	983	984
985	986	987	988	989	990	991	992
993	994	995	996	997	998	999	1000

955-1115-0

Listing of Filename = E44, Filetype = EXEC

```
&TYPE OFF
STATE E44 DATA
&IF &INDEX0 NE 0 &GOTO -NODATA
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE44 RAM
DETACH RAMIS BR
ERASE E44 DATA
&EXIT
-NODATA &PRI * NO TYPE3 CARDS FOUND -- FUNCTION TERMINATING
```

Listing of Filename = RE44, Filetype = RAM

```
REVISE
READ E44 DATA
RECORD 80
FORM 4,3,3,2,6,5,4,10
ORDER 2,38,39,40,41,42,43,45
KEY 2
UPDATE 38
INCLUDE 53
FILE COURSE
END
```

ROOT EXECUTIVE: E34

DATA BASE: Course Master

FUNCTION: Load the Course Master data base from card input

The Course Master data base is loaded from scratch via the following Executive Sequences:

<u>Executive Sequence</u>	<u>Input Card Format</u>	<u>Input Data Contents</u>
E43	Course File, TYPE -1- and TYPE -2-	Fixed data relative to individual Courses
E44	Course File, TYPE -3-	Extension of individual Course data
E34	Instructor File, TYPE -2-	Assignment of individual Instructors to relevant Courses

In the creation of a new Course Master data set, the Executive Sequences should be executed in the order listed above.

If no TYPE -3- Course file data cards are available, they may be omitted from the load sequence and Executive Sequence E44 may then be run at the convenience of the User.

If Executive Sequences E43 and E34 are to be run, the order must be E43; then, E34. E43 must run successfully, if error-free operation of the E34 Sequence is anticipated.

The format of the card input data set associated with Executive Sequence E34 is illustrated in the diagram following entitled "Instructor (Course) Data Base Type -2- Input Card Format".

Executive Sequence E34 Logic

The components of Executive Sequence E34 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	E34	EXEC
(2)	RE34	RAM

[illegible]

ID	NAME	IN	SCH	COP	TTL	T _A		SIR	CHRS
						VIS	QUAL		
1	1	1	1	1	1	1	1	1	1
2	2	2	2	2	2	2	2	2	2
3	3	3	3	3	3	3	3	3	3
4	4	4	4	4	4	4	4	4	4
5	5	5	5	5	5	5	5	5	5
6	6	6	6	6	6	6	6	6	6
7	7	7	7	7	7	7	7	7	7
8	8	8	8	8	8	8	8	8	8
9	9	9	9	9	9	9	9	9	9
10	10	10	10	10	10	10	10	10	10
11	11	11	11	11	11	11	11	11	11
12	12	12	12	12	12	12	12	12	12
13	13	13	13	13	13	13	13	13	13
14	14	14	14	14	14	14	14	14	14
15	15	15	15	15	15	15	15	15	15
16	16	16	16	16	16	16	16	16	16
17	17	17	17	17	17	17	17	17	17
18	18	18	18	18	18	18	18	18	18
19	19	19	19	19	19	19	19	19	19
20	20	20	20	20	20	20	20	20	20
21	21	21	21	21	21	21	21	21	21
22	22	22	22	22	22	22	22	22	22
23	23	23	23	23	23	23	23	23	23
24	24	24	24	24	24	24	24	24	24
25	25	25	25	25	25	25	25	25	25
26	26	26	26	26	26	26	26	26	26
27	27	27	27	27	27	27	27	27	27
28	28	28	28	28	28	28	28	28	28
29	29	29	29	29	29	29	29	29	29
30	30	30	30	30	30	30	30	30	30
31	31	31	31	31	31	31	31	31	31
32	32	32	32	32	32	32	32	32	32
33	33	33	33	33	33	33	33	33	33
34	34	34	34	34	34	34	34	34	34
35	35	35	35	35	35	35	35	35	35
36	36	36	36	36	36	36	36	36	36
37	37	37	37	37	37	37	37	37	37
38	38	38	38	38	38	38	38	38	38
39	39	39	39	39	39	39	39	39	39
40	40	40	40	40	40	40	40	40	40
41	41	41	41	41	41	41	41	41	41
42	42	42	42	42	42	42	42	42	42
43	43	43	43	43	43	43	43	43	43
44	44	44	44	44	44	44	44	44	44
45	45	45	45	45	45	45	45	45	45
46	46	46	46	46	46	46	46	46	46
47	47	47	47	47					

045-1115-0

Listing of Filename = E34, Filetype = EXEC

```
&TYPE OFF
STATE E34 DATA
&IF &INDEX0 NE 0 &GOTO -NOCDS
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE34 RAM
DETACH RAMIS BR
ERASE E34 DATA
&EXIT
-NOCDS &PRINT NO TYPE2 CARDS FOUND -- FUNCTION TERMINATING
```

Listing of Filename = RE34, Filetype = RAM

```
REVISE
READ E34 DATA
RECORD 80
FORM 9,X18,4,4,X16,1,1,3,4,5
ORDER 49,1,2,48,51,50,46,47
KEY 1,2,46,49
INCLUDE 46
FILE COURSE
END
```


ROOT EXECUTIVE: E51

DATA BASE: Course Master
Course Scratch

FUNCTION: Recreate the Scratch data base using the records from
one User-selected school in the Master data base

The first step in the recreation of the Scratch data base is the erase of the existing Scratch copy.

After being prompted, the User must supply the 4-character name of the school of interest.

The Master data base is then dumped into card-image format onto a temporary file, selecting only those records associated with the school chosen by the User. The temporary file is then used as input to recreate the Scratch data base in its entirety.

At the successful conclusion of this Executive Sequence the contents of the Master data base are unchanged. The new Scratch data base will contain only the records associated with the selected school.

Executive Sequence E51 Logic

The components of Executive Sequence E51 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows:

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E51	EXEC	
(2)	X68	RUNPROC	
(3)	PEM20	PLI	(PL/I Program)
(4)	RE49	RAM	

Listing of Filename = E51, Filetype = EXEC

```

&TYPE OFF
ATTACH TEMP5 AS 193 BRIEF
&PRI * FILE - COURSE
&PRI * FUNCTION - SELECT SCHOOL FOR MODEL INPUT
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &EXIT
FILEDEF RAMUTIL1 DSK COURSE DUMP U LR 80 RE FB BL 800
&STACK KT
&STACK EXEC X68 &1
&STACK FIN
ATTACH RAMIS ALL BR
FILEDEF 6 MSG KILL
EXEC RAMIS
DETACH RAMIS BR
&STACK RT
FILEDEF RAMUTIL1 CLEAR
FILEDEF 6 CONO
&STACK KT
&STACK L /D=/
&STACK Q
EDIT MSG KILL
&PRI &1 SCHOOL DUMPED TO DISK FILE
FILEDEF TRANS DSK UREFOR COURSE U LR 218 RE F
FILEDEF CARDS DSK COURSE DUMP U LR 80 RE FB BL 800
LOAD PGM20 (CLEAR LIB) PLILIB
START (BRIEF)
FILEDEF TRANS CLEAR
FILEDEF CARDS CLEAR
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE49 RAM
DETACH RAMIS BR
DETACH 193 BR
&EXIT

```

Listing of Filename = X68, Filetype = RUNPROC

```
DELETE
FILE RAMEXEC
1=OUT=X68,$
END
CATALOG X68
DUMP
FILE COURSE
PRINT ASN AND SAVE
IF SCH IS 61
END
END CATALOG
```

Listing of Filename = RE49, Filetype = RAM

```
ERASE
FILE MODCOURSE
END
INPUT
READ UREFOR COURSE
RECORD 218
FORM 4,4,1,10,16,3,4,3,3,5,5,2,5,5,5,5,4,4,3,4,3,3,5,5,3,3,4,3,3,5,5
FORM 4,5,2,2,4,3,3,2,6,5,4,5,10,4,5,1,9,3,1
SET 1
SEARCH FORWARD
FILE MODCOURSE
END
```

ROOT EXECUTIVE: E50

DATA BASE: Course Master
Course Scratch

FUNCTION: Recreate the Scratch data base using the records
from all Schools in the Master data base

The first step in the recreation of the Scratch data base is the erase of the existing Scratch copy.

The Master is then dumped into card-image format onto a temporary dataset. This file is then used as input to recreate the Scratch data base in its entirety.

Executive Sequence E50 Logic

The components of Executive Sequence E50 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E50	EXEC	
(2)	RE45	RAM	
(3)	PGM20	PLI	(PL/I Program)
(4)	RE49	RAM	

Listing of Filename = E50, Filetype = EXEC

```
&TYPE OFF
ATTACH TEMP5 AS 193 BRIEF
FILEDEF RAMUTIL1 DSK COURSE DUMP U LR 80 RE FB BL 800
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE45 RAM
DETACH RAMIS BR
FILEDEF RAMUTIL1 CLEAR
FILEDEF TRANS DSK UREFOR COURSE U LR 218 RE F
FILEDEF CARDS DSK COURSE DUMP U LR 80 RE FB BL 800
LOAD PGM20 (CLEAR LIBE) PLILIB
START (BRIEF)
FILEDEF TRANS CLEAR
FILEDEF CARDS CLEAR
&STACK KT
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMISIN RE49 RAM
DETACH 193 BRIEF
DETACH RAMIS BR
&EXIT
```

Listing of Filename = RE45, Filetype = RAM

```
DUMP
FILE COURSE
PRINT ASN AND SAVE
END
```

Listing of Filename = RE49, Filetype = RAM

```
ERASE
FILE MODCOURSE
END
INPUT
READ UREFOR COURSE
RECORD 218
FORM 4,4,1,10,16,3,4,3,3,5,5,2,5,5,5,5,4,4,3,4,3,3,5,5,3,3,4,3,3,5,5,3
FORM 4,5,2,2,4,3,3,2,6,5,4,5,10,4,5,1,9,3,1
SET 1
SEARCH FORWARD
FILE MODCOURSE
END
```

ROOT EXECUTIVE: E58

DATA BASE: Course Master

FUNCTION: Dump all records to the User's terminal

This Executive Sequence produces a formatted dump to the User's terminal of all of the records of the Course Master data base.

Executive Sequence E58 Logic

The components of Executive Sequence E58 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E58	EXEC	
(2)	RE45	RAM	
(3)	PGM20	PLI	(PL/1 Program)

Listing of Filename = E58, Filetype = EXEC

```

&TYPE OFF
ATTACH TEMP5 AS 193 BRIEF
FILEDEF RAMUTIL1 DSK COURSE DUMP U LR 80 RE FB BL 800
&STACK KT
ATTACH RAMIS ALL BR
EXEC RAMISIN RE45 RAM
DETACH RAMIS BR
FILEDEF RAMUTIL1 CLEAR
FILEDEF DUMP DSK COURSE DUMP U LR 80 RE FB BL 800
&STACK RT
LOAD PGM19 (CLEAR LIBE) PLILIB
START (BRIEF)
DETACH 193 BRIEF
FILEDEF DUMP CLEAR

```

Listing of Filename = RE45, Filetype = RAM

```

DUMP
FILE COURSE
PRINT ASN AND SAVE
END

```

ROOT EXECUTIVE: E37

DATA BASE: Course Scratch

FUNCTION: Dump all records to the User's terminal

This Executive Sequence produces a formatted dump to the User's terminal of all of the records of the Course Scratch data base.

Executive Sequence E37 Logic

The components of Executive Sequence E37 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	E37	EXEC	
(2)	RE37	RAM	
(3)	PGM19	PLI	(PL/1 Program)

Listing of Filename = E37, Filetype = EXEC

```
&TYPE OFF
ATTACH TEMPS AS 193 BR
FILEDEF RAMUTIL1 DSK MCOURSE DUMP U LR 80 RE FB BL 800
&STACK KT
ATTACH RAMIS ALL BR
EXEC RAMISIN RE37 RAM
DETACH RAMIS BR
FILEDEF RAMUTIL1 CLEAR
FILEDEF DUMP DSK MCOURSE DUMP U LR 80 RE FB BL 800
&STACK RT
LOAD PGM19 (CLEAR LIBE) PLILIB
START (BRIEF)
DETACH 193 BR
FILEDEF DUMP CLEAR
```

Listing of Filename = RE37, Filetype = RAM

```
DUMP
FILE MODCOURSE
PRINT ASN AND SAVE
END
```

ROOT EXECUTIVE: W40

DATA BASE: Course Scratch

FUNCTION: (1) Add a Course to an existing School, /or/
(2) Add a new School and Course

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD40/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD40/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W40 Logic

The components of Executive Sequence W40 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W40	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RW40	RAM	

Listing of Filename = W40, Filetype = EXEC

LTYP OFF
EXEC ESUB1 WPD40 RW40

Listing of Filename = ESub1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RW40, Filetype = RAM

```
REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,1,10,16,3,4,3,3,5,5,2,5,5,5,5,4,4,3,4,3,3,5,5,3,3
FORM 4,3,3,5,5,3,4,5,2,2,4,3,3,2,6,5,4,5,10
KEY 1,2
INCLUDE 1
FILE MODCOURSE
END
```

Listing of Filename = WPD40, Filetype = DATA

```

1* THIS IS EXECUTIVE NUMBER W40
1* FILE - COURSE SCRATCH DATA BASE
1* FUNCTION - ADD A NEW SCHOOL.
1*          AND/OR ADD A NEW COURSE
1*          TO AN EXISTING SCHOOL...
2SCH      11 4      1      1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP      21 4      1      5 4
3* ENTER COURSE CDP (CDP), A4
2DEL      31 1 1      2      9 1
3* ENTER DELETE FLAG (DEL), A1
3* 1 = COURSE ACTIVE
3* 2 = COURSE HAS BEEN DELETED
2CTLG      4110      2      1010
3* ENTER COURSE CATALOG NUMBER, A4
2CRS      5116      2      2016
3* ENTER COURSE TITLE (CRS), A16
2CONV1     62 0.0      240.0      36 3
3* ENTER CONVENINGS NUMBER1 (CONV1), I3
2LEN1      73 0.0      240.0      4 39 4
3* ENTER COURSE LENGTH #1 (LEN1), F4.1
2CAP1      82 0.0      240.0      43 3
3* ENTER COURSE CAPACITY #1 (CAP1), I3
2BCAP1     92 0.0      240.0      46 3
3* ENTER BUPERS CAPACITY #1 (BCAP1), I3
2DMD1     102 0.0      240.0      49 5
3* ENTER COURSE DEMAND #1 (DMD1), I5
2BDMD1    112 0.0      240.0      54 5
3* ENTER BUPERS DEMAND #1 (BDMD1), I5
2OFST     112 0.0      240.0      59 2
3* ENTER SCHEDULE OFFSET (OFST), I2
2PFAIL    133 0.0      240.0      5 61 5
3* ENTER % FAILURE RATE (PFAIL), F5.3
2NADIS    143 0.0      240.0      5 66 5
3* ENTER % NONAC DISENROLL (NADIS), F5.3
2NOSHOW   153 0.0      240.0      5 71 5
3* ENTER % NO-SHOW (NOSHOW), F5.3
2SETB     163 0.0      240.0      5 76 5
3* ENTER % SETBACKS (SETB), F5.3
2BKLG     172 0.0      240.0      81 4
3* ENTER NUMBER OF BACKLOGS (BKLG), I4
2JNO      181 4      85 4
3* COURSE J-NUMBER (JNO), A4
2CONV2     192 0.0      240.0      89 3
3* ENTER CONVENINGS NUMBER2 (CONV2), I3
2LEN2     203 0.0      240.0      4 92 4
3* ENTER COURSE LENGTH #2 (LEN2), F4.1
2CAP2     212 0.0      240.0      96 3
3* ENTER COURSE CAPACITY #2 (CAP2), I3
2BCAP2    222 0.0      240.0      99 3
3* ENTER BUPERS CAPACITY #2 (BCAP2), I3
2DMD2     232 0.0      240.0     102 5
3* ENTER COURSE DEMAND #2 (DMD2), I5
2BDMD2    242 0.0      240.0     107 5
3* ENTER BUPERS DEMAND #2 (BDMD2), I5

```

Listing of Filename = WPD40, Filetype = DATA (Continued)

2CHWK2	252	0.0	240.0	112 3
3* ENTER CHANGE WEEK #2 (CHWK2), I3				
2CONV3	262	0.0	240.0	115 3
3* ENTER CONVENINGS NUMBER3 (CONV3), I3				
2LEN3	273	0.0	240.0	118 4
3* ENTER COURSE LENGTH #3 (LEN3), F4.1				
2CAP3	282	0.0	240.0	122 3
3* ENTER COURSE CAPACITY #3 (CAP3), I3				
2BCAP3	292	0.0	240.0	125 3
3* ENTER BUPERS CAPACITY #3 (BCAP3), I3				
2DMD3	302	0.0	240.0	128 5
3* ENTER COURSE DEMAND #3 (DMD3), I5				
2BDMD3	312	0.0	240.0	133 5
3* ENTER BUPERS DEMAND #3 (BDMD3), I5				
2CHWK3	322	0.0	240.0	138 3
3* ENTER CHANGE WEEK #3 (CHWK3), I3				
2PAOB	332	0.0	240.0	141 4
3* ENTER PLANNED AOB (PAOB), I4				
2AFAIL	343	0.0	240.0	145 5
3* ENTER % ACAD FAILURES (AFAIL), F5.3				
2PRTY	352	0.0	240.0	150 2
3* ENTER COURSE PRIORITY (PRTY), I2				
2CTYPE	361	2	2	152 2
3* ENTER COURSE TYPE (CTYPE), A2				
2PNEC	371	4	2	154 4
3* ENTER PRIMARY NEC (PNEC), A4				
2UCAP	382	0.0	240.0	158 3
3* ENTER % CAPACITY UTILIZED (UCAP), I3				
2UDEM	392	0.0	240.0	161 3
3* ENTER % DEMAND UTILIZED (UDEM), I3				
2FPRTY	402	0.0	240.0	164 2
3* ENTER FTC PRIORITY (FPRTY), I2				
2RDTE	412	0.0	240.0	166 6
3* ENTER REVISION DATE (RDTE),				
2HSETB	423	0.0	240.0	5171 5
3* ENTER HIST. SETBACK (HSETB), F5.3				
2TINSTR	433	0.0	240.0	4177 4
3* ENTER TOT INSTRS REQD (TINSTR), F4.1				
2SUIC	441	5	2	181 5
3* ENTER STUDENT UIC (SUIC), A5				
2CCMM	45110		2	18610
3* ENTER CCMM, A10				

ROOT EXECUTIVE: W41

DATA BASE: Course Scratch

FUNCTION: Add a new Student Instructor Ratio (SIR) and a new Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD41/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD41/DATA is described fully in the documentation associated with the PL/1 program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W41 Logic

The components of Executive Sequence W41 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W41	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/1 Program)
(4)	RW41	EXEC	

Listing of Filename = W41, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 WPD41 RW41
```


Listing of Filename = ESUB1, Filetype = EXEC

```

&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT

```

Listing of Filename = RW41, Filetype = RAM

```

REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,X187,4,5,1,9,3,1
ORDER 1,2,46,47,48,49,50,51
KEY 1,2,46
INCLUDE 46
FILE MODCOURSE
END

```

Listing of Filename = WPD41, Filetype = DATA

```

1* THIS IS EXECUTIVE NUMBER W41
1* FILE - COURSE SCRATCH DATA BASE
1* FUNCTION - ADD A STUDENT/INSTR RATIO
1*             AND AN INSTRUCTOR TO AN
1*             EXISTING COURSE...
2SCH          11 4              1              1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP          21 4              1              5 4
3* ENTER COURSE CDP (CDP), A4
2SIR          463 0.0          140.0          4196 4
3* ENTER STUDENT/INSTR RATIO (SIR), F4.1
2CHRS         473 0.0          240.0          2200 5
3* ENTER INSTR CONTACT HRS (CHRS), F5.1
2CTYP         481 1              1              205 1
3* ENTER COURSE TYPE (CTYP), A1
2ID           491 9              1              206 9
3* ENTER INSTRUCTOR ID (ID), A9
2QUAL         501 3              2              215 3
3* ENTER INSTR % QUALIFIED (QUAL), A3
2ASN          512 1 0.0          140.0          218 1
3* ENTER ASSIGNED FLAG (ASN), I1

```

ROOT EXECUTIVE: W42

DATA BASE: Course Scratch

FUNCTION: Add a new Instructor to an existing Student Instructor Ratio (SIR)

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD42/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD42/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W42 Logic

The components of Executive Sequence W42 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>	
(1)	W42	EXEC	
(2)	ESUB1	EXEC	
(3)	PROMPT	PLI	(PL/I Program)
(4)	RW42	RAM	

Listing of Filename = W42, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 WPD42 RW42
&EXIT
```

Listing of Filename = ESUB1, Filetype = EXEC

```

&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT

```

Listing of Filename = RW42, Filetype = RAM

```

REVISE
READ TRANS FILE
RECORD 250
FORM 4,4,X187,4,X6,9,3,1
ORDER 1,2,46,49,50,51
KEY 1,2,46,49
INCLUDE 49
FILE MODCOURSE
END

```

Listing of Filename = WPD42, Filetype = DATA

```

1* THIS IS EXECUTIVE NUMBER W42
1* FILE - COURSE SCRATCH DATA BASE
1* FUNCTION - ADD A NEW INSTRUCTOR TO AN
1*           EXISTING STUDENT/INSTR
1*           RATIO AND COURSE...
2SCH          11 4              1              1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP          21 4              1              5 4
3* ENTER COURSE CDP (CDP), A4
2SIR          463 0.0          140.0          4196 4
3* ENTER STUDENT/INSTR RATIO (SIR), F4.1
2CHRS         473 0.0          240.0          2200 5
3* ENTER INSTR CONTACT HRS (CHRS), F5.1
2CTYP         481 1              1              205 1
3* ENTER COURSE TYPE (CTYP), A1
2ID           491 9              1              206 9
3* ENTER INSTRUCTOR ID (ID), A9
2QUAL         501 3              2              215 3
3* ENTER INSTR % QUALIFIED (QUAL), A3
2ASN          512 1 0.0          140.0          218 1
3* ENTER ASSIGNED FLAG (ASN), I1

```

ROOT EXECUTIVE: W61

DATA BASE: Course Scratch

FUNCTION: Change an existing Field

This single executive serves to force entry to the SCAN mode of the RAMIS data management system. After SCAN mode has been successfully entered, the user may direct change of existing field(s) interactively through his terminal.

Terminal entry requirements of the RAMIS SCAN mode are fully covered in the NCSS vendor's documentation.

The DOTS User's Manual lists the data field names and identification numbers as appropriate for the Course Scratch data base. This list will not be repeated in this document.

Listing of Executive W61 (SCAN Mode Entry)

```
&TYPE OFF
&BEGSTACK
KT
SCAN
FILE MODCOURSE
&ENDSTACK
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
&EXIT
```


ROOT EXECUTIVE: W62

DATA BASE: Course Scratch

FUNCTION: Delete a School

The components of Executive Sequence W62 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	W62	EXEC
(2)	WX62	RUNPROC

Listing of Filename = W62, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE W62
&PRI * FILE - MODCOURSE
&PRI * FUNCTION - DELETE AN ENTIRE SCHOOL
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -OK
&PRI * WRONG NUMBER OF ARGUMENTS - RETRY
&GOTO -LP1
-OK &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC WX62 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = WX62, Filetype = RUNPROC

```
DELETE  
FILE RAMEXEC  
1=OUT=WX62.S  
END  
CATALOG WX62  
DELETE  
FORM 4  
SET 1  
FILE MODCOURSE  
&1  
END  
END CATALOG
```

ROOT EXECUTIVE: W63

DATA BASE: Course Scratch

FUNCTION: Delete a Course

The components of Executive Sequence W63 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	W63	EXEC
(2)	WX63	RUNPROC

Listing of Filename = W63, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER W63
&PRI * FILE - MODCOURSE
&PRI * FUNCTION - DELETE A COURSE
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK &IF &1 EQ OUT &GOTO -OUT
&SAV1 = &1
-LP2 &PRI *
&PRI * ENTER COURSE CDP (CDP), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -OK
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP2
-OK &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC WX63 &SAV1 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = WX63, Filetype = RUNPROC

```
DELETE  
FILE RAMEXEC  
1=OUT=WX63,$  
END  
CATALOG WX63  
DELETE  
FORM 4,X4,4  
SET 2  
FILE MODCOURSE  
&1  
END  
END CATALOG
```


ROOT EXECUTIVE: W64

DATA BASE: Course Scratch

FUNCTION: Delete an existing Instructor

The sequence described below forms a CLASS A Prompting Type Executive. The file WPD64/DATA contains both the textual character strings to be used in prompting the User and all necessary formatting and editing criteria as required to process the entries made at the terminal.

The record format of the file WPD64/DATA is described fully in the documentation associated with the PL/I program called 'PROMPT' and is not duplicated herein; a listing of the contents of the file is included in this section.

Executive Sequence W64 Logic

The components of Executive Sequence W64 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	W64	EXEC
(2)	ESUB1	EXEC
(3)	PROMPT	PLI (PL/I Program)
(4)	RW64	RAM

Listing of Filename = W64, Filetype = EXEC

```
&TYPE OFF
EXEC ESUB1 WPD64 RW64
&EXIT
```

Listing of Filename = ESUB1, Filetype = EXEC

```
&TYPE OFF
FILEDEF TAB DSK &1 DATA LR 80 RE F
FILEDEF TRANS DSK TRANS FILE LR 250 RE F
LOAD PROMPT (CLEAR LIBE) PLILIB
START (BRIEF)
&IF &INDEX0 NE 0 &GOTO -END
&STACK KT
ATTACH RAMIS ALL BRIEF
FILEDEF 6 MSG KILL
EXEC RAMISIN &2 RAM
DETACH RAMIS BRIEF
EXEC RAMOUT
-END FILEDEF TAB CLEAR
FILEDEF TRANS CLEAR
&EXIT
```

Listing of Filename = RW64, Filetype = RAM

```
DELETE
READ TRANS FILE
RECORD 250
FORM 4.4,X187.4,X6.9
ORDER 1.2.46.49
SET 49
FILE MODCOURSE
END
```

Listing of Filename = WPD64, Filetype = DATA

```
1* THIS IS EXECUTIVE NUMBER W64
1* FILE - COURSE SCRATCH DATA BASE
1* FUNCTION - DELETE AN INSTRUCTOR FROM
1*           AN EXISTING STUDENT/INSTR
1*           RATIO AND COURSE...
2SCH          11 4          1          1 4
3* ENTER SCHOOL CODE (SCH), A4
2CDP          21 4          1          5 4
3* ENTER COURSE CDP (CDP), A4
2SIR          463 0.0        140.0      4196 4
3* ENTER STUDENT/INSTR RATIO (SIR), F4.1
2ID           491 9          1          206 9
3* ENTER INSTRUCTOR ID (ID), A9
```

ROOT EXECUTIVE: W65

DATA BASE: Course Scratch

FUNCTION: Delete a Student/Instructor Ratio (SIR)

The components of Executive Sequence W65 and the chronological order of execution are indicated in the table presented below. A listing of these files (except for programs) follows.

This Executive Sequence is referred to in the DOTS User documentation as a CLASS B Prompting Type Executive.

<u>Sequence</u>	<u>Filename</u>	<u>Filetype</u>
(1)	W65	EXEC
(2)	WX65	RUNPROC

Listing of Filename = W65, Filetype = EXEC

```

&TYPE OFF
&PRI * THIS IS EXECUTIVE NUMBER W65
&PRI * FILE - MODCOURSE
&PRI * FUNCTION - DELETE A STUDENT/INSTRUCTOR RATIO FROM A COURSE
&PRI * ENTER OUT AT ANY TIME FOR PREMATURE EXIT
-LP1 &PRI *
&PRI * ENTER SCHOOL CODE (SCH), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK1
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP1
-CK1 &IF &1 EQ OUT &GOTO -OUT
&SAV1 = &1
-LP2 &PRI *
&PRI * ENTER COURSE CDP (CDP), A4
&READ ARGS
&IF &INDEX EQ 1 &GOTO -CK2
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP2
-CK2 &IF &1 EQ OUT &GOTO -OUT
&SAV2 = &1
-LP3 &PRI *
&PRI * ENTER STUDENT/INSTRUCTOR RATIO (SIR), F4.1
&READ ARGS
&IF &INDEX EQ 1 &GOTO -OK
&PRI * WRONG NUMBER OF ARGUMENTS -- RETRY
&GOTO -LP3
-OK &IF &1 EQ OUT &GOTO -OUT
&STACK KT
&STACK EXEC WX65 &SAV1 &SAV2 &1
&STACK FIN
ATTACH RAMIS ALL BR
&STACK RT
EXEC RAMIS
DETACH RAMIS BR
-OUT &EXIT

```

Listing of Filename = WX65, Filetype = RUNPROC

```
DELETE
FILE RAMEXEC
1=OUT=WX65.$
END
CATALOG WX65
DELETE
FORM 4,X4,4,X4,4
ORDER 1,2,46
SET 46
FILE MODCOURSE
&1
END
END CATALOG
```


PROGRAM NAME: PGM5
TYPE: PL/1
SYSTEM: Data Base Maintenance
NCSS FILENAME/FILETYPE: PGM5/PL1

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

This program converts the data found on the weekly Instructor Time Cards to a transaction format for entry to the Instructor Master data base. Output records (transactions) from this program are subsequently processed into the data base by the RAMIS data maintenance UPDATE function RE22/RAM (filename/filetype).

Any keypunch errors (invalid characters) found within the input record numeric fields will be diagnosed by this program.

USAGE

Program PGM5 is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC</u> <u>Sequence</u>	<u>Data Base</u>
E22E	Instructor Master

INPUT FORMATS

Input record format for PGM5 is found on the following diagram titled "Instructor Data Base Weekly Time Card Format".

The User is terminal prompted for the time card processing date. This date takes the format YYMMDD, e.g., 750915. After verification of the User response, the date input is moved to the output record in positions 18 through 23, inclusive. This date will appear in every output transaction in the same positions.

INSTRUCTOR DATA BASE WEEKLY TIME CARD FORMAT

INSTRUCTOR FILE



80-Column Card Punch Layout

[illegible]A = LOCATION OF ASSUMED
DECIMAL POINT[illegible]

0-5111-656

OUTPUT FORMAT FOR PGM5

Logical Record Length: 121 Bytes

PL/1 Base Data Structure Name: RTRANS

Output PL/1 Filename: TRANS

<u>Start Record Position</u>	<u>Byte Length</u>	<u>PL/1 Identifier</u>	<u>Format</u>	<u>Description</u>
1	17	R17	A17	Direct copy of the first 17 chars of the input time card
18	6	RD	16	Time card transaction date in format YYMMDD as provided by the User terminal
24/121 = Repeating 14 groups of the following seven (7) character sequence:				
1-3		TTT	A3	Instructor time type; A1 through A7, B1 through B6, and B6A are legal.
4-7		RTIM	F4.1	Time expended in the indicated time type

NOTE - As many time-type groups as are
required to contain the input
time card data will be used in
any single output transaction.
The remainder, if any, will be
left blank.

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/I -PGM5- FLOWCHARTS

PL/I MODULE

(LIST,NAME,SEQ,SEQ)

CARD NO

0000

CONTENTS

0000

```


1  OPTION PACKED,COMPRESS
2  PGM5:  /O INSTRUCTOR FILE TIME CARD PROCESSOR: PRI/25/APR/75 0/
3  PROC OPTIONS (MAIN) ;
4
5  DECLARE NC      FIXED BIN STATIC INIT ( 0 );
6  NT             FIXED BIN STATIC INIT ( 0 );
7  NER            FIXED BIN STATIC INIT ( 0 );
8  NTER           FIXED BIN STATIC INIT ( 0 );
9  CARD           CHAR (80) STATIC;
10 F17            CHAR (17) DEF CARD POS (1);
11 P59            CHAR (59) DEF CARD POS (1);
12 REP            CHAR (80) STATIC;
13 R1              CHAR (85) STATIC INIT ;
14
15 ** CONVERSION ERROR ON INPUT CARD - XX,XXX - FIELD CONTAINS XXX ;
16 PRI            PICTURE 'ZZ,ZZ9' DEF R1 POS (37);
17 FR2            CHAR (3) DEF R1 POS (61);
18 TMS (14) CHAR (3) DEF CARD POS (18);
19 LOTE           FIXED DEC (8) STATIC;
20 I J, K         FIXED BIN STATIC;
21 CTIME          FIXED DEC (3,1) STATIC;
22 TYPE (14) CHAR (3) STATIC ; IT
23 I 'A1 ' 'A2 ' 'A3 ' 'A4 ' 'A5 ' 'A6 ' 'A7 '
24 I 'B1 ' 'B2 ' 'B3 ' 'B4 ' 'B5 ' 'B6 ' 'B6A ' ;
25 FILL           PICTURE 'Z,ZZ9' STATIC ;
26
27 DECLARE I RTRANS STATIC;
28 2 R17 CHAR (17);
29 2 RD PICTURE '9999999';
30 2 IIELDS (14);
31 I TTT CHAR (3);
32 RTIM PICTURE '999.9';
33 TCLR CHAR (98) BASED (PC) ;
34
35 STARTERRUPP:
36 OPEN FILE (CARDS) RECORD INPUT;
37 FILE (RTRANS) RECORD OUTPUT;
38 FILE (TRANS) RECORD OUTPUT ;
39 ON ENDFILE (CARDS) GO TO WRAPUP ;
40 PC = ADDR ( IIELDS ) ;
41
42 GET_UPDATE_DATE:
43 ON CONVERSION BEGIN ;
44 DISPLAY ( '** CONVERSION ERROR # ' || ONCODE ) ;
45 GO TO DCC1 ;
46 END ;
47
48 DCC1: DISPLAY ( '** ENTER TRANSACTION DATE - YYYYMM - 6 DIGITS' ) ;
49 REPLY ( REP ) ;
50 J = INDEX ( REP, ' ' ) - 1 ;
51 IF ( J <= 0 ) THEN GO TO BUST_DATE1 ;
52 GET STRING ( SUBSTR( REP, 1, J ) ) EDIT ;
53 ILOTE ( F17 ) ;
54 IF ( LOTE < 750000 ) THEN GO TO BUST_DATE2 ;
55 RD = LOTE ;
56 GO TO MAINLINE ;
57
58 BUST_DATE1:
59 DISPLAY ( '** DATE FORMAT INDETERMINATE, TRY AGAIN' ) ;
60 GO TO DCC1 ;
61
62 BUST_DATE2:
63 DISPLAY ( '** DATE VALUE LESS THAN 75XXXX, TRY AGAIN' ) ;
64 GO TO DCC1 ;
65
66 MAINLINE:
67 ON CONVERSION BEGIN ;
68 NER = NER + 1 ;
69 FR2 = NC ;
70 FR2 = ONSOURCE ;
71 DISPLAY ( R1 ) ;
72 DISPLAY ( '** FIRST 59 CHARACTERS OF CARD IMAGE ARE ' ) ;
73 DISPLAY ( '---' || P59 || '---' ) ;
74 WRITE FILE (RTRANS) FROM (CARD) ;
75 NTER = NTER + 1 ;
76 DISPLAY '** TRANSACTION WILL BE IGNORED' ;
77 GO TO R1 ;
78 END ;
79
80 R1: READ FILE (CARDS) INTO (CARD) ;
81 NC = NC + 1 ;
82 TCLR = ' ' ;
83 R17 = F17 ;
84 J = 0 ;
85
86 TLOOP: DO K = 1 TO 14 ;
87 IF ( TMS(K) = ' ' ) THEN GO TO ETLOOP ;
88 GET STRING ( TMS(K) ) EDIT ;
89 ICTIME ( F17, 1 ) ;
90 J = J + 1 ;
91 TTT (J) = TYPE (K) ;
92 RTIM (J) = CTIME ;
93 ETLOOP: END TLOOP ;
94
95 WRITE FILE (TRANS) FROM (RTRANS) ;
96 NT = NT + 1 ;
97 GO TO R1 ;
98
99 WRAPUP:
100 DISPLAY ;
101 ** INSTRUCTOR TIME TRANSACTION PROCESSING HAS COMPLETED ;
102 FILL = NC ;
103 DISPLAY ( '** TOTAL INPUT CARDS READ = ' || FILL ) ;
104 FILL = NT ;
105 DISPLAY ( '** TOTAL VALID OUTPUT TRANSACTIONS PROCESSED = '
106 || FILL ) ;
107 FILL = NTER ;
108 DISPLAY ( '** TOTAL NUMBER CARD ERRORS = ' || FILL ) ;
109 FILL = NTER ;
110 DISPLAY ( '** TOTAL NUMBER CARD IMAGES IN ERROR-TRANSACTION FILE = ' || FILL ) ;

```


TAEG REPORT NO. 29

CARD NO.	INPUT LISTING	CONTENTS	PL/1 -PGMS- FLOWCHARTS
	****		****
110			00010900
111	WINDUP:		00011000
112		CLOSE FILE (CARDS).	00011100
113		FILE (STRANS).	00011200
114		FILE (TRANS) 1	00011300
115			00011400
116	END PGMS :		00011500

CHART TITLE - PROC PGM5 OPTIONS (MAIN)



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGM5- FLOWCHARTS

PAGE 01

CHART TITLE - ON-UNIT ACTION BLOCKS

```

-----
/ 00000039 /
01.05--->*
.ON-UNIT01

00000038 | NOTE 01
* * * * *
* ON ENDFILE *
* (CARDS) *
* * * * *
|
* * *
* 2.13 *
* * *
WRAPUP
END .ON-UNIT01
    
```

```

-----
/ 00000042 /
01.07--->*
.ON-UNIT02

00000042 | NOTE 02
* * * * *
* ON CONVERSION *
* * * * *
* BEGIN *
* * * * *
|
00000043 | 03
/ /
/ DISPLAY 1'00 /
/ CONVERSION /
/ ERROR 0'11 /
/ ONCODE) /
/ /
|
* * *
* 1.09 *
* * *
DCC1
END .ON-UNIT02
    
```

```

-----
/ 00000065 /
02.01--->*
.ON-UNIT03

00000065 | NOTE 04
* * * * *
* ON CONVERSION *
* * * * *
* BEGIN *
* * * * *
|
00000066 | 05
/ /
/ ASSIGNMENT(S) /
/ /
|
00000069 | 06
/ /
/ DISPLAY (M1) /
/ /
|
00000070 | 07
/ /
/ DISPLAY 1'00 /
/ FIRST 50 /
/ CHARACTERS OF /
/ CARD IMAGE ARE /
/ " " /
/ /
|
00000071 | 08
/ /
/ DISPLAY 1'00 /
/ " " 11 P99 11 /
/ " " /
/ /
|
00000072 | 09
/ /
/ WRITE FILE /
/ (TRANS) FROM /
/ (CARJ) /
/ /
|
00000073 | 10
/ /
/ ASSIGNMENT(S) /
/ /
|
00000074 | 11
/ /
/ DISPLAY 1'00 /
/ TRANSACTION /
/ WILL BE /
/ IGNORED" /
/ /
|
* * *
* 2.02 *
* * *
R1
END .ON-UNIT03
    
```


TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGM5- FLOWCHART5

PAGE 04

CHART TITLE - GET/PUT, FORMAT STATEMENTS

```
00000051 .GET/PUT 001 GET STRING (SUBSTR (REP,L,J)) EDIT (1,DT) (F (J))
00000086 .GET/PUT 002 GET STRING (TIMS (K)) EDIT (1,TIME) (F (3,1))
```

PROGRAM NAME: PGM7

TYPE: PL/1

SYSTEM: Data Base Maintenance

ACCESS FILENAME/FILETYPE: PGM7/PLI

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

Use of the RAMIS data maintenance function DUMP produces an 80-Byte (card image) output file, regardless of the length of the individual RAMIS records. As many card images per RAMIS record as required will be used to represent RAMIS records longer than 80 Bytes.

For the Instructor data base, the field positions in the output of the DUMP are indicated in the following sample RAMIS output:

* EBCDIC RECORD LENGTH 80 CHARACTERS

FIELD NAME	FORMAT	LENGTH
ID	A 9	9
NME	A 16	16
IN	A 2	2
RATE	A 5	5
SCH	A 4	4
REP	I 4	4
ROT	I 4	4
PNEC	A 4	4
SNEC	A 4	4
CDP	A 4	4
TTL	A 16	16
ONB	A 1	1
LDTE	I 6	6
TT	A 3	3
CW	F4 .1	4
QTD	F5 .1	5
YTD	F6 .1	6

Note that one slack byte (X) was included on the first card to prevent split of a field across logical record boundaries. Also, only 18 Bytes are required on the 2nd card image.

Inputs to RAMIS data maintenance functions must be singular records. The function of program PGM7 is to convert the multiple dump format to a single logical record per pair of input records.

For the Instructor file, using input as indicated above, the output record is composed as follows:

Logical Record Length: 97 Bytes

PL/1 Base Data Structure Name: ROUT

Output PL/1 Filename: TRANS

First 79 Characters = Direct copy from input card image number 1

Characters 80 through 97, Inclusive: Direct copy from first
18 characters of input
card image number 2

USAGE

Program PGM7 is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC Sequence</u>	<u>Data Base</u>
E32	Instructor
E27	Instructor

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 -PGM7- FLOWCHARTS

PL/1 MODULE

(LIST,NAMSQ,SOURCEQ)

CARD NO



CONTENTS

```

1  OPTION PACK1,COMPRESS
2  PGM7: /* COMAIN: 2 INSTR DUMP IMAGES TO 1 LREC - TUE/13/MAY/75 */ 00000100
3  PROC OPTIONS (MAIN) : 00000200
4  00000300
5  DECLARE BUFF (259) CHAR (1) STATIC;
6  C1 CHAR (80) BASED (P1); 00000400
7  C2 CHAR (80) BASED (P2); 00000500
8  ROUT CHAR (97) BASED (P3); 00000600
9  BEOF BIT (1) STATIC INIT ( '0'B ); 00000700
10 NC FIXED BIN STATIC INIT ( 0 ); 00000800
11 MN FIXED BIN (31,0) STATIC INIT ( 0 ); 00000900
12 M1 CHAR (39) STATIC INIT ( 0 ); 00001000
13 ** TOTAL DUMP IMAGE COUNT = XX,XXX' ; 00001100
14 PML PICTURE 'ZZ,ZZ9' DEF M1 POS (34); 00001200
15 LML CHAR (5) STATIC INIT ( '0' ); 00001300
16 00001400
17 STARTERRUP: 00001500
18 P1 = ADDR ( BUFF(1) ) ; 00001600
19 P2 = ADDR ( BUFF(81) ) ; 00001700
20 OPEN FILE (DUMP) RECORD INPUT; 00001800
21 FILE (TRANS) RECORD OUTPUT ; 00001900
22 ON ENDFILE (DUMP) GO TO WINDUP ; 00002000
23 00002100
24 00002200
25 R1: READ FILE (DUMP) INTO (C1) ; 00002300
26 BEOF = '1'B ; 00002400
27 READ FILE (DUMP) INTO (C2) ; 00002500
28 BEOF = '0'B ; 00002600
29 NC = NC + 2 ; 00002700
30 WRITE FILE (TRANS) FROM (ROUT) ; 00002800
31 GO TO P1 ; 00002900
32 00003000
33 WINDUP: IF ( BEOF ) THEN 00003100
34 BUMEOF: DO ; 00003200
35 DISPLAY ( '** PROGRAM PGM7 FOUND ODD NUMBER DUMP IMAGES' ); 00003300
36 FM2 = NC ; 00003400
37 DISPLAY ( M1 ) ; 00003500
38 MN = 9 ; 00003600
39 END BUMEOF ; 00003700
40 CLOSE: CLOSE FILE (DUMP), FILE (TRANS) ; 00003800
41 END PGM7 ; 00003900
00004000

```


CHART TITLE - PROC PGM7 OPTIONS (MAIN)



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL PL/1 - PGM7 - FLUJCHART.

PAGE 4

CHART TITLE - ON-UNIT ACTION BLOCKS

```

/ 00000022 /
C1.0%--->*
.ON-UNIT01

      *
00000022 1  NOTE 31
* * * * *
* ON ENOFIE (DU*P) *
* * * * *

      |
      |
      |
      * * *
      * 1.11.
      * * *

      #INQUP

END .ON-UNIT01

```

PROGRAM NAME: PGM8

TYPE: PL/1

SYSTEM: Data Base Maintenance

NCSS FILENAME/FILETYPE: PGM8/PLI

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

Following a standard RAMIS data maintenance DUMP of the Instructor data base, PGM8 is used to cause a display of each of the records of the data base.

USAGE

Program PGM8 is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC Sequence</u>	<u>Data Base</u>
E30	Instructor Master
E35	Instructor Scratch

INPUT FORMAT

For the Instructor data base, the field positions in the output of the RAMIS DUMP are indicated in the following sample RAMIS output:

± EBCDIC RECORD LENGTH 80 CHARACTERS

FIELD NAME	FORMAT	LENGTH
ID	A 9	9
NAME	A 16	16
IN	A 2	2
RATE	A 5	5
SCH	A 4	4
REP	I 4	4
ROT	I 4	4
PNEC	A 4	4
SNEC	A 4	4
CDP	A 4	4
TTL	A 16	16
ONB	A 1	1
LDTE	I 6	6
		X 1
TT	A 3	3
CW	F4 .1	4
QTD	F5 .1	5
YTD	F6 .1	6

Note that one slack byte has been included on the first card image at position (X); this prevents split of a field across distinct logical record boundaries. Also, only 18 Bytes of the second card image are required to complete the RAMIS record.

OUTPUT RECORDS

Output of PGM8 is to the User terminal. Two (2) input card images are used in the construction of an output image. This is the minimum count. For each Course assigned to each Instructor, there will be an input record pair.

Output is composed to fit on the 80-character display face; essentially, an entire screen is required to display the data associated with a single Instructor.

A sample of the output is indicated in the following illustration titled "Sample Terminal Output of Program PGM8".

TAEG REPORT NO. 29

SAMPLE TERMINAL RUN OF PROGRAM PGM8

SCHOOL: COMM
INSTRUCTOR: RA SNYDER

RATE: RM2
ID: 175424494

REPORT: 1272
ROTATE: 676

PNEC:
SNEC: 95#6

	COURSE CDP: 538R !			COURSE CDP: 512F !			COURSE CDP: 512H !			COURSE CDP: 512K !		
	ONBOARD: YES !			ONBOARD: YES !			ONBOARD: YES !			ONBOARD: YES !		
	LUDATE: / / !			LUDATE: / / !			LUDATE: / / !			LUDATE: / / !		
	-CUR-	QTD-	YTD-	-CUR-	QTD-	YTD-	-CUR-	QTD-	YTD-	-CUR-	QTD-	YTD-
A1	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
A2	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
A3	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
A4	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
A5	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
A6	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
A7	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
B1	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
B2	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
B3	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
B4	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
B5	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
B6	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!
B6A	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!	.0	.0	.0!

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 -PGM8- FLOWCHARTS

PL/1 MODULE

LIST,NAMSQ,SOURCEQ

CARD NO

CONTENTS

```

1  OPTION PACKIF,COMPRESS
2  PGM8: /* PRINT INSTR. FILE FROM DISK DUMP - TUE/6/MAY/75 */
3  PROC OPTIONS (MAIN) ;
4
5  DECLARE I CARD1 STATIC,
6  2 ID CHAR (9);
7  2 NME CHAR (16);
8  2 IN CHAR (2);
9  2 RATE CHAR (5);
10 2 SCH CHAR (4);
11 2 REP CHAR (4);
12 2 ROT CHAR (4);
13 2 PNEC CHAR (4);
14 2 SNEC CHAR (4);
15 2 COP CHAR (4);
16 2 TTL CHAR (16);
17 2 OMR CHAR (1);
18 2 LUTE CHAR (6);
19 2 FILL CHAR (1);
20 1 CARD2 STATIC,
21 2 TT CHAR (3);
22 2 CT CHAR (4);
23 2 QTD CHAR (5);
24 2 YTD CHAR (6);
25 2 FIL2 CHAR (62) ;
26
27 DECLARE M1 CHAR (63) STATIC INIT 1
28 /** EUP DETECTED BEFORE ALL TIMES READ - CARD COUNT IS XX,XXX ***/
29 FILLM1 PICTURE 'ZZ,ZZ9' DEF M1 POS (55);
30 M1 CHAR (59) STATIC INIT 1
31 /** SEQUENCING ERROR # X IN PROCESSING INPUT RECORD # XX,XXX* */
32 FILLM3A CHAR (1) DEF M3 POS (23);
33 FILLM3R PICTURE 'ZZ,ZZ9' DEF M3 POS (54);
34 M2 CHAR (56) STATIC INIT 1
35 /** COURSE COP = XXXX, COURSE TITLE = 'XXXXXXXXXXXXX ***/
36 FILLM2A CHAR (4) DEF M2 POS (17);
37 FILLM2B CHAR (16) DEF M2 POS (38) ;
38
39 DECLARE OLDID CHAR (9) STATIC INIT ( ' ' );
40 L1 CHAR (78) STATIC INIT 1
41 * SCHOOL: XXXX RATE: XXXX REPORT: XX/XX PNO0004000
42 EC: XXXX' );
43 LSCH CHAR (4) DEF L1 POS (13);
44 LRTE CHAR (5) DEF L1 POS (41);
45 LREP CHAR (5) DEF L1 POS (48);
46 LPNEC CHAR (4) DEF L1 POS (75);
47 L2 CHAR (78) STATIC INIT 1
48 *INSTRUCTOR: XX XXXXXXXXXXXXXXXX ID: XXXXXXXX ROTATE: XX/XX SNO0004700
49 EC: XXXX' );
50 LMM CHAR (16) DEF L2 POS (16);
51 LIN CHAR (2) DEF L2 POS (13);
52 LID CHAR (9) DEF L2 POS (41);
53 LRDT CHAR (5) DEF L2 POS (61);
54 LSNEC CHAR (4) DEF L2 POS (79);
55 L3 CHAR (78) STATIC INIT ( ' ' );
56 LBLANK CHAR (5) STATIC INIT ( ' ' );
57 L8 CHAR (19) STATIC INIT
58 ( ' -CUR--QTD--YTD--1' );
59
60 DECLARE OUTSEG (20,4) CHAR (19) BASED (P1);
61 OUTROM (20) CHAR (76) BASED (P2);
62 OUTCLR CHAR (1520) STATIC INIT ( ' ' );
63 BUILD CHAR (19) STATIC INIT
64 ( ' ' );
65 BCT CHAR (4) DEF BUILD POS (2);
66 BQT CHAR (5) DEF BUILD POS (7);
67 BYT CHAR (6) DEF BUILD POS (13);
68 BL4 CHAR (19) STATIC INIT
69 ( ' ' );
70 FBL4 CHAR (16) DEF BL4 POS (2);
71 BL5 CHAR (19) STATIC INIT
72 ( ' COURSE COP: XXXX ' );
73 FBL5 CHAR (4) DEF BL5 POS (14);
74 BL6 CHAR (19) STATIC INIT
75 ( ' ONBOARD: XXX ' );
76 FBL6 CHAR (3) DEF BL6 POS (11);
77 BL7 CHAR (19) STATIC INIT
78 ( ' LDATE: MM/DD/YY ' );
79 L7MM CHAR (2) DEF BL7 POS (10);
80 L7DD CHAR (2) DEF BL7 POS (11);
81 L7YY CHAR (2) DEF BL7 POS (16);
82 GETDATE CHAR (4) STATIC,
83 GMM CHAR (2) DEF GETDATE POS (3);
84 GDD CHAR (2) DEF GETDATE POS (5);
85 GYY CHAR (2) DEF GETDATE POS (11) ;
86
87 DECLARE BUMEOR BIT (1) STATIC INIT ( '0' );
88 TTYPE (20) CHAR (3) STATIC INIT ( '111' );
89 'A1' , 'A2' , 'A3' , 'A4' , 'A5' , 'A6' , 'A7' , '
90 'B1' , 'B2' , 'B3' , 'B4' , 'B5' , 'B6' , 'B6A' );
91 M FIXED BIN STATIC INIT ( 0 );
92 LL STATIC,
93 ( J, NC ) FIXED BIN STATIC,
94 DLINE CHAR (79) STATIC,
95 ROUTE LABEL ;
96
97 PUTIB: FORMAT ( INIATIB ) ;
98
99 STARTERRUPP:
100 OPEN FILE (DUMP) RECORD INPUT ;
101 ON ENDFILE (DUMP) GO TO WINDUP ;
102 P1, P2 = ADDR (OUTCLR) ;
103
104
105 R1: READ FILE (DUMP) INTO (CARD1) ;
106 READ FILE (DUMP) INTO (CARD2) ;
107 NC = NC + 2 ;
108 IF ( ID = OLDID ) THEN GO TO MORE_THIS_INSTRUCTOR ;
109 IF ( N > 0 ) THEN

```

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 -PGMR- FLOWCHARTS

CARD NO

CONTENTS

```

110      OUTNOW:      DO ;
111                  ROUTE = START_NEW_INSTRUCTOR ;
112                  GO TO DISPLAY_ONE_PAGE ;
113                  END OUTNOW ;
114
115      START_NEW_INSTRUCTOR:
116          N = 1 ;
117          OLDID = ID ;
118          LSCH = SCH ;
119          LREP = RATE ;
120          LPNEC = PNEC ;
121          LNM = NME ;
122          LIN = IN ;
123          LID = ID ;
124          LROT = ROT ;
125          LSNEC = SWEC ;
126          OUTCLR = ' ' ;
127          GO TO FILL_COURSE ;
128
129      MORE_THIS_INSTRUCTOR:
130          N = N + 1 ;
131
132      FILL_COURSE:
133          FBL4 = TTL ;
134          OUTSEG (1,N) = BL4 ;
135          FBL5 = CDP ;
136          OUTSEG (2,N) = BL5 ;
137          IF ( UMB = '1' ) THEN FBL6 = 'YES' ;
138          ELSE FBL6 = 'NO' ;
139          OUTSEG (3,N) = BL6 ;
140          GETDATE = LOTE ;
141          L7MM = GMM ;
142          L7DD = GDD ;
143          L7YY = GYY ;
144          OUTSEG (4,N) = BL7 ;
145          OUTSEG (5,N) = LB ;
146          IF ( TT = ' ' ) THEN GO TO R1 ;
147
148          BUMEOP = '1'B ;
149          LL = 5 ;
150      GET_TIMES:      DO J = 1 TO 15 ;
151                  IF ( ID = OLDID ) THEN GO TO ERROR1 ;
152                  LL = LL + 1 ;
153
154          IF ( LL = 13 ) THEN
155              DO ;
156                  OUTSEG (13,N) = BL4 ;
157                  GO TO GETTIMS ;
158                  END FILL13 ;
159
160              BCT = CT ;
161              BQT = QTD ;
162              BYT = YTD ;
163              OUTSEG (LL,N) = BUILD ;
164
165              IF ( LL >= 20 ) THEN GO TO CYCLE ;
166              *ADD FILE (DUMP) INTO (CARD1) ;
167              *ADD FILE (DUMP) INTO (CARD2) ;
168              NC = NC + 2 ;
169              END GET_TIMES ;
170
171      EGTIMS:          END GET_TIMES ;
172
173      CYCLE:          BUMEOP = '0' ;
174                  IF ( N < 4 ) THEN GO TO R1 ;
175
176      JUST_FILLED_A_PAGE:
177          ROUTE = RECYCLE ;
178          GO TO DISPLAY_ONE_PAGE ;
179
180      RECYCLE:
181          N = 0 ;
182          GO TO R1 ;
183
184      DISPLAY_ONE_PAGE:
185          DISPLAY ( LBLANK ) ; /* PAGE-CLEAR GOES HERE, */
186          DISPLAY ( LBLANK ) ; /* WHENEVER AVAILABLE... */
187          DISPLAY ( L1 ) ;
188          DISPLAY ( L2 ) ;
189          DISPLAY ( L3 ) ;
190
191      TUBE:            DO J = 1 TO 20 ;
192                  DISPLAY ( TTYPE(J) || OUTROW(J) ) ;
193                  END TUBE ;
194
195                  GO TO ROUTE ; /* VARIABLE EXIT ROUTER */
196
197      ERROR1: FILLM3 = '1' ;
198              GO TO BUSTED ;
199
200      ERROR2: FILLM3 = '2' ;
201
202      BUSTED: FILLM3 = NC ;
203              DISPLAY ( LBLANK ) ;
204              DISPLAY ( M3 ) ;
205              DISPLAY ( '*** FOR FOLLOWING INSTRUCTOR...' ) ;
206
207              DISPLAY ( LBLANK ) ;
208              DISPLAY ( L1 ) ;
209              DISPLAY ( L2 ) ;
210              DISPLAY ( L3 ) ;
211
212      FILLM2 = CDP ;
213      FILLM2B = TTL ;
214          DISPLAY ( LBLANK ) ;
215          DISPLAY ( M2 ) ;
216
217          DISPLAY ( LBLANK ) ;
218          DISPLAY ( '*** ABNORMAL DISPLAY-PROGRAM TERMINATION FOLLOWS' ) ;
219          DISPLAY ( LBLANK ) ;
220
221

```

TAEK REPORT NO. 29

INPUT LISTING

AUTIFLOW CHART SET - FINAL

PL/1 - PGMB - FLOWCHART

CARD NO	****	CONTENTS	****
222		GO TO CLOSEM :	00022100
223			10022200
224			00022300
225	WINDUP:		00022400
226		IF (BUMEDF) THEN	00022500
227	BEOP:	DO :	00022600
228		FILLM1 = NO :	00022700
229		DISPLAY (M1) :	00022800
230		FILLM2A = CDP :	00022900
231		FILLM2B = TTL :	00023000
232		DISPLAY (M2) :	00023100
233		DISPLAY (LBLANK) :	00023200
234		DISPLAY (L1) :	00023300
235		DISPLAY (L2) :	00023400
236		GO TO CLOSEM :	00023500
237		END BEOP :	00023600
238			00023700
239		IF (N > 0) THEN	00023800
240	ANOTHER:	DO :	00023900
241		ROUTE = CLOSEM :	00024000
242		GO TO DISPLAY_ONE_PAGE :	00024100
243		END ANOTHER :	00024200
244			00024300
245	CLOSEM:		00024400
246		CLOSE FILE (DUMP) :	00024500
247		END PGMB :	00024600

PAGE 01

```

/ 0000002 /
-----

PGM#

00000002 | NOTE
* * * * *
* PRINT INSTR. FILE
* FROM DISK DUMP -
*   TUE/6/MAY/75
* * * * *

```

```
STARTERRUPP  
|  
00000100 | 02  
-----  
OPEN FILE  
(OUNP RECD)  
INPUT  
-----  
|  
C0000102 | 03  
-----  
M [ON-UNIT01] | 61  
M ON ENDFILE | 01  
M (OUNP) | 01  
M
```

```

00000103 | 04
-----|
| ASSIGNMENT(S) |
-----|
02.11*-->|

```

```

      RI
      |
      |
00000109 | 09
-----
/      /
/  READ FILE  /
/ (DUMP) INTO /
/ (CARD:)    /

```

```
00000106 | 04
-----
/  READ FILE  /
/ (DUMP) INTO /
/ (CARD2)    /
```

```

00000107 | 07
-----
| ASSIGNMENT(S) |

```

00000108 08
110 010101

```

MORE_THIS_INSTRUCT
00000130 |
-----
| ASSIGNMENT(S)

```

```

      FILL_COURSE
      |
      |
00000133 |
-----
1  ASSIGNMENT15)

```

00000138 * 11

11

```
00000138 |
-----
| ASSIGNMENT(S)
```

• 2.10.

00000109 • 13

11

```

          OUTNOW
            |
07.01--->|
00000111 |
-----
|  ASSIGNMENT(S)
|

```

• 3.02 •

START_NEW_INSTRUCTOR

```
00000119 | 19
-----
1 ASSIGNMENT(S) |
```

FILL_COURSE

DISPLAY_GNE_PAGE

AUTOFLOW CHART SET - FINAL PL/1 - PGMB- FLOWCHARTS

CHART TITLE - PROC PGMB OPTIONS (MAIN)





TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL PL/1 -PGMB- FLOWCHARTS

PAGE 03

CHART TITLE - PRCC PGNB OPTIONS (MAIN)



206

II-190

CHART TITLE - PROC PGMB OPTIONS (MAIN)





CHART TITLE - PROC PGMB OPTIONS (MAIN)



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PGMB - FLOWCHARTS

PAGE 08

CHART TITLE - ON-UNIT ACTION BLOCKS

/ 00000102 /

01.03--->*

.ON UNIT01

00000102 | NOTE 01
 * * * * *
 * ON ENDFILE (DUMP) *
 * * * * *

|

...

* 5.01 *

...

WINDUP

END .ON-UNIT01

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGMB- FLOWCHARTS

PAGE 07

CHART TITLE - LABEL ASSIGNMENT CROSS REFERENCE

/ ROUTE /	
03.11-->	01
SCALAR	
LABEL VARIABLE	
SET AT	TO GO TO
1.14	1.15
00000111	START_ME
2.19	3.01
00000177	RECYCLE
5.10	5.11
00000241	CLOSEM

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PGMS - FLOWCHARTS

PAGE 08

CHART TITLE - GET/PUT, FORMAT STATEMENTS

00000097 PUT18 FORMAT (1N) A (1B1)

PROGRAM NAME: PGM9B

TYPE: PL/1

SYSTEM: Data Base Maintenance

NCSS FILENAME/FILETYPE: PGM9B/PLI

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

PGM9B converts the data found on the Instructor data base Type -2- input cards to the format described below. Output records (transactions) from this program are subsequently processed into the data base by the RAMIS data maintenance RLVICE function RE24/RAM (filename/filetype).

USAGE

Program PGM9B is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC</u> <u>Sequence</u>	<u>Data Base</u>
E24	Instructor Master

INPUT FORMAT

Input to PGM9B is via cards; the input card format is found on the illustration following bearing the title "Instructor (Course) Data Base Type -2- Input Card Format".

Note that this input card type is used in loading both the Instructor and the Course data bases.

Input card column 53 contains a flag (ASN) which indicates whether the Instructor is currently assigned to the Course. Note that an Instructor can be qualified to teach a Course, but not assigned to teach the same Course. A character '1' in the ASN field indicates that the Instructor is currently assigned to teach; PGM9B will select only the current assignments for inclusion in the Instructor data base.

INSTRUCTOR FILE

IBM
Business Systems Group
Business Systems Center
Armonk, New York

[illegible][illegible]

955-1115-0

OUTPUT FORMAT FOR PGM9B

Logical Record Length: 250 Bytes

PL/1 Base Data Structure Name: RTRANS

Output PL/1 Filename: TRANS

<u>Start Record Position</u>	<u>Byte Length</u>	<u>PL/1 Identifier</u>	<u>Format</u>	<u>Description</u>
1-51	51	R51	A51	First 51 columns of input card (direct copy)
52-108	57	FILL	A57	Same on all output records; used to initialize the 14 time-type segments; see program listing, PL/1 Identifier = FILLER, for data content

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 - PGMR - FLOWCHARTS

PL/1 MODULE

PLIST,NAMSQ,SOURCE,ST


CARD NO	****	CONTENTS	****
1		OPTION PACKIF,COMPRESS	00000100
2		PGMR: /* INSTR FILE TYPE -2- CARD TRANS PROCESSOR: SUN/4/20/75 */	00000200
3		PROC OPTIONS (MAIN) :	00000300
4			00000400
5		DECLARE CARD CHAR (10) STATIC	00000500
6		C1 CHAR (51) DEF CARD POS (11);	00000600
7		CASH CHAR (11) DEF CARD POS (13);	00000700
8		COP CHAR (14) DEF CARD POS (12);	00000800
9		NC FIXED BIN (15) STATIC INIT (0);	00000900
10		NCU FIXED BIN (15) STATIC INIT (0);	00001000
11		RTRANS CHAR (250) STATIC INIT (' ');	00001100
12		R51 CHAR (51) DEF RTRANS POS (11);	00001200
13		FILL CHAR (57) DEF RTRANS POS (52);	00001300
14		FILLER CHAR (57) STATIC INIT	00001400
15		(*A1 A2 A3 A4 A5 A6 A7 B1 B2 B3 B4 B5 B6 B6A00.0000.0000.0*);	00001500
16		M1 CHAR (54) STATIC INIT	00001600
17		(* TOTAL # INSTRUCTOR TYPE -2- CARDS PROCESSED = XXXX *);	00001700
18		M2 CHAR (51) STATIC INIT	00001800
19		(* TOTAL # INSTRUCTOR ASSIGNMENTS PROCESSED = XXXX *);	00001900
20		VM1 PICTURE '2229' DEF M1 POS (49);	00002000
21		VM2 PICTURE '2229' DEF M2 POS (46);	00002100
22		J FIXED BIN (15) STATIC	00002200
23		LBL CHAR (2) STATIC INIT (' ');	00002300
24			00002400
25		DECLARE OLDID CHAR (9) STATIC INIT (' ');	00002500
26		OLDIDP CHAR (14) STATIC INIT (0);	00002600
27		NOUP FIXED BIN STATIC INIT (0);	00002700
28		NOUP FIXED BIN STATIC INIT (0);	00002800
29		M3 CHAR (16) DEF CARD POS (11);	00002900
30		M3 CHAR (16) STATIC INIT (	00003000
31		* UNASSIGNED RECORDS = N,XXX - DUPLICATE RECORDS SKIPPED = X,XXX*);	00003100
32		VM3A PICTURE '2229' DEF M3 POS (24);	00003200
33		VM3B PICTURE '2229' DEF M3 POS (40);	00003300
34			00003400
35		STARTERRUP:	00003500
36		OPEN FILE (TRANS) RECORD OUTPUT;	00003600
37		FILE (CARDS) RECORD INPUT ;	00003700
38		ON ENDFILE (CARDS) GO TO WRAPUP ;	00003800
39		FILL = FILLER ;	00003900
40			00004000
41		M1: HEAD FILE (CARDS) INTO (CARD) ;	00004100
42		NC = NC + 1 ;	00004200
43			00004300
44		IF (CASH = '1') THEN GO TO TRYDUP ;	00004400
45		NDA5N: NUNA = NUNA + 1 ;	00004500
46		GO TO M1 ;	00004600
47			00004700
48		TRYDUP: IF (ID = OLDID) THEN GO TO HERE_ASSIGNED ;	00004800
49		IF (LUP = OLDCOP) THEN GO TO HERE_ASSIGNED ;	00004900
50		NOUP = NOUP + 1 ;	00005000
51		GO TO M1 ;	00005100
52			00005200
53		HERE_ASSIGNED:	00005300
54		OLDID = ID ;	00005400
55		OLDCOP = COP ;	00005500
56		NCU = NCU + 1 ;	00005600
57		R51 = C51 ;	00005700
58		WRITE FILE (TRANS) FROM (RTRANS) ;	00005800
59		GO TO M1 ;	00005900
60			00006000
61		WRAPUP: CLOSE FILE (CARDS) ;	00006100
62		CLOSE FILE (TRANS) ;	00006200
63		VM1 = NC ;	00006300
64		VM2 = NCU ;	00006400
65		VM3A = NUNA ;	00006500
66		VM3B = NOUP ;	00006600
67		DISPLAY (LBL) ;	00006700
68		DISPLAY (M1) ;	00006800
69		DISPLAY (M2) ;	00006900
70		DISPLAY (M3) ;	00007000
71			00007100
72		END PGMR ;	00007200

TAE G REPORT NO. 29

AUTOFLOW CHART SET - FINAL PL/1 - PGM98- FLOWCHARTS

PAGE 01

CHART TITLE - PROC PGM98 OF SENS (MAIN)



216

II-200

PROGRAM NAME: PGM16

TYPE: PL/1

SYSTEM: Data Base Maintenance

NCSS FILENAME/FILETYPE: PGM16/PLI

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

This program combines the data found on Type -1- and Type -2- input cards into one logical record for initialization of the Course data base. One output record (transaction) is produced for each pair of input cards. Output transactions are subsequently processed into the Course data base by the RAMIS data maintenance INPUT function RE43/RAM (filename/filetype).

USAGE

Program PGM16 is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC</u> <u>Sequence</u>	<u>Data Base</u>
E43	Course Master

INPUT FORMAT

Input data card formats are illustrated in the diagrams titled: "Course Data Base Type -1- Input Card Format" and "Course Data Base Type -2- Input Card Format" on the pages following. These cards must be stacked in the input stream in pairs; i.e., for a given Course, both types must be present. Type -1- precedes the Type -2- format card.

OUTPUT FORMAT FOR PGM16

Logical Record Length: 250 Bytes (218 Bytes contain data)
 PL/1 Base Data Structure Name: RTRANS
 Output PL/1 Filename: TRANS

LEVEL	FIELD NAME	POSITIONS		
		IN RECORD	TYPE	LENGTH
1	SCH	1-4	A	4
2	CDP	5-8	A	4
3	DEL	9	A	1
	CTLG	10-19	A	10
	CRS	20-35	A	16
	CONV1	36-38	I	3
	LEN1	39-42	F	4.1
	CAP1	43-45	I	3
	BCAP1	46-48	I	3
	DMD1	49-53	I	5
	BDMD1	54-58	I	5
	OFST	59-60	I	2
	PFAIL	61-65	F	5.3
	NADIS	66-70	F	5.3
	NOSHOW	71-75	F	5.3
	SETB	76-80	F	5.3
	BKLG	81-84	I	4
	JNO	85-88	A	4
	CONV2	89-91	I	3
	LEN2	92-95	F	4.1
	CAP2	96-98	I	3
	BCAP2	99-101	I	3
	DMD2	102-106	I	5
	BDMD2	107-111	I	5
	CHWK2	112-114	I	3
	CONV3	115-117	I	3
	LEN3	118-121	F	4.1
	CAP3	122-124	I	3
	BCAP3	125-127	I	3
	DMD3	128-132	I	5
	BDMD3	133-137	I	5
	CHWK3	138-140	I	3
	PAOB	141-144	I	4
	AFAIL	145-149	F	5.3
	PRTY	150-151	I	2
	CTYPE	152-153	A	2
	PNEC	154-157	A	4
	UCAP	158-160	I	3
	UDEM	161-163	I	3
	FPRTY	164-165	I	2
	RDTE	166-170	I	6
	HSETB	171-176	F	5.3
	TINSTR	177-180	F	4.1
	SUIC	181-185	A	5
	CCMM	186-195	A	10

<u>LEVEL</u>	<u>FIELD NAME</u>	<u>POSITIONS IN RECORD</u>	<u>TYPE</u>	<u>LENGTH</u>
4	SIR	196-199	F	4.1
	CHRS	200-204	F	5.1
	CTYP	205	A	1
5	ID	206-214	A	9
	QUAL	215-217	A	3
	ASN	218	I	1

NOTE - RECORD POSITIONS 154-218, INCLUSIVE,
ARE INITIALIZED ONE TIME AT PROGRAM
PGM16 INITIALIZATION; NO DATA ARE
TRANSFERRED INTO THESE POSITIONS FROM
THE INPUT CARDS.

ALPHABETIC (TYPE = A) FIELDS ARE
INITIALIZED TO BLANKS; NUMERIC FIELDS
(TYPE = I OR F) ARE INITIALIZED TO
ZERO.




NAME	COURSE CARD NO. 1	AGE AND SEX	WRITTEN AS NAME	WRITTEN AS PHONETIC	CARD NUMBER	VERIFY	DATE MADE UP	1 2	SERIES

[illegible]

935-1115-0

COURSE DATA BASE TYPE -2- INPUT CARD FORMAT



IBM
Federal Systems Division
Systems Support Center

COURSE CARD NO. 2

80-Column Card Punch Layout

COURSE CARD NO. 2										COURSE CARD NO. 2										COURSE CARD NO. 2										COURSE CARD NO. 2									
COURSE CARD NO. 2										COURSE CARD NO. 2										COURSE CARD NO. 2										COURSE CARD NO. 2									

COP	CONV		LEN		CAP		SCAP		DMD2		BOMC2		CH		CONV		LEN		CAP		SCAP		DMD3		BMD3		CH		PAOB		AFAIL		PNEC		SCH		SUIC		
	2	1	2	1	2	1	2	1	2	2	1	2	1	2	2	1	2	2	1	2	2	1	2	2	1	2	2	1	2	2	1	2	2	1	2	2	1	2	
1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34	35	36	37	38	39	40
41	42	43	44	45	46	47	48	49	50	51	52	53	54	55	56	57	58	59	60	61	62	63	64	65	66	67	68	69	70	71	72	73	74	75	76	77	78	79	80
81	82	83	84	85	86	87	88	89	90	91	92	93	94	95	96	97	98	99	100	101	102	103	104	105	106	107	108	109	110	111	112	113	114	115	116	117	118	119	120
121	122	123	124	125	126	127	128	129	130	131	132	133	134	135	136	137	138	139	140	141	142	143	144	145	146	147	148	149	150	151	152	153	154	155	156	157	158	159	160
161	162	163	164	165	166	167	168	169	170	171	172	173	174	175	176	177	178	179	180	181	182	183	184	185	186	187	188	189	190	191	192	193	194	195	196	197	198	199	200
201	202	203	204	205	206	207	208	209	210	211	212	213	214	215	216	217	218	219	220	221	222	223	224	225	226	227	228	229	230	231	232	233	234	235	236	237	238	239	240
241	242	243	244	245	246	247	248	249	250	251	252	253	254	255	256	257	258	259	260	261	262	263	264	265	266	267	268	269	270	271	272	273	274	275	276	277	278	279	280
281	282	283	284	285	286	287	288	289	290	291	292	293	294	295	296	297	298	299	300	301	302	303	304	305	306	307	308	309	310	311	312	313	314	315	316	317	318	319	320
321	322	323	324	325	326	327	328	329	330	331	332	333	334	335	336	337	338	339	340	341	342	343	344	345	346	347	348	349	350	351	352	353	354	355	356	357	358	359	360
361	362	363	364	365	366	367	368	369	370	371	372	373	374	375	376	377	378	379	380	381	382	383	384	385	386	387	388	389	390	391	392	393	394	395	396	397	398	399	400
401	402	403	404	405	406	407	408	409	410	411	412	413	414	415	416	417	418	419	420	421	422	423	424	425	426	427	428	429	430	431	432	433	434	435	436	437	438	439	440
441	442	443	444	445	446	447	448	449	450	451	452	453	454	455	456	457	458	459	460	461	462	463	464	465	466	467	468	469	470	471	472	473	474	475	476	477	478	479	480
481	482	483	484	485	486	487	488	489	490	491	492	493	494	495	496	497	498	499	500	501	502	503	504	505	506	507	508	509	510	511	512	513	514	515	516	517	518	519	520
521	522	523	524	525	526	527	528	529	530	531	532	533	534	535	536	537	538	539	540	541	542	543	544	545	546	547	548	549	550	551	552	553	554	555	556	557	558	559	560
561	562	563	564	565	566	567	568	569	570	571	572	573	574	575	576	577	578	579	580	581	582	583	584	585	586	587	588	589	590	591	592	593	594	595	596	597	598	599	600
601	602	603	604	605	606	607	608	609	610	611	612	613	614	615	616	617	618	619	620	621	622	623	624	625	626	627	628	629	630	631	632	633	634	635	636	637	638	639	640
641	642	643	644	645	646	647	648	649	650	651	652	653	654	655	656	657	658	659	660	661	662	663	664	665	666	667	668	669	670	671	672	673	674	675	676	677	678	679	680
681	682	683	684	685	686	687	688	689	690	691	692	693	694	695	696	697	698	699	700	701	702	703	704	705	706	707	708	709	710	711	712	713	714	715	716	717	718	719	720
721	722	723	724	725	726	727	728	729	730	731	732	733	734	735	736	737	738	739	740	741	742	743	744	745	746	747	748	749	750	751	752	753	754	755	756	757	758	759	760
761	762	763	764	765	766	767	768	769	770	771	772	773	774	775	776	777	778	779	780	781	782	783	784	785	786	787	788	789	790	791	792	793	794	795	796	797	798	799	800
801	802	803	804	805	806	807	808	809	810	811	812	813	814	815	816	817	818	819	820	821	822	823	824	825	826	827	828	829	830	831	832	833	834	835	836	837	838	839	840
841	842	843	844	845	846	847	848	849	850	851	852	853	854	855	856	857	858	859	860	861	862	863	864	865	866	867	868	869	870	871	872	873	874	875	876	877	878	879	880
881	882	883	884	885	886	887	888	889	890	891	892	893	894	895	896	897	898	899	900	901	902	903	904	905	906	907	908	909	910	911	912	913	914	915	916	917	918	919	920
921	922	923	924	925	926	927	928	929	930	931	932	933	934	935	936	937	938	939	940	941	942	943	944	945	946	947	948	949	950	951	952	953	954	955	956	957	958	959	960
961	962	963	964	965	966	967	968	969	970	971	972	973	974	975	976	977	978	979	980	981	982	983	984	985	986	987	988	989	990	991	992	993	994	995	996	997	998	999	1000

955-1115-0

PL/1 -PGN16- FLOWCHARTS

(11ST,NAMSO,SOURCEQ)

CONTENTS

•••••

223

CHART TITLE - PROC PGM16 OPTIONS (MAIN)





CHART TITLE - PROC PGM16 OPTIONS (MAIN)



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL PL/1 -PGM16- FLOWCHARTS

PAGE 03

CHART TITLE - ON-UNIT ACTION BLOCKS

/ 0000007 /

01.04--->*

.ON-UNIT01

```

      *
0000007 | NOTE 01
* ..... *
* ON ENDFILE *
* (CARDS) *
* ..... *

```

|
|
|

...
* 2.01.
* ... *

WRAPUP

END .ON-UNIT01

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PER16- FLOWCHARTS

PAGE 04

CHART TITLE - GET/PUT, FORMAT STATEMENTS

```

00000080 .GET/PUT 001 GET STRING (CARD1) EDIT (LEN1,PPAIL,NADIS,NOSHOW,SET8) (X (33),F (3,1),X (18),
00000082          (A,8))
00000089 .GET/PUT 002 GET STRING (CARD2) EDIT (LEN2,LEN3,APAIL) (X (7),P (3,1),X (22),F (3,1),X (23),F (4,
00000091          3))
    
```


PROGRAM NAME: PGM19

TYPE: PL/1

SYSTEM: Data Base Maintenance

NCSS FILENAME/FILETYPE: PGM19/PLI

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

Following a standard RAMIS data maintenance DUMP of the Course data base, PGM19 is used to display each of the RAMIS records at the User terminal.

USAGE

Program PGM19 is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC</u> <u>Sequence</u>	<u>Data Base</u>
E58	Course Master
E37	Course Scratch

INPUT FORMAT

For the Course data base, the field positions in the output of the RAMIS DUMP are indicated in the following RAMIS sample output. Note that the DUMP file takes the form of fixed-length card-image records (logical record length = 80 Bytes).

± EBCDIC RECORD LENGTH 80 CHARACTERS

<u>FIELD NAME</u>	<u>FORMAT</u>	<u>LENGTH</u>
SCH	A 4	4
CDP	A 4	4
DEL	A 1	1
CTLG	A 10	10
CRS	A 16	16
CONV1	I 3	3
LEN1	F4 .1	4
CAP1	I 3	3
BCAP1	I 3	3
DMD1	I 5	5
BDMD1	I 5	5
OFST	I 2	2
PFAIL	F5 .3	5

<u>FIELD NAME</u>	<u>FORMAT</u>	<u>LENGTH</u>
NADIS	F5 .3	5
NOSHOW	F5 .3	5
SETB	F5 .3	5
		X 0
BKLG	I 4	4
JNO	A 4	4
CONV2	I 3	3
LEN2	F4 .1	4
CAP2	I 3	3
BCAP2	I 3	3
DMD2	I 5	5
BDMD2	I 5	5
CHWK2	I 3	3
CONV3	I 3	3
LEN3	F4 .1	4
CAP3	I 3	3
BCAP3	I 3	3
DMD3	I 5	5
BDMD3	I 5	5
CHWK3	I 3	3
PAOB	I 4	4
AFAIL	F5 .3	5
PRTY	I 2	2
CTYPE	A 2	2
PNEC	A 4	4
UCAP	I .3	3
		X 0
UDEM	I 3	3
EPRTY	I 2	2
RDTE	I 6	6
HSETB	F5 .3	5
TINSTR	F4 .1	4
SUIC	A 5	5
CCMM	A 10	10
SIR	F4 .1	4
CHRS	F5 .1	5
CTYP	A 1	1
ID	A 9	9
QUAL	A 3	3
ASN	I 1	1

Zeros at the positions marked by 'X' indicate that no slack bytes were required at the end of each card image to prevent split of a data field across card boundaries. Three (3) card-image records are required in the DUMP to represent one RAMIS record; a portion of the last card image of the trio remains unused.

OUTPUT RECORDS

Output of PGM 19 is directed to the User terminal. Three (3) input card images are required (minimum) in the construction of an output terminal screen display.

Output is composed to fit on the 80-Character display face; essentially, an entire screen is required to display the data associated with a single Course.

A sample of the terminal output is illustrated by the diagram following.

SAMPLE TERMINAL OUTPUT PRODUCED BY PROGRAM PGM19

2573	BW/FW T/T	RECERT	--SCHEDULE DATA--	FY	FY+1	FY+2	CHANGE DATE
			ANNUAL CONVENINGS	11	0	0	OFFSET 0
SCHL JNO	CATALOG NO	PNEC	COURSE LENGTH	3.0	.0	.0	FY+1 WK 0
AC&R	A-651-0051		COURSE CAPACITY	16	0	0	FY+2 WK 0
			BUPERS CAPACITY	0	0	0	
PAOB	PFAIL	AFAIL	TYPE	PRTY			
0	.000	.000	F1	0			
			ANNUAL DEMAND	46	46	46	BACKLOG 0
			BUPERS DEMAND	0	0	0	

CCMM	SUIC	RDTE	FPRTY	NADIS	NOSHOW	SETB	ASETB	UCAP	UDEM	TINSTR
		0	0	.000	.000	.000	.000	26	0	.0

!----- INSTRUCTOR ASSIGNMENTS -----!											
SIR	CHRS	CTYP	!INSTR-ID	QUAL	ASSN!	INSTR-ID	QUAL	ASSN!	INSTR-ID	QUAL	ASSN
.0	.0		!		1 !	!		!			
18.0	5.0	1	!123456789	25	1	!222222222	100	1	!333333333	100	1
			!455556667	0	0						

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 -PGM19- FLOWCHARTS

PL/1 MODULE

(LIST,NAMSQ,SOURCEQ)

CARD NO

0000

CONTENTS

0000

```

1  OPTION PACKIF,COMPRESS
2  PGM19: /* COURSE FILE PUMP TO DISPLAY - THRU 8/MAY/75 */ 00000100
3  PROC OPTIONS (MAIN) ; 00000200
4  00000300
5  DECLARE SICLR CHAR (190) STATIC, 00000400
6  LBLAMR CHAR (5) STATIC INIT ( ' ' ), 00000500
7  SIROW (10) CHAR (19) DEF SICLR POS (1), 00000600
8  SIBLD CHAR (19) STATIC INIT ( ' ' ), 00000700
9  BSIR CHAR (4) DEF SIBLD POS (1), 00000800
10 BCRHS CHAR (5) DEF SIBLD POS (7), 00000900
11 BCTYP CHAR (4) DEF SIBLD POS (14), 00001000
12 CLOSTR CHAR (4) STATIC INIT ( ' ' ), 00001100
13 00001200
14 DECLARE INCLR CHAR (600) STATIC, 00001300
15 INROW (10) CHAR (60) DEF INCLR POS (1), 00001400
16 INTAB (10,3) CHAR (20) DEF INCLR POS (1), 00001500
17 INBLD CHAR (20) STATIC INIT ( ' ' ), 00001600
18 BID CHAR (9) DEF INBLD POS (2), 00001700
19 BQUAL CHAR (3) DEF INBLD POS (13), 00001800
20 BASSN CHAR (3) DEF INBLD POS (18) ; 00001900
21 00002000
22 DECLARE OLNE CHAR (79) STATIC, 00002100
23 L1 CHAR (79) STATIC INIT ( 00002200
24 --SCHEDULE DATA-- FY FY+1 FY+2 CM00002300
25 ANGE DATE' ), 00002400
26 L2 CHAR (79) STATIC INIT ( 00002500
27 ANNUAL CONVENINGS' XXX XXX XXX OF00002600
28 FSET XX' ), 00002700
29 L2CON1 CHAR (3) DEF L2 POS (49), 00002800
30 L2CON2 CHAR (3) DEF L2 POS (56), 00002900
31 L2CON3 CHAR (3) DEF L2 POS (63), 00003000
32 L2OFF CHAR (2) DEF L2 POS (78), 00003100
33 L3 CHAR (79) STATIC INIT ( 00003200
34 'SCHL JMD CATALOG NO PNEC COURSE LENGTH XX.X XX.X XX.X FY00003300
35 +1 NR XXX' ), 00003400
36 L3LEN1 CHAR (4) DEF L3 POS (48), 00003500
37 L3LEN2 CHAR (4) DEF L3 POS (55), 00003600
38 L3LEN3 CHAR (4) DEF L3 POS (62), 00003700
39 L3W1 CHAR (3) DEF L3 POS (77), 00003800
40 LICDP CHAR (4) DEF L1 POS (1), 00003900
41 LICRS CHAR (16) DEF L1 POS (10), 00004000
42 L4 CHAR (79) STATIC INIT ( 00004100
43 COURSE CAPACITY XXX XXX XXX FY00004200
44 +2 NR XXX' ), 00004300
45 L4SCH CHAR (4) DEF L4 POS (1), 00004400
46 L4JMD CHAR (4) DEF L4 POS (6), 00004500
47 L4CAT CHAR (10) DEF L4 POS (11), 00004600
48 L4PNEC CHAR (4) DEF L4 POS (23), 00004700
49 L4CAP1 CHAR (3) DEF L4 POS (49), 00004800
50 L4CAP2 CHAR (3) DEF L4 POS (56), 00004900
51 L4CAP3 CHAR (3) DEF L4 POS (63), 00005000
52 L4WR2 CHAR (3) DEF L4 POS (77), 00005100
53 L5 CHAR (79) STATIC INIT ( 00005200
54 SUPERS CAPACITY' ), 00005300
55 L5CAP1 CHAR (3) DEF L5 POS (49), 00005400
56 L5CAP2 CHAR (3) DEF L5 POS (56), 00005500
57 L5CAP3 CHAR (3) DEF L5 POS (63), 00005600
58 L6 CHAR (79) STATIC INIT ( 00005700
59 'PACB PFAIL AFAIL TYPE PRTY ANNUAL DEMAND XXXXX XXXX XXXX BAC00005800
60 KLOG XXXX' ), 00005900
61 L6DMO1 CHAR (5) DEF L6 POS (47), 00006000
62 L6DMO2 CHAR (5) DEF L6 POS (54), 00006100
63 L6DMO3 CHAR (5) DEF L6 POS (61), 00006200
64 L6RXL0E CHAR (4) DEF L6 POS (76), 00006300
65 L7 CHAR (79) STATIC INIT ( 00006400
66 SUPERS DEMAND XXXXX XXXX XXXX' ), 00006500
67 L7A0B CHAR (4) DEF L7 POS (1), 00006600
68 L7PF CHAR (5) DEF L7 POS (6), 00006700
69 L7AF CHAR (5) DEF L7 POS (12), 00006800
70 L7TYPE CHAR (2) DEF L7 POS (19), 00006900
71 L7PRTY CHAR (2) DEF L7 POS (24), 00007000
72 L7BD1 CHAR (5) DEF L7 POS (47), 00007100
73 L7BD2 CHAR (5) DEF L7 POS (54), 00007200
74 L7BD3 CHAR (5) DEF L7 POS (61), 00007300
75 L9 CHAR (79) STATIC INIT ( 00007400
76 'CCMM SUIC RTE PRPTY RADIS NOSHOM SETB ASETB UCAP UDEM00007500
77 TINSTR' ), 00007600
78 L10 CHAR (79) STATIC INIT ( ' ' ), 00007700
79 L10CCMM CHAR (10) DEF L10 POS (1), 00007800
80 L10SUIC CHAR (5) DEF L10 POS (13), 00007900
81 L10RDE CHAR (6) DEF L10 POS (20), 00008000
82 L10PRTY CHAR (2) DEF L10 POS (29), 00008100
83 L10RADIS CHAR (5) DEF L10 POS (35), 00008200
84 L10NOSHOM CHAR (5) DEF L10 POS (42), 00008300
85 L10SETB CHAR (5) DEF L10 POS (50), 00008400
86 L10HSETB CHAR (5) DEF L10 POS (56), 00008500
87 L10UCAP CHAR (3) DEF L10 POS (64), 00008600
88 L10UDEM CHAR (3) DEF L10 POS (69), 00008700
89 L10TIN CHAR (4) DEF L10 POS (75), 00008800
90 L12 CHAR (79) STATIC INIT ( 00008900
91 INSTRUCTOR ASSIGNMENTS 00009000
92 '-----' ), 00009100
93 L13 CHAR (79) STATIC INIT ( 00009200
94 'SIR CHRS CTYP INSTR-ID QUAL ASSNINSTR-ID QUAL ASSNINSTR-ID 00009300
95 QUAL ASSN' ), 00009400
96 LBL2 CHAR (20) STATIC INIT ( ' ' ); 00009500
97 00009600
98 DECLARE 1 CARD1 STATIC, 00009700
99 2 SCH CHAR (4), 00009800
100 2 COP CHAR (4), 00009900
101 2 DEL CHAR (1), 00010000
102 2 CTLE CHAR (10), 00010100
103 2 CRS CHAR (16), 00010200
104 2 CONVL CHAR (3), 00010300
105 2 LEN1 CHAR (4), 00010400
106 2 CAP1 CHAR (3), 00010500
107 2 BCAP1 CHAR (3), 00010600
108 2 UMD1 CHAR (5), 00010700
109 2 BMD1 CHAR (5), 00010800

```

TAE G REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 - PGMI9 - FLOWCHARTS

CARD NO	*****	CONTENTS	*****
110		2 DFST CHAR (21);	00010900
111		2 PFAIL CHAR (51);	00011000
112		2 NADIS CHAR (51);	00011100
113		2 NOSHOW CHAR (51);	00011200
114		2 SETB CHAR (51);	00011300
115			00011400
116	DECLARE 1 CARD2	STATIC;	00011500
117		2 BKLG CHAR (41);	00011600
118		2 JND CHAR (41);	00011700
119		2 CONV2 CHAR (31);	00011800
120		2 LEN2 CHAR (41);	00011900
121		2 CAP2 CHAR (31);	00012000
122		2 BCAP2 CHAR (31);	00012100
123		2 DMD2 CHAR (51);	00012200
124		2 BDMO2 CHAR (51);	00012300
125		2 CHWR2 CHAR (31);	00012400
126		2 CONV3 CHAR (31);	00012500
127		2 LEN3 CHAR (41);	00012600
128		2 CAP3 CHAR (31);	00012700
129		2 BCAP3 CHAR (31);	00012800
130		2 DMD3 CHAR (51);	00012900
131		2 BDMO3 CHAR (51);	00013000
132		2 CHWR3 CHAR (31);	00013100
133		2 PAOB CHAR (41);	00013200
134		2 AFAIL CHAR (51);	00013300
135		2 PRTY CHAR (21);	00013400
136		2 CTYPE CHAR (21);	00013500
137		2 PNEC CHAR (41);	00013600
138		2 UCAP CHAR (31);	00013700
139			00013800
140	DECLARE 1 CARD3	STATIC;	00013900
141		2 UDEM CHAR (31);	00014000
142		2 PPRTY CHAR (21);	00014100
143		2 ROTE CHAR (41);	00014200
144		2 HSETB CHAR (51);	00014300
145		2 TINSTA CHAR (41);	00014400
146		2 SUIC CHAR (51);	00014500
147		2 CCMH CHAR (101);	00014600
148		2 SIR CHAR (41);	00014700
149		2 CHRS CHAR (51);	00014800
150		2 CTYP CHAR (11);	00014900
151		2 IO CHAR (91);	00015000
152		2 QUAL CHAR (31);	00015100
153		2 ASN CHAR (11);	00015200
154		2 CARBG CHAR (221);	00015300
155			00015400
156	DECLARE BEOP	BIT (1) STATIC INIT ('0'B);	00015500
157	NC	FIXED BIN STATIC INIT (0);	00015600
158	SOLDCCP	CHAR (41) STATIC INIT (' ');	00015700
159	NL	FIXED BIN STATIC INIT (0);	00015800
160	N	FIXED BIN STATIC INIT (0);	00015900
161	NCRS	FIXED BIN STATIC INIT (0);	00016000
162	M1	CHAR (51) STATIC INIT (' ');	00016100
163		*** ECF SEQUENCING ERROR IN PGMI9 - CARD COUNT IS XXX,XXX; ***	00016200
164	M1	FILLM1 PICTURE 'Z,ZZ9' DEF M1 POS (50);	00016300
165	M2	CHAR (34) STATIC INIT (' ');	00016400
166		*** TOTAL COURSES PROCESSED = XXX,XXX; ***	00016500
167	M2	FILLM2 PICTURE 'Z,ZZ9' DEF M2 POS (50);	00016600
168	J	STATIC;	00016700
169	ROUTE	LABEL;	00016800
170			00016900
171			00017000
172	STARTERRUPP:		00017100
173	OPEN FILE (DUMP) RECORD INPUT;		00017200
174	ON ENDFILE (DUMP) GO TO WINDUP;		00017300
175			00017400
176	READ1: READ FILE (DUMP) INTO (CARD1);		00017500
177	BEOP = '1'B;		00017600
178	READ FILE (DUMP) INTO (CARD2);		00017700
179	READ FILE (DUMP) INTO (CARD3);		00017800
180	BEOP = '0'B;		00017900
181	NC = NC + 1;		00018000
182			00018100
183	IF (CDP = SOLDCCP) THEN		00018200
184	DO;		00018300
185	IF (NL < 1) THEN GO TO START_NEW_COURSE;		00018400
186	ROUTE = START_NEW_COURSE;		00018500
187	GO TO DISPLAY_ONE_PAGE;		00018600
188	END NEWCCP;		00018700
189			00018800
190	OLDCCP: IF (SIR = OLDSIR) THEN GO TO SAME SIR;		00018900
191	NEWSIR: NL = NL + 1;		00019000
192	IF (NL > 10) THEN GO TO OUTNOWA;		00019100
193	ROUTE = SIR2;		00019200
194	GO TO SETLINE;		00019300
195	SIR2: IF (NL = 10) THEN GO TO OUTNOW;		00019400
196	GO TO RECYCLE1;		00019500
197			00019600
198	/* HERE, OLD COP, SAME OLD SIR - MUST BE ANOTHER INSTRUCTOR */		00019700
199	SAME SIR: N = N + 1;		00019800
200	IF (N <= 3) THEN GO TO FILL_INSTRUCTOR;		00019900
201	N = 1;		00020000
202	NL = NL + 1;		00020100
203	IF (NL <= 10) THEN GO TO FILL_INSTRUCTOR;		00020200
204	OUTNOWA: NL = 10;		00020300
205	OUTNOW: ROUTE = START_WHOLE_ASSIGNMENTS;		00020400
206	GO TO DISPLAY_ONE_PAGE;		00020500
207	START_NEW_COURSE:		00020600
208	NCRS = NCRS + 1;		00020700
209	SOLDCCP = CDP;		00020800
210			00020900
211	FILL_TOPPAGE:		00021000
212	L1COP = COP; L2CON1 = CON1; L3LEN1 = LEN1;		00021100
213	L1CRS = CRS; L2CON2 = CON2; L3LEN2 = LEN2;		00021200
214	L2CON3 = CON3; L3LEN3 = LEN3;		00021300
215	L2OFF = DFST; L3WL1 = CHWR2;		00021400
216			00021500
217	L4SCH = SCH; L5CAP1 = BCAP1; L7A0B = PAOB;		00021600
218	L4JND = JND; L5CAP2 = BCAP2; L7PF = PFAIL;		00021700
219	L4CAT = CTLG; L5CAP3 = BCAP3; L7AF = AFAIL;		00021800
220	L4PNEC = PNEC; L7TYPE = CTYPE;		00021900
221	L4PAOB = CAP; L6DMD1 = DMD1; L7PRTY = PRTY;		00022000

TAEK REPORT NO. 29


INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 -PGM19- FLOWCHARTS

CARD NO	****	CONTENTS	****
222	L4CAP2 = CAP2 :	L6DMO2 = DMO2 :	L7BD1 = BOMD1 :
223	L4CAP3 = CAP3 :	L6DMO3 = DMO3 :	L7BD2 = BOMD2 :
224	L4MR2 = CHWK3 :	L6BKLOG = BKLG :	L7BD3 = BOMD3 :
225			
226	L1OCMM = CMM :	L1ONADIS = NADIS :	L1OUCAP = UCAP :
227	L1OSUIC = SUIC :	L1ONOSHOW = NOSHOW :	L1OUDEN = UDEM :
228	L1ORDTE = RTE :	L1OSETB = SETB :	L1OTIN = TINSTR :
229	L1OPRTY = PPTY :	L1OMSETB = MSETB :	
230			
231	START_WHOLES_ASSIGNMENTS:		
232	NL = 0 :		
233	SICLR = ' ' :		
234	IMCLR = ' ' :		
235	RECYCLE1:		
236	N = 1 :		
237	NL = NL + 1 :		
238	ROUTE = FILL_SI_RATIO :		
239	GO TO SETLINE :		
240			
241	FILL_SI_RATIO:		
242	BSIR = SIR :		
243	BCHRS = CHRS :		
244	BCTYP = CTYP :		
245	SIROW (NL) = SIHLD :		
246	OLDOSIR = SIR :		
247			
248	FILL_INSTRUCTOR:		
249	BIO = IO :		
250	BQUAL = QUAL :		
251	BASSN = ASN :		
252	INTAB (NL, N) = INBLD :		
253	GO TO READ1 :		
254			
255			
256			
257	DISPLAY_ONE_PAGE:		
258	DISPLAY (LBLANK) :	/* PAGE CLEAR GOES HERE, */	
259	DISPLAY (LBLANK) :	/* WHENEVER AVAILABLE... */	
260			
261	/* LINES 1 THRU 10, HERE */		
262	DISPLAY (L1) :	DISPLAY (L2) :	DISPLAY (L3) :
263	DISPLAY (L4) :	DISPLAY (L5) :	DISPLAY (L6) :
264	DISPLAY (L7) :	DISPLAY (LBLANK) :	
265	DISPLAY (L9) :	DISPLAY (L10) :	
266			
267	/* TITLES (LINES 11-13), HERE */		
268	DISPLAY (LBLANK) :		
269	DISPLAY (L12) :		
270	DISPLAY (L13) :		
271			
272	/* NOW, FOR INSTRUCTOR ASSIGNMENTS SECTION */		
273	INOUT:	DO J = 1 TO NL :	
274		DLNE = SIROW(J) INROW(J) :	
275		DISPLAY (DLNE) :	
276		END INOUT :	
277		GO TO ROUTE :	/* VARIABLE EXIT ROUTER */
278			
279			
280	SETLINE: /* SUBROUTINE TO INSERT BLANK VERTICAL SEPARATORS */		
281	INTAB (NL,1) = LBL2 :		
282	INTAB (NL,2) = LBL2 :		
283	INTAB (NL,3) = LBL2 :		
284	GO TO ROUTE :	/* VARIABLE EXIT ROUTER */	
285			
286			
287	WINDUP:		
288	ROUTE = LAST_STEP :		
289	GO TO DISPLAY_ONE_PAGE :		
290			
291	LAST_STEP:		
292	IF (BEOF) THEN		
293	BUMEOF:	DO I	
294		FILLM1 = NC :	
295		DISPLAY (LBLANK) :	
296		DISPLAY (M1) :	
297		END BUMEOF :	
298			
299		FILLM2 = NCRS :	
300		DISPLAY (LBLANK) :	
301		DISPLAY (M2) :	
302		IF (BEOF)	
303		THEN DISPLAY ('** PGM16 TERMINATING ABNORMALLY') :	
304			
305	CLOSEM: CLOSE DATA (DUMP) :		
306		END PGM19 :	

CHART TITLE - PLOC PGM19 OPTIONS (MAIN)





TAEg REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGM19- FLOWCHARTS

PAGE 02

CHART TITLE - PROC PGM19 OPTIONS (MAIN)



236

II-220





TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGM19- FLOWCHARTS

PAGE 03

CHART TITLE - PROC PGM19 OPTIONS (MAIN)





(END DO)



237

II-221

CHART TITLE - PROC PGM19 OPTIONS (MAIN)



(END DO)



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PG 19 - FLOWCHARTS

PAGE 03

CHART TITLE - PROC PG19 OPTIONS (MAIN)

02.17--> 01
00000263

DISPLAY (L6)

00000264 02

DISPLAY (L7)

00000264 03

DISPLAY (L8 BLANK)

00000265 04

DISPLAY (L9)

00000265 05

DISPLAY (L10)

00000267 NOTE 06
* * * * *
* TITLES LINES *
* 11-13 HERE *
* * * * *

00000268 07

DISPLAY (L8 BLANK)

00000269 08

DISPLAY (L12)

00000270 09

DISPLAY (L13)

00000272 NOTE 10
* * * * *
* NOW FOR *
* INSTRUCTOR *
* ASSIGNMENTS *
* SECTION *
* * * * *

INOUT

00000273 11
DO J = 1 TO NL

00000273 12
END DO

END

00000274 13
ASSIGNMENT(S)

00000275 14
DISPLAY (DLINE)

END DO

(END DO)

239

II-223

/ 00000277 /

NOTE 16
* * * * *
* ASSIGNMENT(S) *
* * * * *

01.15-->

SETLINE

00000280 17

ASSIGNMENT(S)

...

* 6.01 *

...

ROUTE

/ 00000284 /

NOTE 18
* * * * *
* ASSIGNMENT(S) *
* * * * *

05.01-->

WINDUP

00000287 19

ASSIGNMENT(S)

...

* 2.09 *

...

DISPLAY ONE PAGE

PAGE 03

02.17--->
00000243 | 01

DISPLAY (L6)

00000264 | 02

DISPLAY (LT)

00000264 | 03

DISPLAY
(BLANK)

00000243 | 04

DISPLAY (L9)

00000245 | 09

DISPLAY (L10)

```

00000267 | NOTE 04
* * * * *
* TITLES | LINES *
* 11-13 | HERE *
* * * * *

```

00000248 | 07

/ /

DISPLAY
(LBLAMM)

55008249 | 08

DISPLAY (L12)

00000270 | 04

DISPLAY (113)

```

00000272 | NOTE 10
* * * * *
* NOW, FOR *
* INSTRUCTOR *
* ASSIGNMENTS *
* SECTION *
* * * * *

```

END DO

240





II-224

AUTOFLOW CHART SET - FINAL

PL/1 -PGM19- FLOWCHARTS

PAGE 03

CHART TITLE - PROC PGM19 OPTIONS (MAIN)




(END CC)

241

11-225

CHART TITLE - PROC PGM19 OPTIONS (MAIN)



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGM19- FLOWCHARTS

PAGE 05

CHART TITLE - ON-UNIT ACTION BLOCKS

/ 00000174 /

01.03--->

.ON-UNIT01

```

      *
00000174 | NOTE 01
* * * * *
* ON ENDFILE (DUMP) *
* * * * *
    
```

|

.

3.19.

.

WINDUP

END .ON-UNIT01

TAEG REPORT NO. 29

AUTOPLOW CHART SET - FINAL

PL/1 -PGW19- FLOWCHARTS

PAGE 06

CHART TITLE - LABEL ASSIGNMENT CROSS REFERENCE

/ ROUTE /	
03.159-->	01
SCALAR	
LABEL VARIABLE	
SET AT	TO GO TO
1.11	2.02
00000186	START_ME
1.15	2.01
00000193	SIR2
1.22	2.04
00000205	START_UH
2.06	2.07
00000238	FILL_SI
3.19	4.01
00000288	LAST_STE

PROGRAM NAME: PGM20

TYPE: PL/1

SYSTEM: Data Base Maintenance

NCSS FILENAME/FILETYPE: PGM20/PLI

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

Use of the RAMIS data maintenance function DUMP produces an 80 Byte (card image) output file, independent of the record length of the individual RAMIS records. As many card images per RAMIS record as required will be used to represent RAMIS records longer than 80 Bytes. For the Course data base, three (3) card-image records per RAMIS record are required.

For the Course data base, the field positions in the output of the DUMP are indicated in the following sample RAMIS output:

± EBCDIC RECORD LENGTH 80 CHARACTERS

<u>FIELD NAME</u>	<u>FORMAT</u>	<u>LENGTH</u>
SCH	A 4	4
CDP	A 4	4
DEL	A 1	1
CTLG	A 10	10
CRS	A 16	16
CONV1	I 3	3
LEN1	F4 .1	4
CAP1	I 3	3
BCAP1	I 3	3
DMD1	I 5	5
BDMD1	I 5	5
OFST	I 2	2
PFAIL	F5 .3	5
NADIS	F5 .3	5
NOSHOW	F5 .3	5
SETB	F5 .3	5
		X 0
BKLG	I 4	4
JNO	A 4	4
CONV2	I 3	3
LEN2	F4 .1	4
CAP2	I 3	3
BCAP2	I 3	3
DMD2	I 5	5
BDMD2	I 5	5
CHWK2	I 3	3
CONV3	I 3	3
LEN3	F4 .1	4
CAP3	I 3	3
BCAP3	I 3	3
DMD3	I 5	5

<u>FIELD NAME</u>	<u>FORMAT</u>	<u>LENGTH</u>
BDMD3	I 5	5
CHWK3	I 3	3
PAOB	I 4	4
AFAIL	F5 .3	5
PRTY	I 2	2
CTYPE	A 2	2
PNEC	A 4	4
UCAP	I 3	3
		X 0
UDEM	I 3	3
FPRTY	I 2	2
RDTE	I 6	6
HSETB	F5 .3	5
TINSTR	F4 .1	4
SUIC	A 5	5
CCMM	A 10	10
SIR	F4 .1	4
CHRS	F5 .1	5
CTYP	A 1	1
ID	A 9	9
QUAL	A 3	3
ASN	I 1	1

Note that no slack bytes were required at the end of each of the first two card images at the positions marked 'X'. Only 58 Bytes were required on the third card image to fully represent the Course data base RAMIS record.

Inputs to RAMIS data management functions must be singular records. It is the function of PGM20 to combine the data from the three card images representing each RAMIS record into a single logical record.

For the Course file, using input as indicated above, the output record is composed of the following:

Logical Record Length: 218 Bytes

PL/1 Base Data Structure Name: RTRANS

PL/1 Output Filename: TRANS

First 80 Bytes of Output Record = Direct copy of first of three input card images

Second 80 Bytes of Output Record = Direct copy of the second of three input card images

Last 58 Bytes of Output Record = Direct copy of the first 58 columns of the last of the three input card images

USAGE

Program PGM 20 is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC Sequence</u>	<u>Data Base</u>
E50	Course
E51	Course

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 -PGM20- FLOWCHARTS

PL/1 MODULE

(LIST,PARAMS,SOURCE)

CARD NO	CONTENTS	****
1	PGM20: /* COURSE FILE BOCH DUMP REFORMAT TO ZIBCH - MON/28/APR/75 */	00000100
2	PROC OPTIONS (MAIN) :	00000200
3		00000300
4		00000400
5	DECLARE RTRANS CHAR (218) STATIC INIT (' '), /* ZIB USED */	00000500
6	FSO CHAR (80) DEF RTRANS POS (1),	00000600
7	SBO CHAR (80) DEF RTRANS POS (81),	00000700
8	T9B CHAR (58) DEF RTRANS POS (161),	00000800
9	CARD CHAR (80) STATIC,	00000900
10	NR FIXED BIN STATIC INIT (0),	00001000
11	NR FIXED BIN STATIC INIT (0),	00001100
12	NR FIXED BIN (31,0) STATIC INIT (0),	00001200
13	IMESARC ENTRY (FIXED BINARY (31,0)),	00001300
14	M1 CHAR (52) STATIC INIT (	00001400
15	*** ERROR INDICATOR WAS -E- AT INPUT CARD COUNT X,XXX'),	00001500
16	PM1A PICTURE '9' DEF M1 POS (25),	00001600
17	PM1B PICTURE 'Z,ZZ9' DEF M1 POS (48),	00001700
18	M2 CHAR (66) STATIC INIT (	00001800
19	*** TOTAL INPUT CARDS PROCESSED = X,XXX; TOTAL TRANSACTIONS = X,XXX'),	00001900
20	PM2A PICTURE 'Z,ZZ9' DEF M2 POS (34),	00002000
21	PM2B PICTURE 'Z,ZZ9' DEF M2 POS (62) ;	00002100
22		00002200
23	STARTERRUPP:	00002300
24	OPEN FILE (CARDS) RECORD INPUT,	00002400
25	FILE (TRANS) RECORD OUTPUT ;	00002500
26	ON ENDFILE (CARDS) GO TO WRAPUP ;	00002600
27		00002700
28	R1: NR = 1 ;	00002800
29	READ FILE (CARDS) INTO (CARD) ;	00002900
30	NR = NR + 1 ;	00003000
31	FSO = CARD ;	00003100
32	M1 = 2 ;	00003200
33	READ FILE (CARDS) INTO (CARD) ;	00003300
34	NR = NR + 1 ;	00003400
35	SBO = CARD ;	00003500
36	M2 = 3 ;	00003600
37	READ FILE (CARDS) INTO (CARD) ;	00003700
38	NR = NR + 1 ;	00003800
39	T9B = CARD ;	00003900
40	WRITE FILE (TRANS) FROM (RTRANS) ;	00004000
41	NR = NR + 1 ;	00004100
42	GO TO R1 ;	00004200
43		00004300
44	WRAPUP:	00004400
45	IF (NR = 1) THEN	00004500
46	DO 1	00004600
47	DISPLAY ('*** CARD SEQUENCING ERROR AT EOF') ;	00004700
48	PM1A = NR ;	00004800
49	PM1B = NR ;	00004900
50	DISPLAY (M1) ;	00005000
51	DISPLAY ('*** ALL TRANSACTIONS IGNORED') ;	00005100
52	NR = 4 ;	00005200
53	GO TO CLOSERUP ;	00005300
54	END LASTER ;	00005400
55		00005500
56	PM2A = NR ;	00005600
57	PM2B = NR ;	00005700
58	DISPLAY (M2) ;	00005800
59		00005900
60	CLOSERUP:	00006000
61	CLOSE FILE (CARDS),	00006100
62	FILE (TRANS) ;	00006200
63		00006300
64	END PGM20 ;	00006400


TAE G REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGM20- FLOWCHARTS

PAGE 01

CHART TITLE - PROC PGM20 OPTIONS (MAIN)



249

II-233

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGM20- FLOWCHARTS

PAGE 02

CHART TITLE - ON-UNIT ACTION BLOCKS

/ 00000026 /

01.04--->0

.ON-UNIT 01

```

      *
00000026 1  NOTE 01
* * * * *
*   ON ENDFILE   *
*   (CARDS)      *
* * * * *

```

11

...

•

• 1 •

•

WEARUP

END .ON-UNITOI

PROGRAM NAME: PGM22

TYPE: PL/1

SYSTEM: Data Base Maintenance

NCSS FILENAME/FILETYPE: PGM22/PLI

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

This program examines the weekly Instructor time cards and determines whether the time data can be successfully entered to the Instructor data base. This operation involves assuring that the Instructor name and ID have been entered into the data base. Also checked are the proper assignment of Courses to each Instructor.

USAGE

Program PGM22 is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC</u> <u>Sequence</u>	<u>Data Base</u>
E22C	Instructor Master

INPUT FORMATS

The format of the weekly Instructor time card is shown on the following page in the illustration titled "Instructor Data Base Weekly Time Card Format". The time card file (filename - E22, filetype - SORT) will have been sorted via Executive Sequence E22A prior to run of program PGM22.

The second input file (filename = SPIN, filetype = DATA) to PGM22 is a reference file produced as output from Executive Sequence E22B. This file represents the current contents of the Instructor Master data base, and is structured as follows:

Logical Record Length: 17 Bytes

PL/1 Base Data Structure Name: RSPIN

Output PL/1 Filename: SPIN

<u>Start Record Position</u>	<u>Byte Length</u>	<u>PL/1 Identifier</u>	<u>Format</u>	<u>Description</u>
1	9	SID	A9	Instructor ID
10	4	SSCH	A4	Instructor School
14	4	SCDP	A4	Course CDP assigned to the indicated Instructor

One SPIN file record exists for each course assigned to each Instructor. Since the Instructor RAMIS data base is inherently sorted by Instructor ID and Course CDP, the SPIN file is sorted.

The Instructor time card file will be sorted to match the order of the SPIN file.

OUTPUT FORMATS

Three output files are produced via PGM22. They are:

<u>NCSS Filename</u>	<u>NCSS Filetype</u>	<u>Logical Record</u>	<u>PL/1 Filename</u>	<u>Contents</u>
E22	EMSG	61	EMSG	Error messages indicating discrepancies between time cards and data base contents
E22	BUST	80	ETRANS	Card images found to contain compare errors
E22	DATA	80	GOOD	Card images found to pass compare checks successfully

If no errors are detected in the processing of a batch of time cards, the error message and error card files (first two, above) will be empty. Conversely, if all cards are found to be in error, the E22/DATA file will be empty after PGM22 is run. Messages are output to the User terminal to indicate the exact results of PGM22 operation.

The two card-image files described above contain copies of the Instructor time cards; accordingly, the format of these two output files is the same as the input time card formats.

935-1115-0

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/I - PGR22- FLOWCHARTS

PL/I MODULE

(LIST, NAME, SOURCE)

CARD NO

CONTENTS

```


1  OPTION PACKED, COMPRESS
2  PGR22: /* TIME CARD PRE-PROCESSOR - NOV/30/JUNE/75 */
3  PROC OPTIONS (MAIN);
4
5  DECLARE CARD      CHAR (80) STATIC INIT (' ');
6  CID               CHAR (9) DEF CARD POS (1);
7  CSCH              CHAR (4) DEF CARD POS (10);
8  CDDP              CHAR (4) DEF CARD POS (14);
9  CF17              CHAR (17) DEF CARD POS (1);
10 RSPIN             CHAR (17) STATIC INIT (' ');
11 SID               CHAR (9) DEF RSPIN POS (1);
12 SSCH              CHAR (4) DEF RSPIN POS (10);
13 SCDP              CHAR (4) DEF RSPIN POS (14);
14
15 DECLARE (NC, NS, NER, NH, NOID, NOSCH, NOCDP
16          ) FIXED BIN STATIC;
17 MLINE              CHAR (61) STATIC INIT (' ');
18 ET                CHAR (3) DEF MLINE POS (7);
19 EC                CHAR (17) DEF MLINE POS (19);
20 ES                CHAR (17) DEF MLINE POS (45);
21 CCN                PICTURE 'Z,ZZ9' DEF MLINE POS (12);
22 SSN                PICTURE 'Z,ZZ9' DEF MLINE POS (38);
23 ROUTE              LABEL;
24
25 DECLARE PLINE1     CHAR (77) STATIC INIT (' ');
26 PLINE2             CHAR (61) STATIC INIT (' ');
27 PNC                PICTURE 'Z,ZZ9' DEF PLINE1 POS (18);
28 PNH                PICTURE 'Z,ZZ9' DEF PLINE1 POS (41);
29 PNID               PICTURE 'Z,ZZ9' DEF PLINE1 POS (57);
30 PNOCDDP             PICTURE 'Z,ZZ9' DEF PLINE1 POS (73);
31 PMS                PICTURE 'Z,ZZ9' DEF PLINE2 POS (18);
32 PNR                PICTURE 'Z,ZZ9' DEF PLINE2 POS (41);
33 PNOSCH              PICTURE 'Z,ZZ9' DEF PLINE2 POS (57);
34
35 STARTERRUP:
36 OPEN FILE (CARDS) RECORD INPUT;
37 FILE (SPIN) RECORD INPUT;
38 FILE (GOOD) RECORD OUTPUT;
39 FILE (MSG) RECORD OUTPUT;
40 FILE (ETRANS) RECORD OUTPUT;
41 ON ENDFILE (CARDS) GO TO WINDUP;
42 ON ENDFILE (SPIN) GO TO DOWETOOSOON;
43 ROUTE = R1;
44 NC, NS, NER, NH, NOID, NOSCH, NOCDP = 0;
45 PLINE1 = 'CARDS (NC) : X,XXX HITS (NH)';
46 || ' : X,XXX NOID : X,XXX NOCDP';
47 || ' : X,XXX';
48 PLINE2 = 'SPIN RECS (NS) : X,XXX ERRORS (NER)';
49 || ' : X,XXX NOSCH : X,XXX';
50
51 READ FILE (SPIN) INTO (RSPIN);
52 NS = 1;
53
54 R1: READ FILE (CARDS) INTO (CARD);
55 NC = NC + 1;
56 R1A: IF (CID = SID) THEN GO TO STEP2;
57 IF (CID < SID) THEN GO TO NODHIT_ID;
58 READ FILE (SPIN) INTO (RSPIN);
59 NS = NS + 1;
60 GO TO R1A;
61
62 STEP2: /* HERE, ID NUMBERS ARE EQUAL */
63 IF (CDDP = SCDP) THEN GO TO STEP3;
64 /* HERE, ID NUMBER HIT, CDDP HIT, NOW TEST SCHOOL */
65 IF (CSCH = SSCH) THEN GO TO NODHIT_SCH;
66 /* HERE, HITS ALL THE WAY... */
67 NH = NH + 1;
68 WRITE FILE (GOOD) FROM (CARD);
69 GO TO R1;
70
71 STEP3: /* HERE ID NUMBER HIT, CDDP MISMATCH - TRY ANOTHER CDDP */
72 READ FILE (SPIN) INTO (RSPIN);
73 NS = NS + 1;
74 IF (CID = SID) THEN GO TO NODHIT_CDDP;
75 GO TO STEP2;
76
77 NODHIT_ID: NOID = NOID + 1; ET = 'ID'; GO TO BUSTED;
78 NODHIT_CDDP: NOCDP = NOCDP + 1; ET = 'CDDP'; GO TO BUSTED;
79 NODHIT_SCH: NOSCH = NOSCH + 1; ET = 'SCH';
80
81 BUSTED:
82 NER = NER + 1; EC = CF17; ES = RSPIN;
83 CCN = NC;
84 WRITE FILE (MSG) FROM (MLINE);
85 WRITE FILE (ETRANS) FROM (CARD);
86 GO TO ROUTE;
87
88 DOWETOOSOON:
89 ROUTE = STEP4;
90 ET = 'EOP';
91 ON ENDFILE (CARDS) GO TO WINDUP;
92 GO TO BUSTED;
93
94 STEP4: READ FILE (CARDS) INTO (CARD);
95 NC = NC + 1;
96 GO TO BUSTED;
97
98 WINDUP:
99 CLOSE FILE (CARDS), FILE (SPIN), FILE (GOOD),
100 FILE (MSG), FILE (ETRANS);
101
102 DISPLAY ('TIME CARD PRE-PROCESSING COMPLETE');
103 PNC = NC; PNH = NH; PNID = NOID; PNOCDDP = NOCDP;
104 PMS = NS; PNR = NER; PNOSCH = NOSCH;
105 DISPLAY (PLINE1);
106 DISPLAY (PLINE2);
107
108 END PGR22;

```


PAGE 01

/ 00000002 /

PGM22




TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL PL/1 -PGM22- FLOWCHARTS

PAGE 02

CHART TITLE - PROC PGM22 OPTIONS (MAIN)



256

II-240

AUTOFLOW CHART SET - FINAL PL/1 -PGN22- FLOWCHARTS

PAGE 03

/ 00000041 /

.ON-UNITOL

```
00000041 | NOTE 01
* * * * *
*      ON ENDFILE      *
*      (CARDS)         *
* * * * *
```

...

• 2.11 •

WINDUP

END .ON-UNITOL

/ 00000042 /

ON-UNIT 02

```
00000042 | NOTE 02
* * * * *
* ON ENDFILE (SPIN) *
* * * * *
```

—

• 2.07 •

DONE TOO SOON

END .ON-UNIT02

/ 00000091 /

.OM-UNIT 03

```

00000001 | NOTE 03
* * * * *
*   ON ENDFILE   *
*   (CARDS)      *
* * * * *

```

—

• 2.11. •

THE MICHIGAN

END .ON-UNIT 03

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PGM22- FLOWCHARTS

PAGE 04

CHART TITLE - LABEL ASSIGNMENT CROSS REFERENCE

/ ROUTE /	
02.08-->	01
SCALAR	
LABEL VARIABLE	
SET AT TO GO TO	
1.09	1.12
00000043 R1	
2.07	2.09
00000089	STEP4

258

II-242

PROGRAM NAME: PROMPTX

TYPE: PL/1

SYSTEM: Data Base Maintenance

NCSS FILENAME/FILETYPE: PROMPT/PLI

A listing of the program source code and machine run flowcharts are included in this document on the pages following.

FUNCTION

This program is used in conjunction with each of the Executive Sequences termed "Class A Prompting Executives". Such Executive Sequences are used for data base maintenance (entry, change, deletion).

The PROMPTX program will direct the User at the terminal as to which data fields to enter. As a result of the manner in which the prompting text has been composed, the field format will also be a portion of the prompt. Some fields are mandatory, some optional. In the case of the optional types, the User may elect to let the field value default rather than provide a specific data entry from the terminal. A keyboard entry has been provided to allow the User to abort the data maintenance operation; such a request effectively cancels any further data maintenance operation that may have resulted.

The actions to be taken by PROMPTX in each of the Executive Sequences mentioned below is directed by a unique table input for each Sequence. The format of this table is discussed under INPUT FORMAT, below.

USAGE

Program PROMPTX is invoked during operation of the following Root Executive Sequences (NCSS Filetype = EXEC):

<u>EXEC Sequence</u>	<u>Data Base</u>
E1, W1 E2, W2	Facilities
E20, W20 E21, W21 E53, W53 E54, W54	Instructor
E40, W40 E41, W41 E42, W42 E64, W64	Course

INPUT FORMAT

PROMPTX is a table-driven program. The input table provides the text to be used in prompting the User at the terminal. Also included in the input table is data which directs PROMPTX in the validation of terminal input. The structure of the input file is:

Logical Record Length: 80 Bytes

PL/1 Base Data Structure Name: CARD

Input PL/1 Filename: TAB

<u>Card Columns</u>	<u>Format</u>	<u>Contents/Meaning</u>
*** TYPE -0- CARD ***		
1	A1	'0' means Type -0- Card
2/9	A8	'ACTION' Signifies "Action" Card
10	A1	'1' = PROMPTX program will be allowed to function in both NEW and CHANGE operational modes
		'2' = PROMPTX allowed to function only in NEW mode
11/12	A2	'1' = Special processing required at start of PROMPTX. Any entry other than '1', implies no special processing on entry.
13/14	A2	'1' = Special processing required on exit from PROMPTX (before writing the completed data maintenance transaction). Entry other than '1' indicates no such processing on exit.

<u>Columns</u>	<u>Format</u>	<u>Contents/Meaning</u>
----------------	---------------	-------------------------

*** TYPE -1- CARD ***

1	A1	'1' = Signifies Type -1- Card format
2/41	A40	Text to be output to the User terminal when PROMPTX commences operation. This text is output only once - prior to prompting for any data fields. As many lines of entry text may be included as desired. Note maximum 40 characters width.

NOTE - PROMPTX has internal array space for 100 lines of text (40 characters per line) - this must suffice for all entry text (Type -1- cards) plus all text required for data field prompting (Type -3- cards).

*** TYPE -3- CARD ***

1	A1	'3' = Signifies Type -3- Card format
2/41	A40	Text to be output when a data field is to be prompted. Line width is 40 characters max. Number of lines may vary - see restrictions on the total number of text lines under the description for the Type -1- card format.

*** TYPE -2- CARD ***

1	A1	'2' = Signifies Type -2- Card format
2/11	A10	Mnemonic name associated with the data field described on this card
12/13	Unused	
14	I1	Field Type: 1 = Character 2 = Integer 3 = Fraction
15/16	I2	For character fields only; maximum number of characters allowed. Zero (0) means don't care.
17/18	Unused	
19/34	A16	Default value for data field, if used; otherwise blank.

Columns	Format	Contents/Meaning
---------	--------	------------------

*** TYPE -2-, Continued ***

35	I1	Mandatory/optional flag; 1 = Cannot omit this field; User must supply a value from the terminal after prompting 2 = Can omit this field if User so indicates; use standard default (numeric = 0, alphabetic = blank). 3 = Can omit; use default provided in card columns 19/34
36	I1	Limit check flag for numeric fields: 1 = No limit check 2 = Check both upper and lower limits 3 = Check only high limit 4 = Check only lower limit
34/46		Numeric, may be signed and/or fractional = Lo limit numeric check, if used
47/56		Numeric, may be signed and/or fractional = Hi limit check for numeric field, if used
Note - Fields in card positions 57 - 63, inclusive, indicate the position and format of the data field in the output transaction. PROMPTX will place the default or verified User input data into this location. . . .		
57/58	I2	PL/1 PUT STRING verb remote format statement selector. Numeric fields will be converted to this format before entry to the output transaction: 01 = PL/1 Format F(6,1) 02 = PL/1 Format F(5,1) 03 = PL/1 Format F(3,1) 04 = PL/1 Format F(4,1) 05 = PL/1 Format F(5,3)
59/61	I3	Starting field position in the output transaction; legal values are 1 - 250
62/63	I2	Length of the data field in the output transaction; length plus starting position minus one cannot exceed 250

INPUT TABLE LAYOUT

Following are the rules to be followed in structuring a table for PROMPTX. The card formats were discussed above; they will be referenced below only by card type (0, 1, 2, or 3).

All input table card images must appear in the following order:

- (1) One (only) Type -0- card. If used, this must be first. Type -0- cards are valid only for the data fields associated with the Instructor data base.
- (2) As many Type -1- entry text cards as desired. If desired, Type -1- cards may be omitted altogether.

From one to 55 data fields may be prompted; the order of appearance in the input table will be the prompt order. Each data field prompt will be signified by:

One Type -2- card describing the data field.

One or more Type -3- cards representing one line per card of prompting text to be presented to the User.

The Type -2- card must precede the Type -3- card(s) for each data field. At least one of each must represent each data field.

Current maximum limitations for the PROMPTX program are:

55 data fields maximum

100 text lines distributed between the entry text and the prompting text for the data fields.

OUTPUT FORMAT FOR PROMPTX

Logical Record Length: 250 Bytes

PL/1 Base Data Structure Name: RTRANS

PL/1 Filename: TRANS (Attributes are RECORD UPDATE SEQUENTIAL)

Output file transaction format is as described in the reference table input.

If NEW is selected by the User as the PROMPTX operational mode, the transaction is blanked before filling with new data.

If CHANGE is selected as the operational mode, the single record of the transaction file is read into store before proceeding. This allows the User to change any/all fields or merely examine the fields' contents.

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/I - PROMPTX - FLOWCHARTS

PL/I MODULE

(LIST,NAMSG,SOURCE)

CARD NO

CONTENTS

```

1  OPTION PACKED,COMPRESS
2  PROMPTX:/* GP FIELD ENTRY AND TRANSACTION PROCESSOR - WED/16/APR/75 */ 00000100
3  PROC OPTIONS (MAIN) ; 00000200
4  00000300
5  DECLARE I P8(55), FT(55), MAXC(55), DSS(55), OMIT(55), LIMIT(55); 00000400
6  FSEL(55), START(55), LEN(55), NLINE(55), LISS(55); 00000500
7  NT, NER, NFLOS, M, NN, K, NMAX, J, L, MODE ; 00000600
8  FIXED BIN (15) STATIC ; 00000700
9  00000800
10 DECLARE MH (55) CHAR (12) STATIC INIT ( '551121' * ); 00000900
11 DEF (55) CHAR (16) STATIC INIT ( '551116' * ); 00001000
12 I LLO(55), LMI(55) ; FIXED DEC (8,2) STATIC; 00001100
13 NEW BIT (1) STATIC; 00001200
14 TEXT FIXED BIN (15) STATIC INIT ( 1 ); 00001300
15 NETXT FIXED BIN (15) STATIC INIT ( 0 ); 00001400
16 N FIXED BIN (15) STATIC INIT ( 0 ); 00001500
17 ( SAMP, LSAMP ) FIXED DEC (12,2) STATIC ; 00001600
18 00001700
19 DECLARE TEXT (100) CHAR (40) STATIC INIT ( (100)401 * ); 00001800
20 CARD CHAR (80) STATIC; 00001900
21 CTYPE CHAR (1) DEF CARD POS (1); 00002000
22 T40 CHAR (40) DEF CARD POS (2); 00002100
23 F40 CHAR (40) DEF CARD POS (3); 00002200
24 F70 CHAR (70) DEF CARD POS (4); 00002300
25 CTACT CHAR (7) DEF CARD POS (5); 00002400
26 LBLANM CHAR (10) STATIC INIT ( '' ); 00002500
27 RTRANS CHAR (250) STATIC; 00002600
28 TIMETYP CHAR (3) DEF RTRANS POS (80); 00002700
29 T100 CHAR (100) DEF RTRANS POS (1); 00002800
30 T200 CHAR (100) DEF RTRANS POS (101); 00002900
31 T50 CHAR (50) DEF RTRANS POS (201) ; 00003000
32 00003100
33 DECLARE REP CHAR (80) STATIC; 00003200
34 REP1 CHAR (1) DEF REP POS (1); 00003300
35 TRY12 CHAR (2) DEF REP POS (1); 00003400
36 REP2 CHAR (2) DEF REP POS (1); 00003500
37 TRYOUT CHAR (3) DEF REP POS (1); 00003600
38 TRYS CHAR (4) DEF REP POS (1); 00003700
39 TRYC CHAR (6) DEF REP POS (1); 00003800
40 REPTAB (80) CHAR (1) BASED (PR); 00003900
41 TRY16 CHAR (16) STATIC; 00004000
42 ( ROUTE, WAY, FF ) LABEL; 00004100
43 FORMS (10) LABEL 00004200
44 INIT ( RF1, RF2, RF3, RF4, RF5 ) ; 00004300
45 00004400
46 DECLARE TRYM CHAR (12) STATIC; 00004500
47 DERM CHAR (27) STATIC INIT 00004600
48 ( '*** ERROR ONCODE WAS XXXX *' ); 00004700
49 NONC PICTURE '9999' DEF DERM POS (22); 00004800
50 ERMSG CHAR (26) STATIC INIT 00004900
51 ( '*** ERROR # MN OCCURED ***' ); 00005000
52 NNER PICTURE 'Z9' DEF ERMSG POS (19); 00005100
53 PNNE CHAR (12) STATIC; 00005200
54 FN12 (12) CHAR (1) BASED (PF); 00005300
55 VMSG CHAR (39) STATIC ; IT 00005400
56 ( ' * CURRENT V' * ) ; 00005500
57 FILLV CHAR (14) DEF VMSG POS (24) ; 00005600
58 00005700
59 DECLARE LIMSG CHAR (47) STATIC INIT 00005800
60 ( ' * VALUE SUPPLIED OUTSIDE XX-LIMIT OF XXXXXXXX *' ); 00005900
61 TYPLIM CHAR (2) DEF LIMSG POS (26); 00006000
62 ILIMVAL PICTURE 'ZZZZZZZ9' DEF LIMSG POS (38); 00006100
63 FLIMVAL PICTURE 'ZZZZ9V.99' DEF LIMSG POS (38) ; 00006200
64 00006300
65 DECLARE IDEF CHAR (84) STATIC INIT ( 00006400
66 '1750000A1 A2 A3 A4 A5 A6 A7 B1 B2 B3 B4 B5 B6 B8A00.0000.0000.0' ); 00006500
67 TIDEF CHAR (84) DEF RTRANS POS (73); 00006600
68 FIRST BIT (1) STATIC INIT ( '1' ); 00006700
69 IMESARC ENTRY (FIXED BINARY(31,0)); 00006800
70 NORM FIXED BIN (15) STATIC INIT (1); 00006900
71 BSTDND FIXED BIN (15) STATIC INIT (0); 00007000
72 ASTAND FIXED BIN (15) STATIC INIT (0) ; 00007100
73 00007200
74 /* FOLLOWING ARE THE REMOTELY-CALLED FORMAT STATEMENTS */ 00007300
75 RF1: FORMAT ( F(6,1) ) ; 00007400
76 RF2: FORMAT ( F(5,1) ) ; 00007500
77 RF3: FORMAT ( F(3,1) ) ; 00007600
78 RF4: FORMAT ( F(4,1) ) ; 00007700
79 RF5: FORMAT ( F(5,3) ) ; 00007800
80 00007900
81 /*** ERROR ONCODE TRAP HERE ***/ 00008000
82 00008100
83 ON ERROR BEGIN ; 00008200
84 NONC = ONCODE ; 00008300
85 DISPLAY ( DERM ) ; 00008400
86 IF ( FIRST ) THEN DISPLAY ( FTO ) ; 00008500
87 NN = 0 ; 00008600
88 GO TO SETCODE ; 00008700
89 END ; 00008800
90 00008900
91 /*** DESCRIPTION FILE IS LOADED HERE ***/ 00009000
92 00009100
93 OPEN FILE (TAB) RECORD INPUT ; 00009200
94 ON ENDFILE (TAB) GO TO STARTUP ; 00009300
95 NN = 0 ; 00009400
96 00009500
97 ERT: NER = 7 ; 00009600
98 READ FILE (TAB) INTO (CARD) ; 00009700
99 IF ( CTACT = 'ACTION' ) THEN GO TO R1A ; 00009800
100 GET STRING (CARD) EDIT ( NORM, BSTDND, ASTAND ) 00009900
101 ( X(9), F(1), F(2), F(2) ) ; 00010000
102 00010100
103 00010200
104 ERI: NER = 1 ; 00010300
105 R1: READ FILE (TAB) INTO (CARD) ; 00010400
106 R1A: IF ( CTYPE = '1' ) THEN 00010500
107 DO ; 00010600
108 NETXT = NETAT + 1 ; 00010700
109 NN = NN + 1 ; 00010800
110 IF ( NN > 100 ) THEN GO TO ERT ;

```

TAGE REPORT NO. 29

INPUT LISTING

AUTOPLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

CARD NO	***	CONTENTS	****
110		TEXT (NN) = T40 ;	00010900
111		GO TO R1 ;	00011000
112		END L1 ;	00011100
113	ER2:	NER = 2 ;	00011200
114	ER2A:	IF (CTYPE = '2') THEN GO TO BUST ;	00011300
115	ER6:	NER = 6 ;	00011400
116		N = N + 1 ;	00011500
117		IF (N > 55) THEN GO TO BUST ;	00011600
118			00011700
119		GET STRING (CARD) EDIT	00011800
120		(MM(N), FB(N), FT(N), MAXC(N), DSS(N), DEF(N),	00011900
121		OMIT(N), LIMIT(N), LLO(N), LMI(N), PSEL(N),	00012000
122		START(N), LEN(N), NLINE(N), LISS(N))	00012100
123		(X(1), A(10), P(2), P(1), P(2), P(2), A(16),	00012200
124		P(1), P(1), P(10,2), P(10,2),	00012300
125		P(2), P(1), P(2), P(1), P(2)) ;	00012400
126			00012500
127		READ FILE (TAB) INTO (CARD) ;	00012600
128	ER3:	NER = 3 ;	00012700
129		IF (CTYPE = '3') THEN GO TO BUST ;	00012800
130			00012900
131		NN = NN + 1 ;	00013000
132	ER4:	NER = 4 ;	00013100
133		IF (NN > 100) THEN GO TO BUST ;	00013200
134		K = 1 ;	00013300
135		LISS (N) = NN ;	00013400
136		GO TO L2A ;	00013500
137			00013600
138	L2:	IF (CTYPE = '3') THEN GO TO L2B	00013700
139		NN = NN + 1 ;	00013800
140		IF (NN > 100) THEN GO TO BUST ;	00013900
141		K = K + 1 ;	00014000
142	L2A:	TEXT (NN) = T40 ;	00014100
143		NLINE (N) = K ;	00014200
144		READ FILE (TAB) INTO (CARD) ;	00014300
145		GO TO L2 ;	00014400
146			00014500
147	L2B:		00014600
148	ER5:	NER = 5 ;	00014700
149		GO TO ER2A ;	00014800
150			00014900
151		/*** HERE, DESCRIPTION TABLE EOF: INITIAL ROUTINE ENTRY PROMPTED ***/	00015000
152			00015100
153	STARTUP:		00015200
154		NN = N ;	00015300
155		CLOSE FILE (TAB) ;	00015400
156		FIRST = '0'B ;	00015500
157			00015600
158		(NEXT < 1) THEN GO TO WHICHWAY ;	00015700
159	L3:	DO J = 1 TO NEXT ;	00015800
160		DISPLAY (TEXT(J)) ;	00015900
161		END L3 ;	00016000
162			00016100
163	WHICHWAY:		00016200
164		OPEN FILE (TRANS) SEQUENTIAL UPDATE ;	00016300
165		READ FILE (TRANS) INTO (TRANS) ;	00016400
166			00016500
167		ON CONVERSION BEGIN ;	00016600
168		NONC = ONCODE ;	00016700
169		DISPLAY (DERM) ;	00016800
170		GO TO NEWLOOP ;	00016900
171		END ;	00017000
172			00017100
173	STEP1:		00017200
174		DISPLAY (LBLANK) ;	00017300
175		IF (NORM = 1) THEN GO TO NEWSTUFF ;	00017400
176		DISPLAY (LBLANK) ;	00017500
177		DISPLAY ('O SPECIFY EITHER NEW OR CHANGE ')	00017600
178		REPLY (REP) ;	00017700
179		IF (TRYOUT = 'NEW') THEN GO TO NEWSTUFF ;	00017800
180		IF (TRYC = 'CHANGE') THEN GO TO CHANGEIT ;	00017900
181		IF (TRYOUT = 'OUT') THEN GO TO OUTNOW ;	00018000
182			00018100
183		ROUTE = STEP1 ;	00018200
184	VOS1:	DISPLAY ('O CANNOT RECOGNIZE LAST ENTRY - TRY AGAIN ') ;	00018300
185		GO TO ROUTE ;	00018400
186			00018500
187		/*** BRAND NEW TRANSACTIONS MADE UP IN THIS SECTION ***/	00018600
188			00018700
189	NEWSTUFF:		00018800
190		NEW = '1'B ;	00018900
191		N = 1 ;	00019000
192		ATrans = ' ' ;	00019100
193		IF (STAND = 1) THEN	00019200
194		TIDEF = IDEF ;	00019300
195			00019400
196	NEWLOOP:		00019500
197		IF (-NEW) THEN GO TO OLDE ;	00019600
198		L = NLINE (N) ;	00019700
199	L4A:	J = LISS (N) - 1 ;	00019800
200		DISPLAY (LBLANK) ;	00019900
201	L4:	DO K = 1 TO L ;	00020000
202		J = J + 1 ;	00020100
203		IF (K = L) THEN GO TO STEP2 ;	00020200
204		DISPLAY (TEXT (J)) ;	00020300
205		END L4 ;	00020400
206			00020500
207	STEP2:	DISPLAY (TEXT (J))	00020600
208		REPLY (REP) ;	00020700
209		IF (TRYOUT = 'OUT') THEN GO TO OUTNOW ;	00020800
210			00020900
211		NN = N ;	00021000
212		IF (TRYS = 'DONE') THEN	00021100
213	HAYBDONE:	DO N = NN TO MAX ;	00021200
214		IF (OMIT(N) = 1) THEN GO TO MAY1 ;	00021300
215		DISPLAY ('O CANNOT OMIT FIELD CALLED ' MM(N)) ;	00021400
216		GO TO NEWLOOP ;	00021500
217	MAY1:	SUBST (ATrans, START(N), LEN(N)) = DEF (N) ;	00021600
218		IF (N = MAX) THEN GO TO FINISH_TRANSACTION ;	00021700
219		END HAYBDONE ;	00021800
220			00021900
221			00022000

TAE G REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

CARD NO	****	CONTENTS	****
222		IF (TRYS = 'N')) (TRYS = 'ND')) (TRYS = 'NONE') THEN	00022100
223	L5:	DO I	00022200
224		IF (OMIT(N) ~ 1) THEN GO TO STEP3 I	00022300
225		DISPLAY (' * CANNOT OMIT THIS ENTRY -TRY AGAIN * ') I	00022400
226		GO TO NEWLOOP I	00022500
227	STEP3:	SUBSTR (ATRANS, START(N), LEN(N)) = DEF (N) I	00022600
228		GO TO TALLY I	00022700
229		END L5 I	00022800
230			00022900
231	LOOKAT:	TRY16 = REP I	00023000
232	CHARACTER_FIELD:		00023100
233		IF (PT(N) = 1) THEN	00023200
234	L6:	DO I	00023300
235		J = MAXC (N) + 1 I	00023400
236		IF (J >= 15) THEN GO TO MAKETRANS I	00023500
237		K = INDEX (TRY16, ' ') I	00023600
238		IF ((K > 0) & (K <= J)) THEN GO TO MAKETRANS I	00023700
239		DISPLAY (' * MAX NUMBER CHARACTERS EXCEEDED * ') I	00023800
240		GO TO NEWLOOP I	00023900
241		END L6 I	00024000
242			00024100
243	NUMERIC_FIELD:		00024200
244		L = LEN (N) I	00024300
245		J = PT (N) I	00024400
246		K = LIMIT (N) I	00024500
247			00024600
248		NT = INDEX (TRY16, ' ') - 1 I	00024700
249		IF (NT = 0) THEN SIGNAL CONVERSION I	00024800
250		IF (INDEX(TRY16,'-') ~ 0) THEN SIGNAL CONVERSION I	00024900
251		IF (INDEX (SUBSTR(TRY16,1,NT), ' ') = 0)	00025000
252		THEN GET STRING (SUBSTR(TRY16,1,NT)) EDIT	00025100
253		(SAMP) (P(NT)) I	00025200
254		ELSE GET STRING (SUBSTR(TRY16,1,NT)) EDIT	00025300
255		(SAMP) (P(NT,1)) I	00025400
256			00025500
257		GO TO PROCESS I	00025600
258			00025700
259	DCL	TESTLINE CHAR (60) STATIC INIT (	00025800
260		'** TESTLINE = XXXXXXXX.XX XXXXXXXX.XX XXXXXXXX.XX XXXXXXXX.XX'	00025900
261		) I	00026000
262		TP1 PICTURE '999999999V.99' DEF TESTLINE POS (15),	00026100
263		TP2 PICTURE '999999999V.99' DEF TESTLINE POS (29),	00026200
264		TP3 PICTURE '999999999V.99' DEF TESTLINE POS (43),	00026300
265		TP4 PICTURE '999999999V.99' DEF TESTLINE POS (57) I	00026400
266			00026500
267	BUGDE:	TF1 = SAMP I	00026600
268		TF2 = LLO (N) I	00026700
269		TF3 = LHI (N) I	00026800
270		DISPLAY (TESTLINE) I	00026900
271		DISPLAY (' **REP16**' SUBSTR(REP,1,16) '**') I	00027000
272		DISPLAY (' **TRY16**' TRY16 '**') I	00027100
273			00027200
274			00027300
275	PROCESS:	IF (K = 1) THEN GO TO MAKETRANS I	00027400
276			00027500
277		IF (K = 3) THEN	00027600
278	DOHI:	DO I	00027700
279		ROUTE = MAKETRANS I	00027800
280	TRYHI:	IF (SAMP <= LHI(N)) THEN GO TO ROUTE I	00027900
281		LSAMP = LHI (N) I	00028000
282		TYPLIN = 'HI' I	00028100
283	BUSTLIN:	IF (J = 2)	00028200
284		THEN (LINVAL = LSAMP I	00028300
285		ELSE PLINVAL = LSAMP I	00028400
286		DISPLAY (LINSG) I	00028500
287		GO TO NEWLOOP I	00028600
288		END DOHI I	00028700
289			00028800
290		IF (K = 4) THEN	00028900
291	DOLO:	DO I	00029000
292		IF (SAMP >= LLO(N)) THEN GO TO MAKETRANS I	00029100
293		LSAMP = LLO (N) I	00029200
294		TYPLIN = 'LO' I	00029300
295		GO TO BUSTLIN I	00029400
296		END DOLO I	00029500
297			00029600
298	TEST_BOTH_LIMITS:		00029700
299		ROUTE = DOLO I	00029800
300		GO TO DOHI I	00029900
301			00030000
302	MAKETRANS:		00030100
303		L = LEN (N) I	00030200
304		IF (PT(N) = 1) THEN	00030300
305	DOCHAR:	DO I	00030400
306		SUBSTR (ATRANS, START(N), L) = TRY16 I	00030500
307		GO TO TALLY I	00030600
308		END DOCHAR I	00030700
309			00030800
310		IF (PT(N) ~ 2) THEN GO TO DOFRACTION I	00030900
311	DOINTEGER:	PUT STRING (SUBSTR(ATRANS, START(N), L)) EDIT	00031000
312		(SAMP) (P(L)) I	00031100
313		GO TO TALLY I	00031200
314			00031300
315	DOFRACTION:		00031400
316		PF = FORMS (PSELIN) I	00031500
317		PUT STRING (SUBSTR(ATRANS, START(N), L)) EDIT	00031600
318		(SAMP) (R(PF)) I	00031700
319		GO TO TALLY I	00031800
320			00031900
321	*** CENTRAL TALLY SECTION FOLLOWS ***		00032000
322			00032100
323	TALLY:		00032200
324		IF (~NEW) THEN GO TO OLDE I	00032300
325		N = N + 1 I	00032400
326		IF (N <= NMAX) THEN GO TO NEWLOOP I	00032500
327			00032600
328	FINISH_TRANSACTION:		00032700
329		REWRITE FILE (TRANS) FROM (ATRANS) I	00032800
330			00032900
331	FIN_TRAN:		00033000
332		CLOSE FILE (TRANS) I	00033100
333		DISPLAY (LBLANK) I	00033200

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPT - FLOWCHARTS

CARD NO	CONTENTS	
334	DISPLAY ('A TRANSACTION(S) HAS/HAVE BEEN REWRITTEN') ;	00033300
335	NN = 0 ;	00033400
336	GO TO SETCODE ;	00033500
337		00033600
338	TRYSET: NN = 0 ;	00033700
339	IF (TRYS = 'DONE') THEN GO TO SETCODE ;	00033800
340		00033900
341	/* TEMPORARY REPEAT FOR DEBUG PURPOSES */	00034000
342	DISPLAY (LBLANK) ;	00034100
343	DISPLAY ('A DEBUG REPEATING TO LABEL = WHICHWAY *') ;	00034200
344	GO TO WHICHWAY ;	00034300
345		00034400
346	/* CORRECT AN EXISTING TRANSACTION IN THIS SECTION */	00034500
347		00034600
348	CHANGEIT:	00034700
349	NEW = 'O'B ;	00034800
350	PR = ADDR (REP) ;	00034900
351	PF = ADDR (FNAME) ;	00035000
352		00035100
353	OLDE:	00035200
354	ASK2: DISPLAY (LBLANK) ;	00035300
355	DISPLAY ('A SPECIFY SHOW OR CHANGE')	00035400
356	REPLY (REP) ;	00035500
357	IF (TRYOUT = 'OUT') THEN GO TO OUTNOW ;	00035600
358	IF (TRYS = 'DONE') THEN GO TO FINISH_TRANSACTION ;	00035700
359		00035800
360	IF (TRYS = 'SHOW') THEN	00035900
361	DO 1	00036000
362	J = 5 ;	00036100
363	L7A: MODE = 1 ;	00036200
364	GO TO LOOKB ;	00036300
365	END L7 ;	00036400
366	J = 2 ;	00036500
367	IF (TRY12 = 'S') THEN GO TO L7A ;	00036600
368		00036700
369	IF (TRYC = 'CHANGE') THEN	00036800
370	DO 1	00036900
371	J = 7 ;	00037000
372	L8A: MODE = 2 ;	00037100
373	GO TO LOOKB ;	00037200
374	END L8 ;	00037300
375	J = 2 ;	00037400
376	IF (TRY12 = 'C') THEN GO TO L8A ;	00037500
377		00037600
378	DISPLAY ('A FIRST WORD OF REPLY UNKNOWN *') ;	00037700
379	GO TO ASK2 ;	00037800
380		00037900
381	LOOKB: IF (REPTAB(J) = ' ') THEN GO TO STEP5 ;	00038000
382		00038100
383	IF (J < 15) THEN GO TO STEP4 ;	00038200
384	DISPLAY ('A CANNOT DETERMINE ENTRY FORMAT *') ;	00038300
385	GO TO ASK2 ;	00038400
386		00038500
387	STEP4: J = J + 1 ;	00038600
388	GO TO LOOKB ;	00038700
389	STEP5: FNAME = ' ' ;	00038800
390	L = 1 ;	00038900
391	GO TO FILLJ ;	00039000
392		00039100
393	FILLN: IF (REPTAB(J) = ' ') [(REPTAB(J) = '*')	00039200
394	THEN GO TO FIND ;	00039300
395	FILLJ: FNAME (L) = REPTAB (J) ;	00039400
396	L = L + 1 ;	00039500
397	IF (L <= 12) THEN GO TO BUMPJ ;	00039600
398	DISPLAY ('A MNEMONIC HAS TOO MANY CHARACTERS *') ;	00039700
399	GO TO ASK2 ;	00039800
400	BUMPJ: J = J + 1 ;	00039900
401	GO TO FILLN ;	00040000
402		00040100
403	FIND: DO K = 1 TO NMAR ;	00040200
404	N = K ;	00040300
405	IF (FNAME = MNIN) THEN GO TO STEP6 ;	00040400
406	END FIND ;	00040500
407	DISPLAY ('A UNKNOWN MNEMONIC - TRY AGAIN *') ;	00040600
408	GO TO ASK2 ;	00040700
409		00040800
410		00040900
411	STEP6: IF (MODE = 2) THEN GO TO STEP7 ;	00041000
412	FILLV = SUBSTR (RTP.NS, START, LEN(N)) ;	00041100
413	DISPLAY (VRSG) ;	00041200
414	GO TO ASK2 ;	00041300
415		00041400
416	STEP7: IF (REPTAB(J) = '*') THEN GO TO STEP9 ;	00041500
417	IF (REPTAB(J) = ' ') THEN GO TO STEP8 ;	00041600
418		00041700
419	STEP7A: DISPLAY ('A ENTRY FORMAT ????? - TRY AGAIN *') ;	00041800
420	GO TO ASK2 ;	00041900
421		00042000
422	STEP8: IF (J >= 80) THEN GO TO STEP7A ;	00042100
423	J = J + 1 ;	00042200
424	GO TO STEP7 ;	00042300
425		00042400
426	STEP9: IF (J > 79) THEN GO TO STEP7A ;	00042500
427	J = J + 1 ;	00042600
428	IF (REPTAB(J) = '*') THEN GO TO STEP10 ;	00042700
429	IF (J >= 80) THEN GO TO STEP7A ;	00042800
430	GO TO STEP9A ;	00042900
431		00043000
432	STEP10: TRY16 = SUBSTR (REP, J) ;	00043100
433	GO TO CHARACTER_FIELD ;	00043200
434		00043300
435	/* ERROR TERMINATIONS HERE */	00043400
436		00043500
437	BUST: NMER = MER ;	00043600
438	DISPLAY (ERMSG) ;	00043700
439		00043800
440		00043900
441	/* TERMINUS SECTION FOLLOWS */	00044000
442		00044100
443	OUTNOW:	00044200
444	NN = 4 ;	00044300
445	CLOSE FILE (TRAN) ;	00044400

TAEG REPORT NO. 29

CARD NO	INPUT LISTING	AUTOFLOW CHART SET - FINAL	PL/1 - PROMPTX- FLOWCHARTS
	****	CONTENTS	****
446		DISPLAY (** NOW EXITING BY COMMAND **) ;	00044500
447		DISPLAY (** TRANSACTION HAS NOT BEEN RE-WRITTEN **) ;	00044600
448			00044700
449	SETCODE1	CALL IHESARC (NN) ;	00044800
450			00044900
451		END PROMPTX ;	00045000


TAE G REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

PAGE 01

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)



270

II-254


TAEQ REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

PAGE 02

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)



271


TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

PAGE 03

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)



AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX- FLOWCHARTS

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)




TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

PAGE 05

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)




TAEF REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

PAGE 06

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)



275

II-259


TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PROMPTX- FLOWCHARTS

PAGE 07

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)



276

II-260

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX- FLOWCHARTS

PAGE 08

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)







CHART TITLE - PROC PROMPTX OPTIONS (MAIN)



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX- FLOWCHARTS

PAGE 10

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)





CHART TITLE - PROC PROMPTX OPTIONS (MAIN)



AUTOFLOW CHART SET - FINAL

PAGE 12

/ 00000393 /

12.09- - - > *

FILM

00000193 • 01

• (REPTAB (J) •
= 1 1)
• (REPTAB (J) •

11.04----->

FILLJ

```
00000399 | 02
-----
| ASSIGNMENT(S) |
```

00000397 • 01

(L C= 12)

00000398 | 04

/ DISPLAY (10) /
 / MNEMONIC HAS /
 / TOO MANY /
 / CHARACTERS (1) /

10.09

ASK2

FINO

```

00000403 | 09
-----
| DO K = 1 TO NMAX |

```

00000403 • 06

END OO

```
00000404 | 01
| ASSIGNMENT(S) |
```

00000405 08

(END DO)

BUMP J

```
00000400 |
-----|
| ASSIGNMENT(S) |
```

•

FILLN

```

----->
00000408 | 10
-----
/      /
/  DISPLAY (00  /
/  UNKNOWN      /
/ MNEMONIC - TRY /
/  AGAIN *')    /

```

10.00

ASR 2

STEP 4

00000411 11

```

00000412 | 12
-----|
| ASSIGNMENT(S) |

```

00000413 | 13

/ /
/ DISPLAY (VMSG) /
/ /

10.0%

ASK 2

STEP 7

00000416 • 14

00000417 • 15

STEP 7A

00000419 | 1

```

/
/  DISPLAY (?? /
/  ENTRY FORMAT /
/  ??????? - TRY /

```

100

ASK2



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

PAGE 13

CHART TITLE - PROC PROMPTX OPTIONS (MAIN)



PAGE 14

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX - FLOWCHARTS

PAGE 15

CHART TITLE - CALLED PROCEDURES - CROSS REFERENCE

ENTRY		
	0	01
M	I	I
M	INESARC	I
M	CALLED FROM	I
M		I
M		I
I	.10003	1.26

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTK- FLOWCHARTS

PAGE 16

CHART TITLE - SIGNALLED ON-UNIT ACTION BLOCKS

CONVERSION

	ON-UNIT BLOCK	
	.ON-UNIT03 14.08	
	SIGNALLED AT	
	.10001 8.04	
	.10002 8.06	

CHART TITLE - LABEL ASSIGNMENT CROSS REFERENCE

```

-----
/  PF  /
-----
|
|
| 01
-----
| SCALAR |
| LABEL VARIABLE |
-----
| SET 11 TO GO TO |
| 8.09 17.02 |
| 00000316 FORMS |
-----

```

```

-----
/  FORMS  /
-----
|
| 17.01-->|
|
| 02
-----
| ARRAY |
| LABEL VARIABLE |
-----
| VALUE AMBIGUOUS |
-----

```

```

-----
/  ROUTE  /
-----
|
| 03.20*-->|
|
| 03
-----
| SCALAR |
| LABEL VARIABLE |
-----
| SET A7 TO GO TO |
| 3.19 3.12 |
| 00000183 STEP1 |
| 8.01 7.10 |
| 00000279 MAKETRAN |
| 8.08 7.02 |
| 00000299 DOLO |
-----

```

TAEK REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 - PROMPTX- FLOWCHARTS

PAGE 18

CHART TITLE - GET/PUT, FORMAT STATEMENTS

```

00000075 RF1      FORMAT (F (6,1))
00000076 RF2      FORMAT (F (5,1))
00000077 RF3      FORMAT (F (3,1))
00000078 RF4      FORMAT (F (4,1))
00000079 RF5      FORMAT (F (5,3))
00000100      .GET/PUT 001 GET STRING (CARD) EDIT (NORM,BSTAND,ASTAND) (X (9),F (1),F (2),F (2))
00000119      .GET/PUT 002 GET STRING (CARD) EDIT (MM (N),PB (N),FT (N),MARC (N),OSS (N),DEF (N),OMIT (N),
00000121          LIMIT (N),LLO (N),LHI (N),FSEL (N),START (N),LEN (N),NLINE (N),LISS (N)) (X (1),A (10),
00000123          F (2),F (1),F (2),F (2),A (16),F (1),F (1),F (10,2),F (10,2),F (2),F (3),F (2),F (1),
00000125          F (2))
00000252      .GET/PUT 003 GET STRING (SUBSTR (TRY16,1,NT)) EDIT (SAMP) (F (NT))
00000254      .GET/PUT 004 GET STRING (SUBSTR (TRY16,1,NT)) EDIT (SAMP) (F (NT,1))
00000311      .GET/PUT 005 PUT STRING (SUBSTR (RTRANS,START (N),L)) EDIT (SAMP) (F (L))
00000317      .GET/PUT 006 PUT STRING (SUBSTR (RTRANS,START (N),L)) EDIT (SAMP) (R (PF))

```


SECTION III

ETE MODEL

MODEL DESCRIPTION

FUNCTIONAL DESCRIPTION. The ETE Model is a set of six (6) NCSS Executive procedures, two (2) FORTRAN programs and one GPSS program. During operational use, the system will also include application-specific GPSS programs generated by the user. The basic purpose of this set of procedures and programs is either to: produce a new, executable GPSS model or update an existing GPSS model. In addition to the programs already mentioned, the ETE model makes extensive use of the NCSS edit program in several modes of operation.

Figure III-1 shows the different possible execution modes of the ETE model. Figure III-2 is a more detailed presentation of overall system logic. The name of the procedure or program used to execute each step in system operation is shown in Figure III-2 along with a few explanatory words about some of the procedures and programs. Table III-1 lists the names of all procedures and programs with a brief description of each one.

The ETE model uses all standard NCSS conventions for file specification and usage. Terminal input is FORTRAN logical 5 and output is FORTRAN logical 6. File descriptions in terms of record length, sequential/random etc. can be obtained by checking the filetype designation against the file descriptions contained in the NCSS documentation. Data files used by the ETE model are summarized in Figure III-3.

Throughout this section, a procedure or executive always refers to a control element written in the NCSS EXEC or CSS languages. A program will always be written in either FORTRAN or GPSS. Note that, as delivered, no executable GPSS programs (models) exist. In order to test the system, an executable GPSS model must be developed, following standard procedures, and that model executed (see User's Guide).





FIGURE III-1 ETE MODEL OPERATION PROCEDURE OVERVIEW



ETE MODEL LOGIC OVERVIEW

FIGURE III-2

ETE2 - The main control executive for the system. ETE2 is always invoked to begin an operational session and is returned to after each step.

HAL4 - Executive - Defines a file called TURK EXEC as logical unit 3 and causes execution of program PROF.

PROF - Program - A FORTRAN program which interacts with the user in in conversational mode and generates a set of GPSS source statements. These source statements are written on logical 3 (TURK EXEC)

TURK - Executive - a skeleton executive which edits either original GPSS source statements into DUMMY GPSS on change statements into an existing GPSS file named by the user.

DUMMY - Program - a GPSS program containing all model execution logic but no data. Execution data (i.e., ILS configuration specifications) are entered by TURK EXEC in the form of GPSS source statements (FUNCTION statements, VARIABLE statements, etc.).

HAL - Executive - This executive defines a file (Logical 3) which carries the name TURK EXEC and executes program MAD.

MAD - Program - a FORTRAN program which accepts model change requests from the user and generates the necessary replacement GPSS statements or CDS EDIT commands required to incorporate these changes in the model file specified by the user. MAD uses logical 2 as the existing model file and logical 3 as the file on which the change requests are listed.

ETEPTR - Executive - This executive locates the output listing of the current model execution run and prints or displays it. The output file may be listed in its entirety or in parts according to user request.

GPSS - Executive - GPSS EXEC stacks answers to all NGPSSV messages and passes the current model file name to the NGPSSV system for compilation and execution.

ETE PROGRAMS AND EXECUTIVES

TABLE III-1

FILE NAME	FILE TYPE	FORTRAN UNIT	PROGRAM USING	CONTENTS
USER SUPPLIED (&MODEL)	GPSS	2	MAD NGPSSV	User Generated GPSS Source Programs.
TURK	EXEC	3	PROF MAD	CSS EDIT Commands for Model Generation and Update
DUMMY	GPSS	-	TURK	GPSS Source Statements
&MODEL (USER SUPPLIED)	LISTING	-	FTEPTR	Output from Model Execution

ETE DATA FILE SUMMARY

FIGURE III-3

EXECUTIVE SUBSYSTEM

Within this subsystem are all the procedures written in the NCSS EXEC or CSS languages. All control of program execution is contained within this subsystem as are all provisions for user selection of different system paths. Two of the six executives exist as separate procedures only because they are sometimes used separately during debugging of the two major FORTRAN programs in the system. TURK EXEC is a skeleton procedure which is generated for each execution. Because of this, only two procedures: ETE2 and ETEPTR will be discussed in detail and flow diagrams provided. Figure III-4 is a flow diagram of the executive subsystem.


ETE2 is the control executive for the complete ETE model system. All returns from other executives and programs are made either to ETE2 or to CSS control.


The ETE model system is invoked by entering: ETE2 at the terminal. Once control has been passed to ETE2 the system is transparent to the user with regard to program or executive names. All control takes place via YES/NO or menu selection (integer) response.

Currently, no provision is made for the user to force exit from ETE2, once it has been entered, other than the standard CSS usage of the BREAK or ATTN keys. This procedure is outlined in the NCSS VP/CSS Reference Manual.

ETE2 control flow is presented in macro form in Figure III-1 and in more detailed form (including program and procedure names) in Figure III-2. Figure III-4 contains detailed logic flows of the two principal executives ETE2 and ETEPTR.

ETEPTR depends upon the presence of a LISTING file formatted by the report writer contained in DUMMY GPSS. ETEPTR searches for the output section headings supplied by the report writer (e.g. STUDENT STATISTICS, INSTRUCTOR STATISTICS, etc.) and will not provide output from a standard GPSS output format. In the event that model execution terminates prematurely for any reason (and the report writer is not entered) ETEPTR cannot be used for output display.





ETEPTR EXECUTIVE LOGIC FLOW
FIGURE III-4

ETE2 EXEC
VP/CSS

```

&TYPE OFF
-LABA &PRINT PLEASE ENTER THE NAME OF YOUR MODEL.
&READ ARGS
&IF &INDEX EQ 0 &GOTO -LABA
&MODEL = &1
-LABB &PRINT IS THIS A NEW MODEL?
&READ ARGS
&IF &INDEX EQ 0 &GOTO -LABB
&IF &1 EQ YES &GOTO -LABC
&IF &1 EQ NO &GOTO -LAB0
&PRINT INVALID ENTRY
&GOTO -LABB
-LABC &STACK &MODEL
EXEC HAL4
-LAB0 &PRINT ETE EXEC READY FOR INPUTS
-LAB1 &PRINT IS ETE INPUT TO BE MODIFIED
&PRINT ENTER : YES OR NO (TO REVIEW PREVIOUS OUTPUT ENTER : SKIP)
&READ ARGS
&IF &INDEX EQ 0 &SKIP -3
&IF &1 EQ NO &GOTO -ENT2
&IF &1 EQ N &GOTO -ENT2
&IF &1 EQ YES &GOTO -ENT1
&IF &1 EQ Y &GOTO -ENT1
&IF &1 EQ SKIP &GOTO -SKIP
&PRINT INVALID ENTRY
&SKIP -9
-ENT1 &PRINT MODIFY MODEL PARAMETERS
&STACK &MODEL
FILEDEF 2 DSK &MODEL GPSS DISP OLD
EXEC HAL &MODEL
&PRINT DO YOU WISH TO EXECUTE THE MODEL?
&READ ARGS
&IF &1 EQ YES &GOTO -ENT2
&IF &1 EQ NO &EXIT
-ENT2 EXEC GPSS &MODEL
-SKIP &CONTINUE
&PRINT IS ETE OUTPUT TO GO OFF LINE
&PRINT ENTER : OFF OR TERM
&READ ARGS
&IF &INDEX EQ 0 &SKIP -3
&IF &1 EQ TERM &GOTO -LAB3
&IF &1 EQ T &GOTO -LAB3
&IF &1 EQ OFF &GOTO -LAB4
&IF &1 EQ 0 &GOTO -LAB4
&PRINT INVALID ENTRY
&SKIP -9
-LAB4 OFFLINE PRINT ETE LISTING
&GOTO -TERM

```

ETE2 EXEC

```

-LAB3 &PRINT FOLLOWING ETE DATA AVAIL.
&PRINT 1). STUDENT STATISTICS
&PRINT 2). INSTRUCTOR STATISTICS
&PRINT 3). MODULE UTILIZATION
&PRINT 4). OTHER FACIL UTILIZ
&PRINT 5). ALL OUTPUT
&PRINT ENTER 1,2,3,4,5
&READ ARGS
&IF &INDEX EQ 0 &SKIP -3
&GLOBAL0 = &1
EXEC ETEPTR &MODEL
&CONTINUE
&PRINT IF THROUGH WITH ETE OUTPUT
&PRINT ENTER : YES OR NO
&READ ARGS
&IF &INDEX EQ 0 &SKIP -3
&IF &1 EQ YES &GOTO -TERM
&IF &1 EQ Y &GOTO -TERM
&GOTO -LAB3
-TERM &PRINT TO RUN OR RERUN ETE
&PRINT ENTER : YES ELSE
&PRINT ENTER : EXIT
&READ ARGS
&IF &INDEX EQ 0 &SKIP -4
&IF &1 EQ YES &GOTO -LAB0
&1
&GOTO -LAB3

```

ETEPTX EXEC
VP/CSS

```
&TYPE OFF
STATE &I LISTING
&IF &INDEX0 EQ 1 &GOTO -ERR
&IF &GLOBAL0 EQ 1 &GOTO -PTR1
&IF &GLOBAL0 EQ 2 &GOTO -PTR2
&IF &GLOBAL0 EQ 3 &GOTO -PTR3
&IF &GLOBAL0 EQ 4 &GOTO -PTR4
&IF &GLOBAL0 EQ 5 &GOTO -PTR5
-PTR1 &BEGSTACK
BRIEF
B
UP /STUDENT STATISTICS/
VERIFY 120
PUT /INSTRUCTOR STATISTICS/
CSS PRINTF (((()))) LISTING
QUIT
&ENDSTACK
&GOTO -COMM
-PTR2 &BEGSTACK
BRIEF
B
UP /INSTRUCTOR STATISTICS/
VERIFY 120
PUT /MODULE UTILIZATION/
CSS PRINTF (((()))) LISTING
QUIT
&ENDSTACK
&GOTO -COMM
-PTR3 &BEGSTACK
BRIEF
B
UP /MODULE UTILIZATION/
VERIFY 120
PUT /OTHER FACILITIES/
CSS PRINTF (((()))) LISTING
QUIT
&ENDSTACK
&GOTO -COMM
-PTR4 &BEGSTACK
BRIEF
B
```

ETEPTR EXEC

```

UP /OTHER FACILITIES UTIL/
VERIFY 120
PUT /FINISH/
CSS PRINTF (((()))) LISTING
QUIT
&ENDSTACK
-COMM EDIT &1 LISTING
&EXIT
-PTR5 &BEGSTACK
BRIEF
B
UP /STUDENT STATISTICS/
VERIFY 120
PUT /FINISH/
CSS PRINTF (((()))) LISTING
QUIT
&ENDSTACK
&GOTO -COMM
-ERR &CONTINUE
&UPRINT ETE MODEL MUST BE EXECUTED
&UPRINT FIRST BY ENTERING RUN ETE
&RETURN
    
```


GPSS EXEC
VP/CSS

&TYPE OFF
&STACK N
&STACK N
&STACK N
&STACK NAME &1
&STACK OPTS B
&STACK RUN
&STACK QUIT
&STACK
ATTACH NGPSSV ALL BRIEF
SET ATTN OFF

TURK EXEC
VP/CSS

&TYPE OFF
&BEGSTACK
TOP
L / 1 FUNC/
R 1 FUNCTION P9,L7
D 1
C 1,3111
FILE FIRE GPSS
&ENDSTACK
EDIT FIRE GPSS
&EXIT

HAL EXEC
VP/CSS

&TYPE OFF
FILEDEF 3 DSK TURK EXEC DISP NEW
RUN MAD
EXEC TURK
&EXIT

HAL3 EXEC
VP/CSS

&TYPE OFF
FILEDEF 3 DSK TURK EXEC DISP NEW
FORTRAN PROF
RUN PROF
&EXIT

HAL4 EXEC
VP/CSS

&TYPE OFF
FILEDEF 3 DSK TURK EXEC DISP NEW
RUN PROF
EXEC TURK
&EXIT

TABLE III-2 (CONTINUED)

MODEL GENERATION SUBSYSTEM

The Model Generation Subsystem consists of a single interactive FORTRAN program (PROF) which runs under control of the Executive Subsystem.

Figure III-5 is the Autoflow diagram of program PROF. However, some general statements concerning PROF will make the logic flow easier to understand.

The first READ statement in the program makes use of an NCSS program feature called stacking. When PROF is called by the ETE2 EXEC, the name of the model (and hence the name of the file where the newly generated GPSS program will be stored) is stacked in the terminal input stream via the calling sequence. Consequently, the first attempt to read logical unit 5 (the terminal) will cause the contents of the input stack to be read and no intervention on the part of the operator is required.

The GPSS function cards (see Figure III-6) generated by PROF constitute an $n \times m$ matrix where n is the number of learning modules to be simulated and m is the number of different resources which may be used in support of that module. PROF builds a similar matrix using the responses of the operator to supply values for the matrix elements. The matrix is called ITABL and is currently set at 30 X 7.

The seven columns of the matrix correspond to:

1. Table location of instructor group
2. Group size for group modules
3. Staff group number
4. Facility group number
5. Remedial module type code
6. Module type code
7. Instructor group size

In practice only that number of rows will be filled in the matrix equal to the number of learning modules in the system being simulated. Column 6 (module type code) is not part of the regular input. Its values are calculated from the other matrix elements. The module type code is a binary number that can be decoded, in the GPSS model, to determine the support requirements for the module in question.

If the column element for a particular resource is non-zero, the corresponding binary code number for that column is obtained from JTAB and added to column 6. In this way, the sum of all the individual codes for that module (row) is calculated and becomes the module type code.

Subroutine CHECK is used during the part of PROF where general model conditions, such as type of output data, are being set. Check reads each response under an "A" format, and tests the response for "YES", "NO" or "QUIT". If the response is not equal to one of these, a "NOT UNDERSTOOD" message is generated and the user is queried again.

A "YES" response causes the flag word sent in the calling sequence to be set equal to 1. A "NO" response causes the flag word to be set equal to 0. A "QUIT" response results in a call to EXIT.

The indicators set by Subroutine CHECK are:

- INSF - Instructor data wanted
- IFAC - Facilities data wanted
- IREM - Remedial material used
- ISTF - Staff personnel used
- IGRU - Group modules used.

These indicators serve a double purpose. They are used to determine if data concerning these variables is to be requested and they are used to determine if dummy functions are required. Because the GPSS model will not assemble unless all required functions are present, PROF writes out dummy functions for those variables which the user does not require.

CHART TITLE - PROCEDURES




FIGURE III-5

III-17 304

CHART TITLE - PROCEDURES




CHART TITLE - PROCEDURES




FIGURE III-5 (CONTINUED)

CHART TITLE - PROCEDURES




CHART TITLE - PROCEDURES




FIGURE III-5 (CONTINUED)

CHART TITLE - PROCEDURES




FIGURE III-5 (CONTINUED)

CHART TITLE - PROCEDURES




FIGURE III-5 (CONTINUED)

CHART TITLE - PROCEDURES




FIGURE III-5 (CONTINUED)

CHART TITLE - PROCEDURES





FIGURE III-5 (CONTINUED)

313 III-26

CHART TITLE - PROCEDURES



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -PROF- FLOWCHARTS

PAGE 13

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

500  FORMAT (' COURSE PROFILE DATA')
501  FORMAT (1X)
502  FORMAT ('PLEASE ANSWER THE FOLLOWING QUESTIONS: YES OR NO')
504  FORMAT ('WILL DATA BE NEEDED ON INSTRUCTOR UTILIZATION?')
506  FORMAT ('WILL DATA BE NEEDED ON FACILITIES UTILIZATION?')
508  FORMAT ('ARE SPECIAL REMEDIAL MODULES INCLUDED IN ANY COURSE?')
510  FORMAT ('DO ANY COURSES REQUIRE STAFF MEMBERS (NOT INSTRUCTORS)?')
512  FORMAT ('ARE ANY MODULES GROUP MODULES?')
514  FORMAT (199)
516  FORMAT (1A4)
518  FORMAT (1912)
520  FORMAT ('HOW MANY INSTRUCTOR GROUPS ARE THERE?')
522  FORMAT ('HOW MANY INSTRUCTORS IN EACH GROUP?')
524  FORMAT ('HOW MANY FACILITIES GROUPS ARE THERE?')
526  FORMAT ('GROUP',12,'?')
528  FORMAT ('HOW MANY UNITS IN EACH FACILITY GROUP?')
530  FORMAT ('MODULE DATA, ANSWER EACH QUESTION.')
532  FORMAT ('WHEN FINISHED, ENTER WORD STOP')
534  FORMAT ('INSTRUCTOR REQUIRED?')
536  FORMAT ('ENTER INSTRUCTOR GROUP NUMBER.')
538  FORMAT ('FACILITIES REQUIRED?')
540  FORMAT ('ENTER FACILITY NUMBER.')
542  FORMAT ('IS THIS A TEAM MODULE?')
544  FORMAT ('ENTER NUMBER OF TEAM MEMBERS.')
546  FORMAT ('IS STAFF REQUIRED?')
548  FORMAT ('HOW MANY STAFF GROUPS ARE THERE?')
550  FORMAT ('HOW MANY STAFF PERSONNEL IN EACH GROUP?')
552  FORMAT (10(11,'',11,''))
554  FORMAT ('L /# START')
556  FORMAT ('INPUT')
558  FORMAT ('BEGSTACK')
560  FORMAT ('PLEASE ENTER THE NAME OF YOUR NEW MODEL')
562  FORMAT ('FILE ',3A4,'GPSS')
564  FORMAT ('ENDSTACK')
566  FORMAT (3A4)
568  FORMAT ('EDIT DUMMY GPSS')
570  FORMAT (' INST FUNCTION  P2,D3')
572  FORMAT (' INSTN FUNCTION  P2,D3')
574  FORMAT (' FACT FUNCTION  P2,D3')
600  FORMAT ('HOW MANY COURSES ARE THERE?')
602  FORMAT ('WHAT PERCENT OF STUDENTS GO INTO EACH COURSE?')
604  FORMAT ('ENTER PERCENTAGE AS WHOLE NUMBER')
606  FORMAT ('COURSE',12,'?')
608  FORMAT (' STUDT FUNCTION  RN2,D',11)
610  FORMAT (' STUDT FUNCTION  RN2,D',12)
612  FORMAT (9(F4.2,'',11,''))
614  FORMAT (9(F4.2,'',12,''))

```

FIGURE III-5 (CONTINUED)

315 III-28

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -PROF- FLOWCHARTS

PAGE 14

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

616 FORMAT ('THE FOLLOWING DATA DESCRIBES THE INDIVIDUAL')
618 FORMAT ('COURSE MODULES')
620 FORMAT ('ALL ENTRIES SHOULD BE WHOLE NUMBERS')
621 FORMAT ('IF AN INPUT IS NOT NEEDED, ENTER A ZERO')
622 FORMAT ('MODULE NO. ',I2)
624 FORMAT ('ENTER TOTAL NUMBER OF MODULES')
626 FORMAT ('ENTER INSTRUCTOR GROUP NUMBER')
628 FORMAT ('IF GROUP MODULE, ENTER GROUP SIZE')
630 FORMAT ('IF STAFF REQUIRED, ENTER STAFF GROUP NUMBER')
632 FORMAT ('ENTER FACILITY GROUP NUMBER')
634 FORMAT ('ENTER NUMBER OF ASSOCIATED REMEDIAL MODULE')
636 FORMAT ('MODT FUNCTION P2,L',I2)
638 FORMAT (9(I1,'',I2,'')/(10(I2,'',I2,'')/1))
639 FORMAT (9(I2,'',I2,''))
640 FORMAT (10(I2,'',I2,''))
642 FORMAT (' ')
644 FORMAT ('U /* START/')
646 FORMAT ('C /% /% / 50 *')
647 FORMAT ('C /%L /%L / 50')
648 FORMAT (27199)
650 FORMAT ('NEXT, CURRICULUM DATA IS TO BE ENTERED')
652 FORMAT ('FIRST, THE NUMBER OF STEPS IN THE SPECIFIED CURRICULUM')
653 FORMAT ('IS ENTERED, THEN MODULE NUMBERS SEPARATED BY COMMAS')
654 FORMAT ('FOR EXAMPLE: 1,3,4,6,7,10 ETC. UNTIL THE COMPLETE')
656 FORMAT ('CURRICULUM HAS BEEN SPECIFIED')
658 FORMAT ('CURRICULUM NO.',I2)
660 FORMAT ('ENTER NUMBER OF STEPS IN THIS CURRICULUM')
661 FORMAT ('NOW ENTER THE CURRICULUM')
662 FORMAT ('1')
664 FORMAT (1X,I2,4X,'FUNCTION P9,L',I2)
666 FORMAT ('NEXT, ENTER ESTIMATED COMPLETION TIMES FOR EACH MODULE')
668 FORMAT ('ENTRY FORMAT IS THE SAME AS FOR CURRICULUM DATA')
670 FORMAT (' TIME FUNCTION P2,L',I2)
672 FORMAT (' TIME FUNCTION P2,L',I1)
674 FORMAT (' SPED FUNCTION P2,L',I2)
676 FORMAT (' SPED FUNCTION P2,L',I1)
678 FORMAT ('AFTER COMPLETION TIMES FOR ALL MODULES HAVE BEEN')
680 FORMAT ('ENTERED, EXPECTED VARIATION RANGE IN COMPLETION')
682 FORMAT ('TIMES ARE ENTERED IN THE SAME WAY. A VARIATION MUST')
684 FORMAT ('BE ENTERED EVEN IF IT IS A 0.')
686 FORMAT (1X,'STORAGE',4X,6('S',I2,'',I2,''))
687 FORMAT (1X,'STORAGE',4X,6('S',I1,'',I2,''))
688 FORMAT (' FACT FUNCTION P2,L',I2)
689 FORMAT (1X,'STORAGE',4X,6('S',I3,'',I2,''))
690 FORMAT (' TEAM FUNCTION P2,L3')
692 FORMAT (' REEM FUNCTION P2,L3')
694 FORMAT (' UNHL FUNCTION P2,L3')
696 FORMAT (' INSTT FUNCTION P2,L',I2)

```

FIGURE III-5 (CONTINUED)

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -PROF- FLOWCHARTS

PAGE 15

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

698      FORMAT (' INSTN FUNCTION  P2,L',I2)
700      FORMAT ('NOW ENTER THE NUMBER OF COPIES OF INSTRUCTION')
702      FORMAT ('MATTER AVAILABLE FOR EACH MODULE')
704      FORMAT ('ENTRY FORMAT IS THE SAME AS FOR FACILITIES DATA.')
706      FORMAT ('NOW ENTER COMPLETION VARIATION TIME FOR EACH MODULE.')
708      FORMAT ('SAME FORMAT AS COMPLETION TIMES.')
710      FORMAT (' AOB  VARIABLE  K',I3)
712      FORMAT (' AOB  VARIABLE  K',I2)
714      FORMAT ('ENTER SCHOOL CAPACITY (AOB)')
716      FORMAT (' MODR  FUNCTION  P2,L',I2)
718      FORMAT ('C +/- ++ 50')
720      FORMAT (' UNSHL FUNCTION  P2,L',I2)
722      FORMAT (' UNSHL FUNCTION  P2,L',I2)
724      FORMAT ('C +/- ++ 50')
726      FORMAT (' TEAM  FUNCTION  P2,L',I2)
728      FORMAT ('DOES THIS MODULE HAVE AN ASSOCIATED REMEDIAL MODULE? (YES
/NO)')
730      FORMAT ('DOES THE REMEDIAL MODULE REQUIRE AN INSTRUCTOR? YES/NO')
732      FORMAT ('DOES THE REMEDIAL MODULE REQUIRE FACILITIES? (YES/NO)')
734      FORMAT (' MODR  FUNCTION  P2,L',I2)

      DIMENSION NSTRG(200),NSPRO(30),MCPY(30)
      DIMENSION INGRU(20),TITL(3),INLOC(20),NPGRU(20),LFGRU(20)
      DIMENSION JTAB(5),NSTEP(30)
      DATA YES/'YES'/,XNO/'NO'/,QUIT/'QUIT'/
      DATA JTAB/1,2,4,8,16/

      DIMENSION NPERC(30),FPERC(30),ITABL(30,7),ICUR(15,30),NTYM(30)
      DATA ITABL/210*0/,ICUR/450*99/
    
```

FIGURE III-5 (CONTINUED)

PAGE 16

/ CHECK /

03.20*-->*

THIS SUBROUTINE READS
ANSWERS TO QUESTIONS
AND
SETS FLAGS FOR MODULE
PROFILE SO USER
DOESN'T
HAVE TO ANSWER
REDUNDANT QUESTIONS.




FIGURE III-5 (CONTINUED) 318
III-31

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -PROF- FLOWCHARTS

PAGE 17

CHART TITLE - NON-PROCEDURAL STATEMENTS

```
516/  FORMAT (A4)
518    FORMAT ('INPUT NOT UNDERSTOOD, TRY AGAIN.')
522    FORMAT ('FILE')
520    FORMAT('DO YOU WISH TO SAVE THIS CONFIGURATION? ENTER YES OR NO')
      DATA YES/'YES'//,XNO/'NO'//,QUIT/'QUIT'//
```

FIGURE III-5 (CONTINUED)

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-PROF- FLOWCHARTS

FORTRAN MODULE

(LIST,NAMSQ,SOURCEQ)

CARD NO	CONTENTS	****
1	500 FORMAT (1* COURSE PROFILE DATA*)	00000100
2	501 FORMAT (1X)	00000200
3	502 FORMAT (1* PLEASE ANSWER THE FOLLOWING QUESTIONS: YES OR NO*)	00000300
4	504 FORMAT (1* WILL DATA BE NEEDED ON INSTRUCTOR UTILIZATION?*)	00000400
5	506 FORMAT (1* WILL DATA BE NEEDED ON FACILITIES UTILIZATION?*)	00000500
6	508 FORMAT (1* ARE SPECIAL REMEDIAL MODULES INCLUDED IN ANY COURSE?*)	00000600
7	510 FORMAT (1* DO ANY COURSES REQUIRE STAFF MEMBERS (NOT INSTRUCTORS)?*)	00000700
8	512 FORMAT (1* ARE ANY MODULES GROUP MODULES?*)	00000800
9	514 FORMAT (199)	00000900
10	516 FORMAT (1A4)	00001000
11	518 FORMAT (1S12)	00001100
12	520 FORMAT (1* HOW MANY INSTRUCTOR GROUPS ARE THERE?*)	00001200
13	522 FORMAT (1* HOW MANY INSTRUCTORS IN EACH GROUP?*)	00001300
14	524 FORMAT (1* HOW MANY FACILITIES GROUPS ARE THERE?*)	00001400
15	526 FORMAT (1* GROUP*,12,*)	00001500
16	528 FORMAT (1* HOW MANY UNITS IN EACH FACILITY GROUP?*)	00001600
17	530 FORMAT (1* MODULE DATA, ANSWER EACH QUESTION.*)	00001700
18	532 FORMAT (1* WHEN FINISHED, ENTER WORD STOP*)	00001800
19	534 FORMAT (1* INSTRUCTOR REQUIRED?*)	00001900
20	536 FORMAT (1* ENTER INSTRUCTOR GROUP NUMBER.*)	00002000
21	538 FORMAT (1* FACILITIES REQUIRED?*)	00002100
22	540 FORMAT (1* ENTER FACILITY NUMBER.*)	00002200
23	542 FORMAT (1* IS THIS A TEAM MODULE?*)	00002300
24	544 FORMAT (1* ENTER NUMBER OF TEAM MEMBERS.*)	00002400
25	546 FORMAT (1* IS STAFF REQUIRED?*)	00002500
26	548 FORMAT (1* HOW MANY STAFF GROUPS ARE THERE?*)	00002600
27	550 FORMAT (1* HOW MANY STAFF PERSONNEL IN EACH GROUP?*)	00002700
28	552 FORMAT (10111,*,*,11,*/*)	00002800
29	554 FORMAT (1* /# START/*)	00002900
30	556 FORMAT (1* INPUT*)	00003000
31	558 FORMAT (1* DEBSTACK*)	00003100
32	560 FORMAT (1* PLEASE ENTER THE NAME OF YOUR NEW MODEL*)	00003200
33	562 FORMAT (1* FILE *,3A*,GPSS*)	00003300
34	564 FORMAT (1* ENDSTACK*)	00003400
35	565 FORMAT (3A4)	00003500
36	566 FORMAT (1* EDIT DUMMY GPSS*)	00003600
37	568 FORMAT (1* INST FUNCTION P2,D3*)	00003700
38	570 FORMAT (1* 1,2/2,3/3,4*)	00003800
39	572 FORMAT (1* INSTN FUNCTION P2,D3*)	00003900
40	574 FORMAT (1* FACT FUNCTION P2,D3*)	00004000
41	600 FORMAT (1* HOW MANY COURSES ARE THERE?*)	00004100
42	602 FORMAT (1* WHAT PERCENT OF STUDENTS GO INTO EACH COURSE?*)	00004200
43	604 FORMAT (1* ENTER PERCENTAGE AS WHOLE NUMBER*)	00004300
44	606 FORMAT (1* COURSE*,12,*)	00004400
45	608 FORMAT (1* STUDT FUNCTION AN2,D*,11)	00004500
46	610 FORMAT (1* STUDT FUNCTION AN2,D*,12)	00004600
47	612 FORMAT (91FA,2,*,*,11,*/*)	00004700
48	614 FORMAT (91FA,2,*,*,12,*/*)	00004800
49	616 FORMAT (1* THE FOLLOWING DATA DESCRIBES THE INDIVIDUAL*)	00004900
50	618 FORMAT (1* COURSE MODULES*)	00005000
51	620 FORMAT (1* ALL ENTRIES SHOULD BE WHOLE NUMBERS*)	00005100
52	621 FORMAT (1* IF AN INPUT IS NOT NEEDED, ENTER A ZERO*)	00005200
53	622 FORMAT (1* MODULE NO. *,12)	00005300
54	624 FORMAT (1* ENTER TOTAL NUMBER OF MODULES*)	00005400
55	626 FORMAT (1* ENTER INSTRUCTOR GROUP NUMBER*)	00005500
56	628 FORMAT (1* IF GROUP MODULE, ENTER GROUP SIZE*)	00005600
57	630 FORMAT (1* IF STAFF REQUIRED, ENTER STAFF GROUP NUMBER*)	00005700
58	632 FORMAT (1* ENTER FACILITY GROUP NUMBER*)	00005800
59	634 FORMAT (1* ENTER NUMBER OF ASSOCIATED REMEDIAL MODULES*)	00005900
60	636 FORMAT (1* MODT FUNCTION P2,L*,12)	00006000
61	638 FORMAT (9111,*,*,12,*/*/110112,*,*,12,*/*/11)	00006100
62	639 FORMAT (91,*,*,12,*/*)	00006200
63	640 FORMAT (10112,*,*,12,*/*)	00006300
64	C THESE TWO FORMATS SHOULD HANDLE ALL 'L' TYPE FUNCTIONS	00006400
65	642 FORMAT (1* *)	00006500
66	644 FORMAT (1* /# START/*)	00006600
67	646 FORMAT (1* /# /# 50 *)	00006700
68	647 FORMAT (1* /# /# 50*)	00006800
69	648 FORMAT (12199)	00006900
70	650 FORMAT (1* NEXT, CURRICULUM DATA IS TO BE ENTERED*)	00007000
71	652 FORMAT (1* FIRST, THE NUMBER OF STEPS IN THE SPECIFIED CURRICULUM*)	00007100
72	653 FORMAT (1* IS ENTERED, THEN MODULE NUMBERS SEPARATED BY COMMAS*)	00007200
73	654 FORMAT (1* FOR EXAMPLE: 1,3,4,6,7,10 ETC. UNTIL THE COMPLETE*)	00007300
74	656 FORMAT (1* CURRICULUM HAS BEEN SPECIFIED*)	00007400
75	658 FORMAT (1* CURRICULUM NO. *,12)	00007500
76	660 FORMAT (1* ENTER NUMBER OF STEPS IN THIS CURRICULUM*)	00007600
77	661 FORMAT (1* NOW ENTER THE CURRICULUM*)	00007700
78	662 FORMAT (1*)	00007800
79	664 FORMAT (1X,12,4X,FUNCTION P9,L*,12)	00007900
80	666 FORMAT (1* NEXT, ENTER ESTIMATED COMPLETION TIMES FOR EACH MODULE*)	00008000
81	668 FORMAT (1* ENTRY FORMAT IS THE SAME AS FOR CURRICULUM DATA*)	00008100
82	670 FORMAT (1* TYPE FUNCTION P2,L*,12)	00008200
83	672 FORMAT (1* TYPE FUNCTION P2,L*,11)	00008300
84	674 FORMAT (1* SPND FUNCTION P2,L*,12)	00008400
85	676 FORMAT (1* SPND FUNCTION P2,L*,11)	00008500
86	678 FORMAT (1* AFTER COMPLETION TIMES FOR ALL MODULES HAVE BEEN*)	00008600
87	680 FORMAT (1* ENTERED, EXPECTED VARIATION RANGE IN COMPLETION*)	00008700
88	682 FORMAT (1* TIMES ARE ENTERED IN THE SAME WAY, A VARIATION MUST*)	00008800
89	684 FORMAT (1* BE ENTERED EVEN IF IT IS A 0.*)	00008900
90	686 FORMAT (1X,STORAGE*,4X,61'S*,12,*,*,12,*/*)	00009000
91	687 FORMAT (1X,STORAGE*,4X,61'S*,11,*,*,12,*/*)	00009100
92	688 FORMAT (1* FACT FUNCTION P2,L*,12)	00009200
93	689 FORMAT (1X,STORAGE*,4X,61'S*,13,*,*,12,*/*)	00009300
94	690 FORMAT (1* TEAM FUNCTION P2,L3*)	00009400
95	692 FORMAT (1* REHM FUNCTION P2,L3*)	00009500
96	694 FORMAT (1* UNSHL FUNCTION P2,L3*)	00009600
97	696 FORMAT (1* INST FUNCTION P2,L*,12)	00009700
98	698 FORMAT (1* INSTN FUNCTION P2,L*,12)	00009800
99	700 FORMAT (1* NOW ENTER THE NUMBER OF COPIES OF INSTRUCTIONAL*)	00009900
100	702 FORMAT (1* MATTER AVAILABLE FOR EACH MODULE*)	00010000
101	704 FORMAT (1* ENTRY FORMAT IS THE SAME AS FOR FACILITIES DATA*)	00010100
102	706 FORMAT (1* NOW ENTER COMPLETION VARIATION TIME FOR EACH MODULE*)	00010200
103	708 FORMAT (1* SAME FORMAT AS COMPLETION TIMES*)	00010300
104	710 FORMAT (1* AOB VARIABLE N*,13)	00010400
105	712 FORMAT (1* AOB VARIABLE N*,12)	00010500
106	714 FORMAT (1* ENTER SCHOOL CAPACITY (AOB)*)	00010600
107	716 FORMAT (1* MODR FUNCTION P2,L3*)	00010700
108	718 FORMAT (1* C +/S + 50*)	00010800
109	720 FORMAT (1* UNSHL FUNCTION P2,L*,12)	00010900

TABLE III-3

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-PROF- FLOWCHARTS

CARD NO	*****	CONTENTS	*****
110	722	FORMAT (' UNSHL FUNCTION P2,L3')	00011000
111	724	FORMAT ('C * / * 50')	00011100
112	726	FORMAT (' TEAM FUNCTION P2,L*,12)	00011200
113	728	FORMAT (' DOES THIS MODULE HAVE AN ASSOCIATED REMEDIAL MODULE? (YES/NO)')	00011300
114	1/(NO)')		00011400
115	730	FORMAT (' DOES THE REMEDIAL MODULE REQUIRE AN INSTRUCTOR? YES/NO')	00011500
116	732	FORMAT (' DOES THE REMEDIAL MODULE REQUIRE FACILITIES? (YES/NO)')	00011600
117	734	FORMAT (' MODR FUNCTION P2,L*,12)	00011700
118		DIMENSION NSTRG(200),NSPRD(30),NCPY(30)	00011800
119		DIMENSION INGRU(20),ITZL(13),INLOC(20),NFGRU(20),LFGRU(20)	00011900
120		DIMENSION JTAB(15),NSTEP(30)	00012000
121		DATA YES/'YES'/.AND/'NO'/.QUIT/'QUIT'/.	00012100
122		DATA JTAB/1,2,*,*,18/	00012200
123		DIMENSION NPERC(30),FPERC(30),ITABL(30,7),ICUR(15,30),NTVM(30)	00012300
124		DATA ITABL/210*0/,ICUR/450*99/	00012400
125		C THIS PROGRAM CALLED PROF READS ILS CONFIGURATION DATA IN TUTORIAL	00012500
126		C MODE. IT SETS UP APPROPRIATE FUNCTIONS AND INSERTS THEM IN ETE MODEL.	00012600
127		READ (5,56)ITITL	00012700
128		WRITE (3,558)	00012800
129		C INITIALIZE TURK EXEC FOR EDITING DUMMY MODEL	00012900
130		WRITE (3,554)	00013000
131		WRITE (3,554)	00013100
132		C POSITION EDITOR AT * START CARD	00013200
133		C AND PUT INTO INPUT MODE	00013300
134		WRITE (6,501)	00013400
135		WRITE (6,500)	00013500
136		WRITE (6,600)	00013600
137		READ (5,514)NCORS	00013700
138		WRITE (6,714)	00013800
139		READ (5,514)NAOB	00013900
140		IF (NAOB.GT.99) GOTO 83	00014000
141		WRITE (3,712)NAOB	00014100
142		GOTO 86	00014200
143	83	WRITE (3,710)NAOB	00014300
144	86	WRITE (6,602)	00014400
145		WRITE (6,604)	00014500
146		C SET UP DISTRIBUTION FUNCTION	00014600
147		DO 88 I = 1,NCORS	00014700
148		WRITE (6,608)	00014800
149		READ (5,514)NPERC(I)	00014900
150		FPERC(I) = NPERC(I)	00015000
151	88	FPERC(I) = FPERC(I)/100.	00015100
152		DO 93 I = 2,NCORS	00015200
153	93	FPERC(I) = FPERC(I) + FPERC(I-1)	00015300
154		IF (NCORS.GE.10) GOTO 89	00015400
155		WRITE (3,608)NCORS	00015500
156		WRITE (3,612)(FPERC(I),I,I=1,NCORS)	00015600
157		GOTO 90	00015700
158	89	WRITE (3,610)NCORS	00015800
159	91	WRITE (3,612)(FPERC(I),I,I=1,9)	00015900
160		WRITE (3,614)(FPERC(I),I,I=10,NCORS)	00016000
161	90	CONTINUE	00016100
162		WRITE (6,501)	00016200
163		WRITE (6,502)	00016300
164		WRITE (6,504)	00016400
165	100	CALL CHECK(IINSF)	00016500
166		CALL CHECK(IISF)	00016600
167	102	CALL CHECK(IIFAC)	00016700
168		WRITE (6,508)	00016800
169		CALL CHECK(IIREN)	00016900
170		WRITE (6,510)	00017000
171		CALL CHECK(IISTF)	00017100
172		WRITE (6,512)	00017200
173		CALL CHECK(IIGRU)	00017300
174		IF (IINSF.EQ.0) GOTO 110	00017400
175		WRITE (6,662)	00017500
176		WRITE (6,520)	00017600
177		READ (5,514)NIG	00017700
178		WRITE (6,522)	00017800
179		DO 105 I = 1,NIG	00017900
180		WRITE (6,526)	00018000
181		READ (5,514)INGRU(I)	00018100
182	105	CONTINUE	00018200
183		C SET UP TABLE OF INSTRUCTOR GROUP START LOCATIONS	00018300
184		INLOC(1) = 50	00018400
185		DO 112 I = 2,NIG	00018500
186	112	INLOC(I) = INLOC(I-1)-INGRU(I-1)	00018600
187		GOTO 115	00018700
188	110	WRITE (3,568)	00018800
189		C WHEN NO INSTRUCTOR CALLED FOR WRITE OUT DUMMY FUNCTIONS	00018900
190		WRITE (3,570)	00019000
191		WRITE (3,572)	00019100
192		WRITE (3,570)	00019200
193	115	IF (IFAC.EQ.0) GOTO 120	00019300
194		WRITE (6,662)	00019400
195		WRITE (6,524)	00019500
196		READ (5,514)NFAG	00019600
197		WRITE (6,528)	00019700
198		DO 117 I = 1,NFAG	00019800
199		WRITE (6,526)	00019900
200		C A SINGLE TABLE CALLED NSTRG TAKES CARE OF:	00020000
201		C MODULES, FACILITIES AND STAFF.	00020100
202	117	READ (5,514)NSTRG(I+50)	00020200
203		KUKU = NFAG + 50	00020300
204		WRITE (3,686)(J,NSTRG(I),J = 91,KUKU)	00020400
205		GOTO 125	00020500
206	120	WRITE (3,574)	00020600
207		C INSERT DUMMY FACILITIES FUNCTIONS	00020700
208		WRITE (3,570)	00020800
209	125	IF (IISTF.EQ.0) GOTO 171	00020900
210		WRITE (6,548)	00021000
211		READ (5,514)NSGR	00021100
212		WRITE (6,550)	00021200
213		DO 214 I = 1,NSGR	00021300
214		WRITE (6,526)	00021400
215	214	READ (5,514)INSTRG(I+100)	00021500
216		JA = NSGR + 100	00021600
217		WRITE (3,689)(J,NSTRG(I),J = 101,JA)	00021700
218		GOTO 173	00021800
219	171	WRITE (3,722)	00021900
220		WRITE (3,570)	00022000
221		GOTO 173	00022100

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-PROF- FLOWCHARTS

CARD NO	*****	CONTENTS	*****
222	173	WRITE (6,616)	00022200
223	C	PREPARE USER FOR MODULE DATA ENTRY	00022300
224		WRITE (6,618)	00022400
225		WRITE (6,620)	00022500
226		WRITE (6,621)	00022600
227		WRITE (6,624)	00022700
228		READ (5,514)NTOT	00022800
229		DO 130 I = 1,NTOT	00022900
230		WRITE (6,622)I	00023000
231		IF (I*NSP.EQ.0) GOTO 135	00023100
232		WRITE (6,626)	00023200
233		READ (5,514)ITABL(1,1)	00023300
234		IF (ITABL(1,1).EQ.0) GOTO 135	00023400
235		RGB = ITABL(1,1)	00023500
236		ITABL(1,1) = INLOC(KGB)	00023600
237		ITABL(1,7) = INGRU(KGB)	00023700
238	135	IF (IGRU.EQ.0) GOTO 136	00023800
239		WRITE (6,628)	00023900
240		READ (5,514)ITABL(1,2)	00024000
241	136	IF (ISTF.EQ.0)GOTO 137	00024100
242		WRITE (6,630)	00024200
243		READ (5,514)ITABL(1,3)	00024300
244	137	IF (IPAC.EQ.0) GOTO 138	00024400
245		WRITE (6,632)	00024500
246		READ (5,514)ITABL(1,4)	00024600
247	138	IF (IREM.EQ.0)GOTO 130	00024700
248	133	WRITE (6,728)	00024800
249		READ (5,516)ANS	00024900
250		IF (ANS.EQ.XNO) GOTO 130	00025000
251		IF (ANS.NE.YES) GOTO 133	00025100
252	1331	WRITE (6,730)	00025200
253		READ (5,516)ANS	00025300
254		IF (ANS.EQ.XNO) GOTO 1332	00025400
255		IF (ANS.NE.YES) GOTO 1331	00025500
256		ITABL(1,5) = 1	00025600
257	1332	WRITE (6,732)	00025700
258		READ (5,516)ANS	00025800
259		IF (ANS.EQ.XNO) GOTO 130	00025900
260		IF (ANS.NE.YES) GOTO 1332	00026000
261		ITABL(1,5) = ITABL(1,5)+8	00026100
262	130	CONTINUE	00026200
263		DO 131 I = 1,NTOT	00026300
264	131	ITABL(1,6) = 0	00026400
265		DO 145 J = 1,5	00026500
266		DO 145 I = 1,NTOT	00026600
267		IF (ITABL(I,J).EQ.0) GOTO 145	00026700
268		ITABL(I,6) = ITABL(I,6) + JTAB(J)	00026800
269	145	CONTINUE	00026900
270	C	TABLE OF MODULE TYPES HAS NOW BEEN SET UP.	00027000
271		WRITE (3,636)NTOT	00027100
272		WRITE (3,638)I,ITABL(1,6),I = 1,NTOT)	00027200
273	C	FROM NOW ON 141 WILL BE THE CLOSE OUT SECTION	00027300
274		WRITE (3,640)NTOT	00027400
275		WRITE (3,638)I,ITABL(1,4),I = 1,NTOT)	00027500
276	C	TABLE OF FACILITY LOCATIONS HAS BEEN SET UP	00027600
277	199	IF (I*NSP.EQ.0) GOTO 193	00027700
278		WRITE (3,646)NTOT	00027800
279		WRITE (3,638)I,ITABL(1,1),I = 1,NTOT)	00027900
280	193	IF (IPAC.EQ.0) GOTO 194	00028000
281		WRITE (3,648)NTOT	00028100
282		WRITE (3,638)I,ITABL(1,7),I = 1,NTOT)	00028200
283	194	IF (ISTF.EQ.0) GOTO 1711	00028300
284		WRITE (3,720)NTOT	00028400
285		WRITE (3,638)I,ITABL(1,3),I = 1,NTOT)	00028500
286	1711	IF (IGRU.EQ.0) GOTO 1733	00028600
287		WRITE (3,726) NTOT	00028700
288		WRITE (3,638)I,ITABL(1,2),I = 1,NTOT)	00028800
289	1733	IF (IREM.EQ.0) GOTO 17	00028900
290		WRITE (3,734)NTOT	00029000
291		WRITE (3,638)I,ITABL(1,5),I = 1,NTOT)	00029100
292	177	WRITE (6,662)	00029200
293		WRITE (6,650)	00029300
294		WRITE (6,652)	00029400
295		WRITE (6,653)	00029500
296		WRITE (6,654)	00029600
297		WRITE (6,656)	00029700
298		DO 158 I = 1,NCORS	00029800
299		WRITE (6,658)I	00029900
300		WRITE (6,660)	00030000
301		READ (5,514)NSTEP (1)	00030100
302		WRITE (6,661)	00030200
303	C	WHEN CURRICULUM IS READ IT WILL GO INTO AN ARRAY	00030300
304	C	PREVIOUSLY SET TO ALL 99'S. THIS WAY WE CAN COUNT THE NUMBER	00030400
305	C	OF ITEMS IN EACH RECORD AND ACT ACCORDINGLY.	00030500
306		KUR = NSTEP(1)	00030600
307		READ (5,648)(ICUR(I,J),J = 1,KUR)	00030700
308	193	DO 197 J = 1,KUR	00030800
309		IF (ICUR(I,J).EQ.0) GOTO 198	00030900
310	197	CONTINUE	00031000
311		GOTO 159	00031100
312	198	NN = J	00031200
313		READ (5,648)(ICUR(I,J),J = NN,KUR)	00031300
314	159	KK = KUR + 1	00031400
315	158	ICUR(I,KK) = 50	00031500
316	C	SET LAST STEP TO A 50 FOR FLAG	00031600
317		DO 163 I = 1,NCORS	00031700
318		KU = NSTEP(1) + 1	00031800
319		WRITE (3,664)I , KU	00031900
320	167	WRITE (3,639)(ICUR(I,J),J=1,KU)	00032000
321	163	CONTINUE	00032100
322	C	CURRICULA HAVE NOW BEEN	00032200
323	C	WRITTEN OUT. NEXT, READ AND COMPILE COMPLETION TIMES AND SPREADS	00032300
324		WRITE (6,662)	00032400
325		WRITE (6,664)	00032500
326		WRITE (6,666)	00032600
327		READ (5,648)(NTYM(I), I=1,NTOT)	00032700
328	212	IF (INTOT.LE.9) GOTO 213	00032800
329		WRITE (3,670)NTOT	00032900
330		GOTO 219	00033000
331	C	READY TO WRITE OUT TIMES	00033100
332	213	WRITE (3,672)NTOT	00033200
333	219	WRITE (3,638)I,NTYM(I),I = 1,NTOT)	00033300

322

TABLE III-3 (CONTINUED)

III-35

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-PROF- FLOWCHARTS

CARD NO	****	CONTENTS	****
334		WRITE (6,706)	00033400
335		WRITE (6,708)	00033500
336		READ (5,648) (NSPRD (I), I = 1, NTOT)	00033600
337		WRITE (3,674) (NTOT)	00033700
338		WRITE (3,638) (I, NSPRD (I), I = 1, NTOT)	00033800
339		C COMPLETION SPREADS HAVE BEEN WRITTEN OUT.	00033900
340		WRITE (6,700)	00034000
341		WRITE (6,702)	00034100
342		WRITE (6,704)	00034200
343		READ (5,648) (NCPY (I), I = 1, NTOT)	00034300
344		IF (INTOT.GT.9) GOTO 342	00034400
345		WRITE (3,687) (I, NCPY (I), I = 1, NTOT)	00034500
346		GOTO 343	00034600
347		342 WRITE (3,686) (I, NCPY (I), I = 1, NTOT)	00034700
348		343 CONTINUE	00034800
349		C STORAGES FOR MODULES HAVE BEEN SET UP.	00034900
350		C NEXT, WRITE OUT DUMMY FUNCTIONS FOR COMPLETENESS	00035000
351		IF (IGAU.NE.0) GOTO 181	00035100
352		WRITE (3,690)	00035200
353		WRITE (3,570)	00035300
354		181 IF (IREH.NE.0) GOTO 182	00035400
355		WRITE (3,692)	00035500
356		WRITE (3,570)	00035600
357		WRITE (3,716)	00035700
358		WRITE (3,570)	00035800
359		182 IF (ISTF.NE.0) GOTO 141	00035900
360		WRITE (3,694)	00036000
361		WRITE (3,570)	00036100
362		141 WRITE (3,642)	00036200
363		WRITE (3,644)	00036300
364		WRITE (3,646)	00036400
365		WRITE (3,644)	00036500
366		WRITE (3,647)	00036600
367		WRITE (3,644)	00036700
368		WRITE (3,718)	00036800
369		WRITE (3,644)	00036900
370		WRITE (3,724)	00037000
371		WRITE (3,562) (ITITL (I), I = 1, 3)	00037100
372		WRITE (3,564)	00037200
373		WRITE (3,566)	00037300
374		CALL EXIT	00037400
375		END	00037500
376		SUBROUTINE CHECK (ITM)	00037600
377		C THIS SUBROUTINE READS ANSWERS TO QUESTIONS AND	00037700
378		C SETS FLAGS FOR MODULE PROFILE SO USER DOESN'T	00037800
379		C HAVE TO ANSWER REDUNDANT QUESTIONS.	00037900
380		516 FORMAT (A4)	00038000
381		518 FORMAT ('INPUT NOT UNDERSTOOD, TRY AGAIN.')	00038100
382		522 FORMAT ('FILE')	00038200
383		520 FORMAT ('DO YOU WISH TO SAVE THIS CONFIGURATION? ENTER YES OR NO')	00038300
384		DATA YES/'YES',XND/'NO',QUIT/'QUIT'/	00038400
385		21 READ (5,516) ARG1	00038500
386		ITM = 99	00038600
387		IF (ARG1.EQ.YES) ITM = 1	00038700
388		IF (ARG1.EQ.XND) ITM = 0	00038800
389		IF (ARG1.EQ.QUIT) GOTO 20	00038900
390		IF (ITM.EQ.99) GOTO 15	00039000
391		13 RETURN	00039100
392		15 WRITE (6,518)	00039200
393		GOTO 21	00039300
394		20 WRITE (6,520)	00039400
395		38 READ (5,518) ARG2	00039500
396		IF (ARG2.EQ.YES) GOTO 33	00039600
397		IF (ARG2.EQ.XND) CALL EXIT	00039700
398		35 WRITE (6,518)	00039800
399		GOTO 38	00039900
400		33 WRITE (3,522)	00040000
401		GOTO 35	00040100
402		END	00040200

TABLE III-3 (CONTINUED)

TAEG REPORT NO. 29

INPUT CARD SPECIFICATIONS

[illegible]

FIGURE III-6

MODEL UPDATE

Types of Update. There are two basic types of updates: when a new source card is generated to replace an existing source card and when an Edit Change command is generated to act upon an existing source statement.

MODEL UPDATE SUBSYSTEM. Once an executable GPSS model has been generated via the Model Generation Subsystem, the user may desire to vary some of the model parameters to obtain simulation runs for different ILS configurations. The Model Update Subsystem provides a means for making changes to an existing model without requiring all the steps needed to generate a model from scratch.

This subsystem consists of a main element: the FORTRAN program called MAD that interrogates the user as to changes required, the control executive (ETE2), a dummy executive (TURK) and the NCSS Edit Program. Figure III-7 is the Autoflow diagram for the update subsystem. MAD uses the model name, supplied by ETE2, to locate the appropriate GPSS source file for update. Initially, the program displays a menu of eight possible changes and branches to the correct program section based on the user response via a computed GOTO statement.

The most complex update activity is curriculum update. This is because module insertion or deletion requires a change in the length of the curriculum itself. Each curriculum is made up of a function designator card which specifies the curriculum number and length, and some number of follower cards (see Figure III-6).

Insertion or deletion requires that the appropriate function designator card be located and the length designation increased or decreased by one. A replacement card is then generated with the correct length designation field.

Insertion, replacement or deletion is done by generating a CSS Edit Change command. Since this command permits specification of the number of lines to be scanned while attempting to make the specified change, it is necessary to count the cards following the function designator card. The number of function follower cards is then inserted in the change command and the command written into the stack of edit commands contained in TURK EXEC. A sample of a set of commands to delete a module from a curriculum is shown in Table III-4.

The edit commands listed in Table III-4 are representative of the procedures used for most update procedures and perform the following steps:

- a. Move the edit pointer to the top of the file.
- b. Locate (i.e. move the edit pointer) to function number 1.
Note that the location procedure assumes the GPSS statements are in fixed format, not free-form as is permitted under GPSS V.
- c. Replace the existing function definition statement with a new statement having a length designation field decremented by 1.
- d. Move the edit pointer to the next record.
- e. Remove the field: /,3 from the record indicated by the edit pointer.
- f. Replace the file FIRE GPSS with the updated file and return to CSS control.

Change card structure. MAD and PROF use different techniques for structuring change cards. GPSS does not permit embedded blanks in function follower cards (and the majority of initial inputs and changes are function follower cards) so both programs must structure these cards with no embedded blanks.

MAD avoids embedded blanks by testing all input field sizes (e.g. 9,99 etc) and by using an output FORMAT statement structured with no empty output columns.

PROF uses a limited number of different output FORMAT statements and produces function follower cards which may have 1 (but never more than 1) embedded blank per field. These blanks are later removed during the edit phase. PROF writes two sets of edit commands at the end of the stack. The function of these commands is to reposition the edit pointer at the beginning of the input section (at the * START card) and to search for character combinations containing embedded blanks (eg:, 3,) and remove the blank.

Because the length specification change is not incorporated into the model until after editing is finished, only one insertion or deletion can be made in a given curriculum, during a single execution of the update subsystem. For example, if two insertions are attempted in the same curriculum, during a single run the second insertion will be made, and a new length specification calculated, based on the length specification that existed at the start of the run and will produce an erroneous new length specification.

```


TOP
L / 2      FUNC/
R  2      FUNCTION   P9,L7
D 1
C !/,3!!!
FILE ETE      GPSS

```

SAMPLE EDIT COMMANDS

TABLE III-4

CHART TITLE - PROCEDURES




327

FIGURE III-7

III-40

CHART TITLE - PROCEDURES




328

FIGURE III-7 (CONTINUED)

III-41

CHART TITLE - PROCEDURES




329

FIGURE III-7 (CONTINUED)

III-42

CHART TITLE - PROCEDURES



330

FIGURE III-7 (CONTINUED)

III-43

CHART TITLE - PROCEDURES




CHART TITLE - PROCEDURES




FIGURE III-7 (CONTINUED)

CHART TITLE - PROCEDURES





CHART TITLE - PROCEDURES




334

FIGURE III-7 (CONTINUED)

III-47

CHART TITLE - PROCEDURES



335


FIGURE III-7 (CONTINUED)

III-48

CHART TITLE - PROCEDURES



CHART TITLE - PROCEDURES



337

FIGURE III-7 (CONTINUED)


III-50

```

    graph TD
      99[99] --> 01
      01[01] --> 02
      02[02] --> 03
      03[03] --> 04
      04[04] --> 05
      05[05] --> 06
      06[06] --> 07
      07[07] --> 08
      08[08] --> 09
      09[09] --> 10
      10[10] --> 11
      11[11] --> 12
      12[12] --> 13
      13[13] --> 14
      14[14] --> 15
      15[15] --> 16
      16[16] --> 17
      17[17] --> 18
      18[18] --> 19
      19[19] --> 20
      20[20] --> 21
      21[21] --> 22
      22[22] --> 23
      23[23] --> 24
      24[24] --> 25
      25[25] --> 26
      26[26] --> 27
      27[27] --> 28
      28[28] --> 29
      29[29] --> 30
      30[30] --> 31
      31[31] --> 32
      32[32] --> 33
      33[33] --> 34
      34[34] --> 35
      35[35] --> 36
      36[36] --> 37
      37[37] --> 38
      38[38] --> 39
      39[39] --> 40
      40[40] --> 41
      41[41] --> 42
      42[42] --> 43
      43[43] --> 44
      44[44] --> 45
      45[45] --> 46
      46[46] --> 47
      47[47] --> 48
      48[48] --> 49
      49[49] --> 50
      50[50] --> 51
      51[51] --> 52
      52[52] --> 53
      53[53] --> 54
      54[54] --> 55
      55[55] --> 56
      56[56] --> 57
      57[57] --> 58
      58[58] --> 59
      59[59] --> 60
      60[60] --> 61
      61[61] --> 62
      62[62] --> 63
      63[63] --> 64
      64[64] --> 65
      65[65] --> 66
      66[66] --> 67
      67[67] --> 68
      68[68] --> 69
      69[69] --> 70
      70[70] --> 71
      71[71] --> 72
      72[72] --> 73
      73[73] --> 74
      74[74] --> 75
      75[75] --> 76
      76[76] --> 77
      77[77] --> 78
      78[78] --> 79
      79[79] --> 80
      80[80] --> 81
      81[81] --> 82
      82[82] --> 83
      83[83] --> 84
      84[84] --> 85
      85[85] --> 86
      86[86] --> 87
      87[87] --> 88
      88[88] --> 89
      89[89] --> 90
      90[90] --> 91
      91[91] --> 92
      92[92] --> 93
      93[93] --> 94
      94[94] --> 95
      95[95] --> 96
      96[96] --> 97
      97[97] --> 98
      98[98] --> 99
      99[99] --> 100
      100[100] --> 101
      101[101] --> 102
      102[102] --> 103
      103[103] --> 104
      104[104] --> 105
      105[105] --> 106
      106[106] --> 107
      107[107] --> 108
      108[108] --> 109
      109[109] --> 110
      110[110] --> 111
      111[111] --> 112
      112[112] --> 113
      113[113] --> 114
      114[114] --> 115
      115[115] --> 116
      116[116] --> 117
      117[117] --> 118
      118[118] --> 119
      119[119] --> 120
      120[120] --> 121
      121[121] --> 122
      122[122] --> 123
      123[123] --> 124
      124[124] --> 125
      125[125] --> 126
      126[126] --> 127
      127[127] --> 128
      128[128] --> 129
      129[129] --> 130
      130[130] --> 131
      131[131] --> 132
      132[132] --> 133
      133[133] --> 134
      134[134] --> 135
      135[135] --> 136
      136[136] --> 137
      137[137] --> 138
      138[138] --> 139
      139[139] --> 140
      140[140] --> 141
      141[141] --> 142
      142[142] --> 143
      143[143] --> 144
      144[144] --> 145
      145[145] --> 146
      146[146] --> 147
      147[147] --> 148
      148[148] --> 149
      149[149] --> 150
      150[150] --> 151
      151[151] --> 152
      152[152] --> 153
      153[153] --> 154
      154[154] --> 155
      155[155] --> 156
      156[156] --> 157
      157[157] --> 158
      158[158] --> 159
      159[159] --> 160
      160[160] --> 161
      161[161] --> 162
      162[162] --> 163
      163[163] --> 164
      164[164] --> 165
      165[165] --> 166
      166[166] --> 167
      167[167] --> 168
      168[168] --> 169
      169[169] --> 170
      170[170] --> 171
      171[171] --> 172
      172[172] --> 173
      173[173] --> 174
      174[174] --> 175
      175[175] --> 176
      176[176] --> 177
      177[177] --> 178
      178[178] --> 179
      179[179] --> 180
      180[180] --> 181
      181[181] --> 182
      182[182] --> 183
      183[183] --> 184
      184[184] --> 185
      185[185] --> 186
      186[186] --> 187
      187[187] --> 188
      188[188] --> 189
      189[189] --> 190
      190[190] --> 191
      191[191] --> 192
      192[192] --> 193
      193[193] --> 194
      194[194] --> 195
      195[195] --> 196
      196[196] --> 197
      197[197] --> 198
      198[198] --> 199
      199[199] --> 200
      200[200] --> 201
      201[201] --> 202
      202[202] --> 203
      203[203] --> 204
      204[204] --> 205
      205[205] --> 206
      206[206] --> 207
      207[207] --> 208
      208[208] --> 209
      209[209] --> 210
      210[210] --> 211
      211[211] --> 212
      212[212] --> 213
      213[213] --> 214
      214[214] --> 215
      215[215] --> 216
      216[216] --> 217
      217[217] --> 218
      218[218] --> 219
      219[219] --> 220
      220[220] --> 221
      221[221] --> 222
      222[222] --> 223
      223[223] --> 224
      224[224] --> 225
      225[225] --> 226
      226[226] --> 227
      227[227] --> 228
      228[228] --> 229
      229[229] --> 230
      230[230] --> 231
```


III-51 338

CHART TITLE - PROCEDURES



339 FIGURE III-7 (CONTINUED)
III-52

CHART TITLE - PROCEDURES



340 FIGURE III-7 (CONTINUED)
III-53

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

900  FORMAT (5I2,A4)
956  FORMAT ('L /',A4,' PUNC/')
19   FORMAT ('ACTION NOT UNDERSTOOD')
257  FORMAT (1X,12,1X)
10   FORMAT ('SELECT PARAMETER TO BE CHANGED')
100  FORMAT (' 1 = CURRICULUM')
11   FORMAT ('2 = MODULE TYPE',/, '3 = MODULE COMPLETION TIMES')
12   FORMAT ('4 = NUMBER OF INSTRUCTORS',/, '5 = GROUP SIZES')
13   FORMAT ('6 = FACILITIES')
7    FORMAT ('7 = STUDENT INPUT RATE')
8    FORMAT ('8 = SCHOOL CAPACITY')
29   FORMAT (11)
14   FORMAT ('ENTER ACTION: INSERT, REPLACE, OR DELETE')
15   FORMAT (A4)
16   FORMAT ('ENTER CURRICULUM NO.')
17   FORMAT (199)
18   FORMAT ('NEW MODULE = ')
20   FORMAT ('FUNCTION CARD ERROR')
21   FORMAT ('ENTER MOD NO. TO BE REPLACED OR DELETED')
23   FORMAT (8A4)
22   FORMAT ('NEW MODULE TO BE INSERTED FOLLOWING')
27   FORMAT (22X,199)
253  FORMAT (199)
254  FORMAT('CANNOT LOCATE.')
252  FORMAT (12)
250  FORMAT (1X,12,1X)
251  FORMAT (A4)
549  FORMAT ('PRINT ')
550  FORMAT ('EDIT ',2A4,' GPSS')
551  FORMAT ('TOP')
552  FORMAT ('BEGSTACK')
553  FORMAT ('FILE',2A4,'GPSS')
554  FORMAT ('ENDSTACK')
555  FORMAT ('R ',A4,' FUNCTION P9,L',11)
655  FORMAT ('R ',A4,' FUNCTION P9,L',12)
557  FORMAT ('C /',',11,'/',',11,'/',',11,'/',',11)
558  FORMAT ('D ')
559  FORMAT ('C /',',11,'/',',11,'/',',11,'/',',11)
561  FORMAT ('C /',',11,'/',',11)
562  FORMAT ('FILE ',2A4,'GPSS')
563  FORMAT ('ENDSTACK')
564  FORMAT ('EXIT')
560  FORMAT ('&TYPE OFF')
565  FORMAT ('ANYMORE CHANGES?')
670  FORMAT ('MODULE TYPE CODE CHANGE.'/ENTER MODULE NUMBER')
671  FORMAT ('ENTER OLD TYPE CODE')
672  FORMAT ('ENTER NEW TYPE CODE')
673  FORMAT ('L /ROOT/')

```

FIGURE III-7 (CONTINUED)

III-54

341

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

674 FORMAT ('C /',11,'',11,'',11,'',11,'',11,'',11)
675 FORMAT ('C /',12,'',11,'',12,'',11,'',11,'',11)
676 FORMAT ('C /',11,'',12,'',11,'',11,'',11,'',11)
677 FORMAT ('C /',12,'',12,'',12,'',11,'',11,'',11)
678 FORMAT ('C /',11,'',11,'',11,'',12,'',12,'',11)
679 FORMAT ('C /',12,'',11,'',12,'',12,'',12,'',11)
680 FORMAT ('C /',11,'',12,'',11,'',12,'',12,'',11)
681 FORMAT ('C /',12,'',12,'',12,'',12,'',12,'',11)
685 FORMAT ('COMPLETION TIME CHANGE',/, 'ENTER MODULE NUMBER')
686 FORMAT ('ENTER OLD COMPLETION TIME')
687 FORMAT ('ENTER NEW COMPLETION TIME')
688 FORMAT ('L /TYPE P')
690 FORMAT ('CHANGE NUMBER OF INSTRUCTORS')
691 FORMAT ('ENTER INSTRUCTOR GROUP NUMBER')
692 FORMAT ('ENTER OLD GROUP SIZE')
693 FORMAT ('ENTER NEW GROUP SIZE')
694 FORMAT ('L /INSTN P')
695 FORMAT ('CHANGE STUDENT GROUP SIZE')
696 FORMAT ('ENTER GROUP NUMBER')
697 FORMAT ('ENTER OLD GROUP SIZE')
698 FORMAT ('ENTER NEW GROUP SIZE')
699 FORMAT ('L /TEAM P')
700 FORMAT ('CHANGE FACILITIES INVENTORY')
701 FORMAT ('ENTER FACILITY TYPE')
702 FORMAT ('ENTER CURRENT CAPACITY')
703 FORMAT ('ENTER NEW CAPACITY')
704 FORMAT ('L /STORAGE')
711 FORMAT ('R GENERATE ',11,'',11,'',20)
712 FORMAT ('R GENERATE ',12,'',11,'',20)
713 FORMAT ('R GENERATE ',12,'',12,'',20)
714 FORMAT ('CHANGE STUDENT INPUT RATE')
715 FORMAT ('NEW STUDENT EVERY ? CLOCK UNITS')
716 FORMAT ('ENTER NUMBER OF CLOCK UNITS OF VARIATION')
717 FORMAT ('L / GENERATE')
718 FORMAT ('VARIATION GREATER THAN MEAN - TRY AGAIN')
720 FORMAT ('CHANGE STUDENT CAPACITY')
721 FORMAT ('ENTER NEW CAPACITY')
722 FORMAT ('L /AOB VAR')
723 FORMAT ('R AOB VARIABLE K',12)
724 FORMAT ('R AOB VARIABLE K',13)
DATA TEAM/' TEA'/
DATA REPL/'REPL',,XINS/'INSE',,DELE/'DELE',,FUN/'UNCT'/
DATA EOP/'/' 'YES/'YES',,XMCOT/' MOD'/
DATA TIME/' TYR'/
DATA TNIN/' INS'/
DATA STO/'TORA'/
DIMENSION ARG (8),TITL(2)

```

FIGURE III-7 (CONTINUED)

CHART TITLE - PROCEDURES

//00033400//

1
1 01
• EXIT •

RETURN
BE SURE THAT ALL
STORAGE CARDS ARE
CHECKED.

343

FIGURE III-7. (CONTINUED)

III-56

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-HAD- FLOWCHARTS

FORTRAN MODULE (LIST, NAME, SOURCE)

CARD NO	****	CONTENTS	****
1	900	FORMAT (3I2,A4)	00000100
2	990	FORMAT ('L /,A4, ' FUNC/')	00000200
3	19	FORMAT ('ACTION NOT UNDERSTOOD')	00000300
4	257	FORMAT (1X,12,1X)	00000400
5	10	FORMAT ('SELECT PARAMETER TO BE CHANGED')	00000500
6	100	FORMAT ('1 = CURRICULUM')	00000600
7	11	FORMAT ('2 = MODULE TYPE',/,',3 = MODULE COMPLETION TIMES')	00000700
8	12	FORMAT ('4 = NUMBER OF INSTRUCTORS',/,',5 = GROUP SIZES')	00000800
9	13	FORMAT ('6 = FACILITIES')	00000900
10	7	FORMAT ('7 = STUDENT INPUT RATE')	00001000
11	8	FORMAT ('8 = SCHOOL CAPACITY')	00001100
12	29	FORMAT (111)	00001200
13	14	FORMAT ('ENTER ACTION: INSERT, REPLACE, OR DELETE')	00001300
14	15	FORMAT (A4)	00001400
15	16	FORMAT ('ENTER CURRICULUM NO.')	00001500
16	17	FORMAT (I99)	00001600
17	18	FORMAT ('NEW MODULE =')	00001700
18	20	FORMAT ('FUNCTION CARD ERROR')	00001800
19	21	FORMAT ('ENTER MOD NO. TO BE REPLACED OR DELETED')	00001900
20	23	FORMAT (8A4)	00002000
21	22	FORMAT ('NEW MODULE TO BE INSERTED FOLLOWING?')	00002100
22	27	FORMAT (I22,199)	00002200
23	253	FORMAT (I99)	00002300
24	254	FORMAT ('CANNOT LOCATE.')	00002400
25	252	FORMAT (I12)	00002500
26	250	FORMAT (1X,12,1X)	00002600
27	251	FORMAT (A4)	00002700
28	549	FORMAT ('PRINT 1')	00002800
29	550	FORMAT ('EDIT ',2A4,' GPSS')	00002900
30	551	FORMAT ('STOP')	00003000
31	552	FORMAT ('SDESTACK')	00003100
32	553	FORMAT ('FILE',2A4,'GPSS')	00003200
33	554	FORMAT ('SDESTACK')	00003300
34	555	FORMAT ('R ',A4,' FUNCTION P9,L',I,)	00003400
35	655	FORMAT ('R ',A4,' FUNCTION P9,L',I,)	00003500
36	557	FORMAT ('C ',/,',11',/,',11',/,',11',/,',11')	00003600
37	558	FORMAT ('D 1')	00003700
38	559	FORMAT ('C 1/,',11',/,',11',/,',11',/,',11')	00003800
39	561	FORMAT ('C 1/,',11',/,',11',/,',11')	00003900
40	562	FORMAT ('FILE ',2A4,'GPSS')	00004000
41	563	FORMAT ('SDESTACK')	00004100
42	564	FORMAT ('EXIT')	00004200
43	560	FORMAT ('&TYPE OFF')	00004300
44	565	FORMAT ('ANYMORE CHANGES?')	00004400
45	670	FORMAT ('MODULE TYPE CODE CHANGE.//ENTER MODULE NUMBER')	00004500
46	671	FORMAT ('ENTER OLD TYPE CODE')	00004600
47	672	FORMAT ('ENTER NEW TYPE CODE')	00004700
48	673	FORMAT ('L /MOD/')	00004800
49	674	FORMAT ('C ',/,',11',/,',11',/,',11',/,',11')	00004900
50	675	FORMAT ('C ',/,',12',/,',12',/,',12',/,',12')	00005000
51	676	FORMAT ('C ',/,',11',/,',12',/,',11',/,',11')	00005100
52	677	FORMAT ('C ',/,',12',/,',12',/,',12',/,',12')	00005200
53	678	FORMAT ('C ',/,',11',/,',11',/,',12',/,',12')	00005300
54	679	FORMAT ('C ',/,',12',/,',11',/,',12',/,',12')	00005400
55	680	FORMAT ('C ',/,',11',/,',12',/,',11',/,',12')	00005500
56	681	FORMAT ('C ',/,',12',/,',12',/,',12',/,',12')	00005600
57	685	FORMAT ('COMPLETION TIME CHANGE.//ENTER MODULE NUMBER')	00005700
58	684	FORMAT ('ENTER OLD COMPLETION TIME')	00005800
59	687	FORMAT ('ENTER NEW COMPLETION TIME')	00005900
60	688	FORMAT ('L /TYPE F')	00006000
61	690	FORMAT ('CHANGE NUMBER OF INSTRUCTORS')	00006100
62	691	FORMAT ('ENTER INSTRUCTOR GROUP NUMBER')	00006200
63	692	FORMAT ('ENTER OLD GROUP SIZE')	00006300
64	693	FORMAT ('ENTER NEW GROUP SIZE')	00006400
65	694	FORMAT ('L /INSTN F')	00006500
66	695	FORMAT ('CHANGE STUDENT GROUP SIZE')	00006600
67	696	FORMAT ('ENTER GROUP NUMBER')	00006700
68	697	FORMAT ('ENTER OLD GROUP SIZE')	00006800
69	698	FORMAT ('ENTER NEW GROUP SIZE')	00006900
70	699	FORMAT ('L /TEAM F')	00007000
71	700	FORMAT ('CHANGE FACILITIES INVENTORY')	00007100
72	701	FORMAT ('ENTER FACILITY TYPE')	00007200
73	702	FORMAT ('ENTER CURRENT CAPACITY')	00007300
74	703	FORMAT ('ENTER NEW CAPACITY')	00007400
75	704	FORMAT ('L /STORAGE/')	00007500
76	711	FORMAT ('R GENERATE ',11',/,',11',/,',20')	00007600
77	712	FORMAT ('R GENERATE ',12',/,',11',/,',20')	00007700
78	713	FORMAT ('R GENERATE ',12',/,',12',/,',20')	00007800
79	714	FORMAT ('CHANGE STUDENT INPUT RATE')	00007900
80	715	FORMAT ('NEW STUDENT EVERY ? CLOCK UNITS')	00008000
81	716	FORMAT ('ENTER NUMBER OF CLOCK UNITS OF VARIATION')	00008100
82	717	FORMAT ('L / GENERATE/')	00008200
83	718	FORMAT ('VARIATION GREATER THAN MEAN - TRY AGAIN')	00008300
84	720	FORMAT ('CHANGE STUDENT CAPACITY')	00008400
85	721	FORMAT ('ENTER NEW CAPACITY')	00008500
86	722	FORMAT ('L /ADM VAR/')	00008600
87	723	FORMAT ('R ADD VARIABLE K',12)	00008700
88	724	FORMAT ('R ADD VARIABLE K',13)	00008800
89		DATA TEAM/ TEA/	00008900
90		DATA REPL/REPL/ XINS//INSE//DELE//DELE//FUN//UNCT//	00009000
91		DATA EDF// / /,YES//YES//,XMOD// MOD//	00009100
92		DATA TIME// TYP//	00009200
93		DATA TWIN// INS//	00009300
94		DATA STO//TORA//	00009400
95		DIMENSION ARG (8),TITL(2)	00009500
96		C THIS SET OF WRITES INITIALIZES THE EXEC: &TYPE OFF ETC.	00009600
97		READ (5,23)TITL	00009700
98		WRITE (3,560)	00009800
99		WRITE (3,552)	00009900
100		CALL REREND (12)	00010000
101	122	WRITE (6,10)	00010100
102		WRITE (6,100)	00010200
103		WRITE (6,11)	00010300
104		WRITE (6,12)	00010400
105		WRITE (6,13)	00010500
106		WRITE (6,7)	00010600
107		WRITE (6,8)	00010700
108		READ (5,24)JBRA	00010800
109	323	GOTO (190,60,70,80,90,99,991,995),JBRA	00010900

TABLE III-5

III-57

344

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-HAD- FLOWCHARTS

CARD NO	*****	CONTENTS	*****
110		C THIS SECTION DEALS WITH CURRICULUM UPDATE	00011000
111	50	WRITE (6,14)	00011100
112		READ (9,15) ACT	00011200
113		REWIND 2	00011300
114		WRITE (6,16)	00011400
115		READ (9,17)NCUR	00011500
116		C FOR REPLACE THERE IS NO NEED TO CHANGE FUNCTION CARD	00011600
117		IF(FACT.EQ.DELE)GOTO 52	00011700
118		WRITE (6,18)	00011800
119	194	READ (9,17)NM00	00011900
120		IF(NCUR.GE.10) GOTO 120	00012000
121		WRITE (12,250)NCUR	00012100
122		GOTO 125	00012200
123	52	WRITE (6,21)	00012300
124		GOTO 194	00012400
125	120	WRITE (12,257)NCUR	00012500
126	125	READ(12,251)TEST	00012600
127		C FILE: TURK SHOULD BE SET UP AS SOON AS PROGRAM ENTERED	00012700
128		C EREGSTACK AND EDIT REQUEST ENTERED INTO IT.	00012800
129	121	READ (2,23)(ARG(1),I=1,8)	00012900
130		IF(ARG(1).EQ.EOP)GOTO 130	00013000
131		IF(ARG(1).NE.TEST)GOTO 121	00013100
132		IF(ARG(3).NE.FUN) GOTO 121	00013200
133		C READ A RECORD FROM ETE GPSS, TEST FOR EOP THEN CURRICULUM	00013300
134		C NUMBER AND SO ON.	00013400
135		C IF ALL THESE TESTS PASS WE HAVE LOCATED THE RIGHT CURRICULUM.	00013500
136		IF(FACT.EQ.REPL) GOTO 139	00013600
137		WRITE (12,23)(ARG(1),I=1,8)	00013700
138		READ (12,27)LEN	00013800
139		IF(FACT.EQ.DELE)GOTO 132	00013900
140		LEN = LEN+ 1	00014000
141		GOTO 133	00014100
142	132	LEN = LEN-1	00014200
143		C FUNCTION CARD UPDATE IS NOW COMPLETE	00014300
144		C NEXT, PREPARE CHANGE CARD FOR FUNCTION FOLLOWER	00014400
145	133	WRITE (3,551)	00014500
146		WRITE (3,556)TEST	00014600
147		IF (LEN.GE.10) GOTO 123	00014700
148	124	WRITE (3,555)TEST.LEN	00014800
149		GOTO 138	00014900
150		C THIS SECTION LOCATES NEXT FUNCTION CARD AND COUNTS	00015000
151		C FOLLOWER CARDS	00015100
152	123	WRITE (3,655)TEST.LEN	00015200
153	138	NCNT = 0	00015300
154	194	READ (2,23)(ARG(1),I = 1,8)	00015400
155		IF (ARG(3).EQ.FUN)GOTO 139	00015500
156		NCNT = NCNT +1	00015600
157		GOTO 134	00015700
158	139	WRITE (3,551)	00015800
159		WRITE (3,556)TEST	00015900
160		GOTO 138	00016000
161	135	IF(NCNT) 140,141,140	00016100
162	140	IF(FACT.EQ.XINS)GOTO 157	00016200
163		IF(FACT.EQ.REPL) GOTO 158	00016300
164		GOTO 181	00016400
165	157	WRITE (6,22)	00016500
166		READ (9,17)NPOL	00016600
167		GOTO 177	00016700
168	158	WRITE (6,21)	00016800
169		READ (9,17)NPOL	00016900
170		WRITE (3,551)	00017000
171		WRITE (3,556)TEST	00017100
172		WRITE (3,558)	00017200
173		WRITE (3,557)NPOL,NMOD,NCNT	00017300
174	162	CONTINUE	00017400
175		WRITE (6,565)	00017500
176		READ (9,15)COR	00017600
177		IF (CONV.NE.YES)GOTO 51	00017700
178		WRITE (6,10)	00017800
179		READ (9,17)JBRA	00017900
180		GOTO 323	00018000
181	51	WRITE (3,562)TITL	00018100
182		WRITE (3,563)	00018200
183		WRITE (3,550)TITL	00018300
184		WRITE (3,564)	00018400
185		CALL EXIT	00018500
186	177	WRITE (3,558)	00018600
187		WRITE (3,559)NPOL,NPOL,NMOD,NCNT	00018700
188		GOTO 162	00018800
189	181	WRITE (3,558)	00018900
190		WRITE (3,561)NMOD,NCNT	00019000
191		GOTO 162	00019100
192	130	WRITE (6,254)	00019200
193		REWIND 2	00019300
194		GOTO 122	00019400
195	141	WRITE (6,20)	00019500
196		REWIND 2	00019600
197		GOTO 122	00019700
198	60	WRITE (6,670)	00019800
199		ENODT = ENODT	00019900
200		READ (9,17)NM00	00020000
201		WRITE (6,671)	00020100
202		READ (9,17)KOLD	00020200
203		WRITE (6,672)	00020300
204		READ (9,17)INTVP	00020400
205		C THESE ARE ALL THE PARAMETERS THE USER MUST SUPPLY	00020500
206	64	WRITE (3,551)	00020600
207		WRITE (3,673)	00020700
208		WRITE (3,558)	00020800
209	633	REWIND 2	00020900
210		NCNT = 0	00021000
211	61	READ (2,15)VAR	00021100
212		IF (VAR.EQ.EOP)GOTO 130	00021200
213		IF (VAR.NE.ENODT) GOTO 61	00021300
214		C NODT FUNCT HAS BEEN LOCATED	00021400
215		C NOW COUNT FUNCTION FOLLOWER CARDS	00021500
216	62	READ (2,23)(ARG (1),I = 1,3)	00021600
217		IF (ARG(3).EQ.FUN)GOTO 63	00021700
218		NCNT = NCNT+1	00021800
219		GOTO 62	00021900
220	63	IF(NCNT)364,141,364	00022000
221		C WE ARE NOW READY TO INSERT EDIT COMMANDS	00022100

TAEK REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-MAD- FLOWCHARTS

CARD NO	CONTENTS	*****
222	304 IF (NMDD,GE,10)GOTO 65	00022200
223	IF (KOLD,GE,10)GOTO 66	00022300
224	IF (INTYP,GE,10)GOTO 67	00022400
225	WRITE (3,674)NMDD,KOLD,NMDD,NTYP,NCNT	00022500
226	GOTO 162	00022600
227	65 IF (KOLD,GE,10)GOTO 620	00022700
228	IF (INTYP,GE,10)GOTO 621	00022800
229	WRITE (3,675)NMDD,KOLD,NMDD,NTYP,NCNT	00022900
230	GOTO 162	00023000
231	66 IF (INTYP,GE,10)GOTO 622	00023100
232	WRITE (3,676)NMDD,KOLD,NMDD,NTYP,NCNT	00023200
233	GOTO 162	00023300
234	67 WRITE (3,678)NMDD,KOLD,NMDD,NTYP,NCNT	00023400
235	GOTO 162	00023500
236	620 IF (INTYP,GE,10)GOTO 623	00023600
237	WRITE (3,677)NMDD,KOLD,NMDD,NTYP,NCNT	00023700
238	GOTO 162	00023800
239	621 WRITE (3,679)NMDD,KOLD,NMDD,NTYP,NCNT	00023900
240	GOTO 162	00024000
241	622 WRITE (3,680)NMDD,KOLD,NMDD,NTYP,NCNT	00024100
242	GOTO 162	00024200
243	623 WRITE (3,681)NMDD,KOLD,NMDD,NTYP,NCNT	00024300
244	GOTO 162	00024400
245	70 WRITE (6,685)	00024500
246	READ (5,17)NMDD	00024600
247	WRITE (6,686)	00024700
248	READ (5,17)KOLD	00024800
249	WRITE (6,687)	00024900
250	READ (5,17)INTYP	00025000
251	WRITE (3,551)	00025100
252	WRITE (3,688)	00025200
253	WRITE (3,558)	00025300
254	EMDDY = TIME	00025400
255	GOTO 633	00025500
256	80 WRITE (6,690)	00025600
257	WRITE (6,691)	00025700
258	READ (5,17)NMDD	00025800
259	WRITE (6,692)	00025900
260	READ (5,17)KOLD	00026000
261	WRITE (6,693)	00026100
262	READ (5,17)INTYP	00026200
263	EMDDY = TIME	00026300
264	WRITE (3,551)	00026400
265	WRITE (3,694)	00026500
266	WRITE (3,558)	00026600
267	GOTO 633	00026700
268	90 WRITE (6,695)	00026800
269	WRITE (6,696)	00026900
270	READ (5,17)NMDD	00027000
271	WRITE (6,697)	00027100
272	READ (5,17)KOLD	00027200
273	WRITE (6,698)	00027300
274	READ (5,17)INTYP	00027400
275	WRITE (3,551)	00027500
276	WRITE (3,699)	00027600
277	WRITE (3,558)	00027700
278	EMDDY = TEAM	00027800
279	GOTO 633	00027900
280	99 WRITE (6,700)	00028000
281	WRITE (6,701)	00028100
282	READ (5,17)NMDD	00028200
283	WRITE (6,702)	00028300
284	READ (5,17)KOLD	00028400
285	WRITE (6,703)	00028500
286	READ (5,17)INTYP	00028600
287	WRITE (3,551)	00028700
288	WRITE (3,704)	00028800
289	REWIND 2	00028900
290	NCNT = 0	00029000
291	101 READ (2,23)(ARG(1),I=1,8)	00029100
292	IF (ARG(1),EQ,END) GOTO 102	00029200
293	IF (ARG(1),NE,STO) GOTO 101	00029300
294	NCNT = NCNT + 1	00029400
295	GOTO 101	00029500
296	102 IF (NCNT) 364,141,364	00029600
297	991 WRITE (6,714)	00029700
298	WRITE (6,715)	00029800
299	READ (5,17)NRAT	00029900
300	WRITE (6,716)	00030000
301	READ (5,17)NVAR	00030100
302	WRITE (3,551)	00030200
303	WRITE (3,717)	00030300
304	IF (NVAR,GE,NRAT)GOTO 993	00030400
305	IF (NRAT,GE,10)GOTO 992	00030500
306	IF (NVAR,GE,10)GOTO 993	00030600
307	WRITE (3,711)NRAT,NVAR	00030700
308	GOTO 162	00030800
309	992 IF (NVAR,GE,10)GOTO 994	00030900
310	WRITE (3,712)NRAT,NVAR	00031000
311	WRITE (3,549)	00031100
312	GOTO 162	00031200
313	994 WRITE (3,713)NRAT,NVAR	00031300
314	WRITE (3,549)	00031400
315	GOTO 162	00031500
316	993 WRITE (6,718)	00031600
317	GOTO 991	00031700
318	995 WRITE (6,720)	00031800
319	WRITE (6,721)	00031900
320	READ (5,17)NCAP	00032000
321	WRITE (3,551)	00032100
322	WRITE (3,722)	00032200
323	IF (NCAP,GE,100) GOTO 996	00032300
324	WRITE (3,723)NCAP	00032400
325	WRITE (3,549)	00032500
326	GOTO 162	00032600
327	996 WRITE (3,724)NCAP	00032700
328	WRITE (3,549)	00032800
329	GOTO 162	00032900
330	END	00033000
331	C FOR CHANGES INVOLVING STORAGES THE ASSUMPTION IS	00033100
332	C MADE THAT THEY ARE SPECIFIED INDIVIDUALLY.	C,033200
333	C HOWEVER, A COUNT OF STORAGE CARDS WILL BE MADE TO	00033300
334	C BE SURE THAT ALL STORAGE CARDS ARE CHECKED.	00033400

SIMULATION SUBSYSTEM

The simulation subsystem consists of one GPSS program (DUMMY) and its associated executive (GPSS EXEC). As previously mentioned, DUMMY does not constitute an executable model. Only after insertion of the required FUNCTION and VARIABLE statements is the model executable.

GPSS EXEC forms the link between ETE2 and the NGPSS compiler. It is transparent to the user and requires no operator intervention. GPSS EXEC provides responses to the queries of the NGPSS compiler via the STACK command. GPSS EXEC passes the name of the model to be executed to the NGPSS system and causes NGPSS to terminate execution after a single model run.

DUMMY GPSS contains all the simulation logic. Function cards are inserted beginning at the *START card. This area is clearly denoted in the program listing by a set of comments cards. The functions supplied by the model generation subsystem are listed and described in Figure III-8.

Figure III- 9 is a flow of the logic contained in DUMMY GPSS. Model logic can be summarized as follows:

1. Transactions (students) are generated at a fixed rate.
2. Each time a transaction is generated, a test is made to see if the system already contains the maximum permissible number of transactions (a variable designated AOB is used for this test). The total number of transactions currently in the system is contained in SAVEVALUE 101. If the system is full (i.e. SAVEVALUE 101 AOB) the transaction is destroyed.
3. If the transaction is permitted to enter the system, it is then assigned a transaction type number via the function INTIM. Once the type number has been assigned, it remains the same as long as the transaction is in the system.
4. For each transaction type there is a corresponding function which controls transaction activity for the remainder of its time in the system. These functions do not have symbolic names but are designated 1, 2, 3,---etc. and constitute the curricula to be followed by the students. The transaction type number and the curriculum function number are equal.
5. The numbers contained in the curriculum functions are learning module numbers and are used as arguments for reference to other functions to determine module type code, completion time, etc.
6. Module type code is discussed under the model generation subsystem and determines the support requirements for each module.

FUNCTION NAME	TYPE	DESCRIPTION
1,2,3, etc.	LIST	Curriculum Functions relate step number to module number.
MODT	LIST	Relates module number to module type code.
TYME	LIST	Relates module number to completion time.
SPRD	LIST	Relates module number to completion time variation.
INSTT	LIST	Relates instructor group number to module number.
INSTN	LIST	Relates instructor group size to module number.
STUDT	DISCRETE	Relates student type to random number distribution.
FACT	LIST	Relates facilities groups to module number.
TEAM	LIST	Relates team size to module number.
REMM	LIST	Relates remedial module groups to module numbers.
UNSHL	LIST	Relates staff groups to module numbers.

SYSTEM GENERATED GPSS FUNCTIONS

FIGURE III-8

7. Once the student begins a module, resources are obtained in the following order:


- a) Instructional materials - STORAGES 1-50
- b) Staff personnel - STORAGES 101 - 125
- c) Other facilities - STORAGES 51 - 100
- d) Instructor - FACILITIES 1 - 50

As the flow diagram shows, the transaction (student) always waits when a particular resource is needed but not available.

8. The students move through each module (as controlled by the curriculum function) until the last module is completed (this condition is noted when the next curriculum step = 50). The student is then terminated and the student head count and graduation statistics updated.

SIMULATION OUTPUT. All output is generated via the GPSS report generator. No standard GPSS output appears (although it is easily obtained by editing an OUTPUT card into DUMMY GPSS).

Two cards: UNLIST and SKIP are used to suppress output of any assembly listings. These listings are suppressed in order to keep the output files as small as possible.






FIGURE III- 9 (CONTINUED)


```

EDUCATIONAL TECHNOLOGY EVALUATION MODEL LEVEL 1
SIMULATE
UNLIST
SKIP
ONE VARIABLE FN$TYME/2 THESE ARE USED TO COMPUTE MEAN
TWO VARIABLE FN$SPRD/2 AND SPREAD FOR REMEDIAL MODULES
THREE VARIABLE X*P2/X*P1 COMPUTE AVG TRANSIT TIME
FOUR FVARIABLE (1-FN$INTIM)*FN$TYME
* FOUR COMPUTES REDUCED TIME FOR INSTRUCTOR IN USE
FIVE FVARIABLE (1-FN$INTIM)*FN$SPRD
* FIVE COMPUTES REDUCED SPREAD FOR INSTRUCTOR IN USE
SIX VARIABLE FN$TYME-P15
SEVN VARIABLE FN$SPRD-P16
ATE VARIABLE P15/2 VARIABLE TO COMPUTE REDUCED
NINE VARIABLE P16/2 TIMES FOR REMEDIAL MODULES.
THE FUNCTION CARDS WITHIN
THIS AREA ARE SAMPLE DATA
ONLY AND SHOULD
BE REPLACED BY THE USER-GENERATED TABLES
DESCRIBING THE CURRICULA, INSTRUCTORS, AND
EQUIPMENT, ETC. NECESSARY TO DEFINE THE
ILS TO BE SIMULATED
INTIM FUNCTION RN5,C3
1.0 .2 1.0 1.0 .0
START
INTIM ASSIGNS FRACTIONAL TIMES WHEN INSTRUCTOR IN USE
GENERATE 4,0,,,20
SAVEVALUE 101+,K1 INCREMENT NO. OF STUDENTS
TEST G X101,V$AOB,OKK TEST FOR AOB EXCEEDED
SAVEVALUE 101-,K1
TERMINATE
OKK ASSIGN 9,1 OK, GO AHEAD, SET P9 = 1
ASSIGN 1,FN$STUD ASSIGN STUDENT TYPE TO P1
ASSIGN 2,FN*1 GET FIRST MODULE NUMBER IN P2
ASSIGN 3,FN$MODT PUT MODULE TYPE IN P3
ZZZ SAVEVALUE 51,P3 MOVE MODULE TYPE TO X51
TEST GE X51,K16,BBB TEST MOD TYPE GE 16
ASSIGN 8,1 YES SET LOGIC SWITCH FOR REMEDIAL
SAVEVALUE 51-,K16 REDUCE MODULE DESIGNATOR BY 16
BBB TEST GE X51,K8,CCC TEST MODULE TYPE GE 8
ASSIGN 7,1 SET FACILITIES REQUIRED SWITCH
SAVEVALUE 51-,K8 REDUCE MODULE DESIGNATOR BY 8
CCC TEST GE X51,K4,DDD TEST MODULE TYPE GE 4
ASSIGN 6,1 SET STAFF REQUIRED SWITCH

```

DUMMY GPSS LISTING
TABLE III-6

TAEG REPORT NO. 29

DDD	SAVEVALUE	51-,K4	REDUCE MODULE TYPE BY 4
	TEST GE	X51,K2,EEE	TEST GE 2
	ASSIGN	5,1	SET OTHER STUDENTS REQUIRED
	SAVEVALUE	51-,K2	REDUCE MODULE TYPE BY 2
EEL	TEST GE	X51,K1,FFF	TEST GE 1
	ASSIGN	4,1	EQUALS 1-SET INSTRUCTOR REQUIRED
*			ALL REQUIRED SWITCHES ARE SET
*			SWITCH ASSIGNMENTS ARE AS FOLLOWS
*			PARAMETER 1 - STUDENT TYPE
*			PARAMETER 2 - CURRENT MODULE NUMBER (FOR THIS XACT)
*			PARAMETER 3 - CURRENT MODULE TYPE
*			PARAMETER 4-8 - SWITCHES FOR INSTRUCTOR NEEDED ETC
*			PARAMETER 4 - INSTRUCTOR NEEDED
*			PARAMETER 5 - GROUP MODULE
*			PARAMETER 6 - STAFF REQUIRED
*			PARAMETER 7 - FACILITIES REQUIRED
*			PARAMETER 8 - REMEDIAL MATTER OUTSIDE MODULE
*			PARAMETER 9 - CURRENT MODULE STEP (FOR THIS XACT)
*			PARAMETER 10 -FLAG THAT SAYS REMEDIATION IS NEEDED
*			PARAMETER 11 -FLAG THAT DESIGNATES CURRENT MODULE
			IS A REMEDIAL MODULE
FFF	TEST E	K1,P5,GRUP	TEST FOR OTHER STUDENTS REQUIRED
	ASSIGN	12,FNSTEAM	PUT NUMBER OF TEAM MEMBERS IN 12
	ASSIGN	2+,100	ASSIGN QUEUE NUMVER = TYPE + 100 (GROUP)
	QUEUE	*2	YES THEY ARE-TEST FOR OTHERS
	ASSIGN	10,P2	P10 WILL HAVE P2+8 AS LOGIC SWITCH NO.
	ASSIGN	10+,8	
	TEST E	Q*10,0,FIX	IF Q*10 IS EMPTY LET FIRST
	LOGIC R	*10	TEAM MEMBER GO THROUGH
FIX	TEST GE	Q*2,P12,HLD	TEST FOR REQ. NO. IN QUEUE
	LOGIC S	*2	YES THERE ARE, OPEN GATE FOR OTHERS
HLD	GATE LS	*2	HOLD HERE UNTIL TEAM COMPLETE
	DEPART	*2	REMOVE FROM TEAM QUEUE
	GATE LR	*10,ENDS	DIVERT IF OTHER THAN FIRST MEMBER
	LOGIC S	*10	FIRST MEMBER SETS GATE TO DIVERT
	ASSIGN	2-,100	SET BACK TO STUDENT TYPE
	BUFFER		
GRUP	TEST E	K1,P11,GRUPE	TEST FOR REMEDIAL MODULE
GROPE	ASSIGN	2+,100	MOVE POINTER TO REMEDIAL MODULE STORAGE
	ENTER	*2	GET REMEDIAL MODULE
	ASSIGN	2-,100	RESET POINTER
	TRANSFER	,COM1	YOU MAY NOW PROCEED
GRUPE	ENTER	*2	POINTER FOR MODULE STORAGE IS P2
COM1	TEST E	K1,P6,NINS	TEST FOR STAFF NEEDED
NSH	ASSIGN	20,FNSUNSHL	PUT FACILITY LOCATION AND
	ASSIGN	17,35	LOGIC SWITCH 35 FOR THIS FACILITY
	ASSIGN	20+,125	ASSIGN CORRECT QUEUE AND STORAGE
	QUEUE	*20	
	ENTER	*20	GET UNSHARED STAFF
	DEPART	*20	LEAVE QUEUE WHEN STAFF OBTAINED
	TRANSFER	,NINS	
SHR	GATE LR	43	SHARED STAFF-AVAILABLE IF RESET
MMM	TEST E	K1,P4,NFAC	TEST FOR INSTRUCTOR REQUIRED
	ASSIGN	14,FNSINSTT	PUT QUEUE
	QUEUE	*14	QUEUE PRIOR TO TRYING FOR INSTRUCTOR
LLL	ASSIGN	14,FNSINSTT	PUT HIGHEST INST. FAC LOC IN P14
	ASSIGN	12,1,INSTN	PUT NUMBER OF INSTRUCTORS IN 12
	ASSIGN	17,36	LOGIC SWITCH 36 FOR INSTRUCTORS
LLL1	TRANSFER	SBR,CCCS,18PH	ATTEMPT TO SEIZE INSTRUCTOR
	GATE LR	*17	HOLD HERE UNTIL SOMEBODY RELEASES
	TRANSFER	,LLL	AN INSTRUCTOR, THEN TRY AGAIN
	ASSIGN	19,P14	MOVE INSTRUCTOR POINTER TO P19
	ASSIGN	14,FNSINSTT	RESTORE QUEUE NO. IN P14

TABLE III-6 (CONTINUED)

	DEPART	*14	RELEASE AFTER GETTING INSTRUCTOR
	ASSIGN	14-, 12#	RESET P14 TO CORRECT VALUE
	ASSIGN	12, FNSFACT	
	ASSIGN	12+, 5#	RESET 12 TO OFAC
	TRANSFER	, NFAC	
NINS	TEST E	K1, P7, MMM	TEST FOR OTHER FACILITIES
	ASSIGN	12, FNSFACT	PUT FACILITY STORAGE NUMBER IN 12
	ASSIGN	12+, 5#	MOVE POINTER TO CORRECT QUEUE
	QUEUE	*12	QUEUE PRIOR TO ENTERING STORAGE
	ENTER	*12	OCCUPY OTHER FACILITIES IF POSSIBLE
	DEPART	*12	LEAVE QUEUE WHEN FINISHED
	TRANSFER	, MMM	
NFAC	TEST E	K1, P8, DEL	TEST FOR REMEDIATION SELF CONTAINED
	TRANSFER	.6, REM, DEL	NOT SELF CONTAINED. SPLIT 4# PERCENT
REM	ASSIGN	8, 2	SET REMEDIAL NEEDED
	TRANSFER	, DEL	GO DELAY
ENDS	QUEUE	*1#	
	TEST E	Q*2, #, STT	TEST FOR ALL REMOVED
	LOGIC R	*2	CLOSE GATE TO Q*2 EXIT
STT	GATE LR	*1#	HOLD HERE FOR REST OF THEM
	DEPART	*1#	
	ASSIGN	2-, 1#	SET BACK TO STUDENT TYPE
	TEST E	Q*1#, #, NNFC	KEEP SENDING XACTS TO COMPLETION
	LOGIC S	*1#	UNTIL QUEUE IS EMPTY. THEN CLOSE
	TRANSFER	, NNFC	GATE.
GRAD	ASSIGN	2, P1	MOVE POINTER TO P2
	ASSIGN	2+, 25	SET IT 1#-15
	SAVEVALUE	P1+, 1	ADD 1 TO GRAD COUNT
	SAVEVALUE	P2+, M1	ADD TRANSIT TIME TO TOTAL
	SAVEVALUE	P1, VSTHREE, XH	COMPUTE AVG TIME AND PUT IN P3 SAVE
	SAVEVALUE	1#1-, K1	REDUCE AOB FOR GRADUATION
TRM1	TERMINATE	1	
NRM	TEST E	K1, P11, NRM1	TEST FOR REMEDIAL MODULE
	ASSIGN	15, VNONE	YES, SET UP REDUCED COMPLETION
	ASSIGN	16, VSTWO	TIME AND SPREAD
	TRANSFER	, DELS	GO DELAY
NRM1	ASSIGN	15, FNSTYME	FN 5 HAS MODULE TIME
	ASSIGN	16, FNSSPRD	FN 6 HAS SPREAD FOR MODULE
	TRANSFER	, DELS	GO TO DELAY FOR THIS MODULE
DEL	TEST E	K1, P4, NRM	TEST FOR INSTRUCTOR NEEDED
	ASSIGN	15, VSFOR	ASSIGN REDUCED COMPLETION TIME
	ASSIGN	16, VSFIVE	AND SPREAD.
	TEST E	K1, P11, JDEL	TEST FOR REMEDIAL
	ASSIGN	15, VSATE	IT ARE ONE, REDUCE
	ASSIGN	16, VSNINE	COMPLETION TIME
JDEL	ADVANCE	P15, P16	DELAY FOR THIS MODULE
	RELEASE	*19	LET THE INSTRUCTRO GO
	LOGIC R	*17	
	BUFFER		
	ASSIGN	15, VSSIX	SET UP REMAINDER
	ASSIGN	16, VSSEVN	OF DELAY.
	ADVANCE	P15, P16	DELAY REST OF TIME
	TRANSFER	, DELP	GO FNISH UP
DELS	ADVANCE	P15, P16	DELAY FOR THIS MODULE
"	AT THIS POINT THE STUDENT HAS BEEN SET UP TO DO THE MODULE		
"	THE COMPLETION LOGIC TAKES CARE OF THING LIKE REMEDIAL		
"	MODULES, LAST MODULE ETC.		
DLP	TEST E	K2, P8, ABD	TEST FOR REMEDIAL MODULE NEEDED
	TEST E	K1, P5, ABM	TEST FOR GROUP XACT
	ASSIGN	8, #	TURN OFF REMEDIAL FLAG
	ASSIGN	11, #	TURN OFF FLAG FOR REMEDIAL MODULE

TABLE III-6 (CONTINUED)

	ASSIGN	15,V\$ONE	AND SPREAD. FUNCTION 3 IS REMEDIAL TIME
	ASSIGN	16,V\$TWO	FN4 IS REMEDIAL SPREAD
	TRANSFER	,DELS	YES, GO DELAY FULL TIME
ABM	LEAVE	*2	GIVE UP MODULE
	TEST E	K1,P7,NNF1	
	ASSIGN	12,FN\$FACT	
	ASSIGN	12+,50	SET TO OTHER FACILITIES
	LEAVE	*12	
NNF1	ASSIGN	11,1	SET FLAG THAT THIS IS A REMEDIAL MODUL
	BUFFER		
	ASSIGN	3,FN\$MODR	SET REMEDIAL MODULE TYPE
	ASSIGN	4,0	
	ASSIGN	5,0	
	ASSIGN	6,0	
	ASSIGN	7,0	
	ASSIGN	8,0	
	TRANSFER	,ZZZ	PROCESS LIKE REGULAR MODULE.
ABD	TEST E	K1,P11,AAB	TEST FOR COMPLETION OF REMEDIAL MOD
	ASSIGN	11,0	YES IT WAS,TURN OFF REMEDIAL FLAG
	TEST L	P2,K100,REL	
	ASSIGN	2+,100	SET TO REM MOD POINTER
AAB	TEST E	K1,P5,AABB	TEST FOR GROUP XACT FINISHED
	LOGIC R	*10	OPEN GATE FOR REST OF TEAM
	BUFFER		LET OTHER TEAM MEMBERS MOVE
AABB	TRANSFER	,REL	
REL	LEAVE	*2	GIVE UP MODULE
	TEST NE	0,P20,DDD1	TEST FOR UNSHARED STAFF
	LEAVE	*20	RELEASE STAFF
	ASSIGN	20,0	TURN OFF FLAG AFTER RELEASING
DDD1	LOGIC R	34	OPEN GATES FOR MODULE, INSTRUCTOR
	LOGIC R	35	OR STAFF AGAIN
	LOGIC R	36	
	TEST E	K1,P7,NNFC	TEST FOR OTHER FACILITIES
	LEAVE	*12	RELEASE OTHER FACILITIES
	BUFFER		
NNFC	ASSIGN	4,0	ZERO OUT ALL LOGIC SETTINGS
	ASSIGN	5,0	ZERO OUT ALL LOGIC STTINGS
	ASSIGN	6,0	
	ASSIGN	7,0	
	ASSIGN	8,0	
	ASSIGN	11,0	ZERO REMEDIAL SWITCH
	TRANSFER	,AAC	GO TO NEXT MODULE
AAC	ASSIGN	9+,1	STEP P9 TO NEXT COURSE STEP
	ASSIGN	2,FN*1	PUT NEW MOD NO. IN P2
	TEST NE	50,P2,GRAD	
	ASSIGN	3,FN\$MODT	ASSIGN NEW MODULE TYPE
	TRANSFER	,ZZZ	GO PROCESS NEXT MODULE
*	THIS IS A SUBROUTINE FOR SEIZING MODULES, INSTRUCTORS OR WHAT EVER		
*	ENTER WITH NUMBER OF ENTITIES TO BE TESTED IN P12		
*	NUMBER (LOCATION) OF HIGHEST ENTITY IN P14		
*	LOCATION OF LOGIC SWITCH IN P17		
*	RETURNS WITH SEIZED ENTITY IN P14. IF FACILITY UNAVAILABLE		
*	CLOSES LOGIC GATE AT RETURN POINT		
*	RETURNS TO TRANSFER+1 WHEN BAD, TRANSFER+2 WHEN GOOD		
CCCS	GATE U	*14,SEZ	CHECK FACILITY IN USE
	ASSIGN	14-,1	YES IT IS,TRY NEXT
	LOOP	12,CCCS	
	LOGIC 5	*17	DIDNT FIND ANY CLOSE GATE
	TRANSFER	PH,18,1	RETURN TO CALLER
SEZ	SEIZE	*14	FACILITY AVAILABLE SEIZE IT
	TRANSFER	PH,18,3	DIFFERENT RETURN WHEN SUCCESSFUL
	START	50	

TABLE III-6 (CONTINUED)


```

REPORT
SPACE      25

STUDENT STATISTICS
SPACE      2
STUDENT TYPE  NUMBER COMPLETING  AVG. COMPLETION TIME
FORMAT      1-25/X1,X2,XH2
SPACE      2
EJECT

INSTRUCTOR STATISTICS
SPACE      1
INSTRUCTOR NO.  PERCENT UTIL.  AVG. WAIT TIME  MAX. NO. WAITING
FORMAT        1-50/F1,F2,Q8,Q2
SPACE

MODULE UTILIZATION
SPACE      1
MODULE NO.    PERCENT USAGE  NO.USING  AVG. TIME
SPACE      1
FORMAT      1-30/S1,S4,S5,S6
SPACE
EJECT

OTHER FACILITIES UTILIZATION
SPACE      1
FACILITY NUMBER  PERCENT USAGE  NO. USING  AVG. TIME
SPACE      1
FORMAT      51-70/S1,S4,S5,S6
SPACE
EJECT

QUEUE DATA
SPACE      1
QUEUE NUMBER  MAX CONTENTS  AVG WAIT TIME  AVG CONTENTS
FORMAT        1-35/Q1,Q2,Q7,Q3
FORMAT        51-70/Q1,Q2,Q7,Q3
FORMAT        101-150/Q1,Q2,Q7,Q3
EJECT

STAFF GROUP  PERCENT UTIL.  AVG WAIT TIME  MAX NO WAITING
FORMAT        125-140/S1,S4,Q8,Q2

FINISH
END
/

07.47.14

```

TABLE III-6 (CONTINUED)

SECTION IV.

SYSTEM CAPABILITIES/REQUIREMENTS AND RESOURCES MODEL

MODEL DESCRIPTION

The SCRR model is a set of sixteen (16) VP/CSS Executive procedures, eight (8) FORTRAN programs, two (2) PL/I programs, and one (1) MPS III/OL procedure. All of these procedures and programs are executed under the control of the seven (7) primary VP/CSS Executives depicted in Figure IV-1. Figure IV-1 shows the overall flow through the seven executives and the connection with the RAMIS scratch data base procedures. The various input and output data files and all executives, programs and procedures executed by the primary executives do not appear, since some are accessed several times and the over-view flowchart would be nearly unintelligible.

Table IV-1 gives a brief description of the VP/CSS Executive programs utilized by the SCRR model. All RAMIS procedures, FORTRAN programs, PL/I programs, and the MPS III/OL procedure are executed by these executives. This section of the Programmer's Manual has been organized based on these VP/CSS executive programs. For example, the RAMSCRR subsection contains the verbal descriptions, flowcharts, and listings for the RAMSCRR EXEC and the five RAMIS procedures executed by RAMSCRR. The SCRR1 subsection contains descriptions, flows, and listings for the SCRR1 EXEC, the MPS III/OL procedure, and the FORTRAN subroutine executed under control of MPS III.

Table IV-2 gives a list of the input and output data files used by each of the executive programs. All files are stored on disk and are named by a unique three-part identifier composed of a filename, a filetype and a filemode. Only the filename and filetype are shown in Table IV-2. All these files have a filemode of P which indicates that they reside on the P (Permanent) disk.

OVERVIEW OF SCRR EXECUTIVE PROGRAMS




FIGURE IV-1

SCRR EXECUTIVE PROGRAMS DESCRIPTION

EXEC NAME	DESCRIPTION
SCRR	A top level executive which executes the following programs: RAMSCRR, BLANK, IF1, IF2, SCRRSORT, IF3, IF4, COMB, and SCRR1.
RAMSCRR	Uses the RAMIS data base procedures SCRR INST, SCRR FACIL, SCRR IAVAIL, SCRR FAVAIL, and SCRR CRSE to retrieve all SCRR model basic input data from the three scratch data files MODCOURSE, MODINST, and MODFACIL and to derive additional data from these basic inputs.
BLANK	Deletes all internal blank characters from facility names in the files FILE FACIL and FILE FAVAIL.
IF1	Formats NAME and ROW data for LP input.
IF2	Formats LP COLUMN data including instructor and facility requirements and objective function coefficients.
SCRRSORT	Sorts IF2 output by course CDP number.
IF3	Formats LP RHS data section, including instructor and facility availabilities.
IF4	Formats BOUNDS data section, including course convenings limits, of LP input data.
COMB	Combines outputs from IF1, IF2, IF3, and IF4 into a single file MATRIX1 DATA which is directly readable through MPS III/OL Terminal Control Language.
SCRR1	Establishes all control data (i.e., input, output, and internal processing files) required by MPS III/OL system and initiates the LP processing.
SCRR2	A top level executive which executes the following programs: BLANK, IF2, SCRRSORT, COMB, SCRR1.
ASSIGN	Compiles and prints a list of instructor assignments and contact hour requirements.
MODAVAIL	Modifies resource availability data prior to LP optimization.
REQMT	Permits user to specify percentage changes to variables which impact instructor requirements.
FIXCONV	Modifies the LP input data to fix the number of course convenings at the current level.

TABLE IV-1

SCRR DATA FILE SUMMARY

EXEC	INPUT FILES	OUTPUT FILES
RAMSCRR	RAMIS files MODCOURSE, MODINST, MODFACIL	FILE INST, FILE IAVAIL, FILE FACIL, FILE FAVAIL, FILE CRSE
BLANK	FILE FACIL, FILE FAVAIL	FILE FACIL, FILE FAVAIL
IF1	FILE IAVAIL, FILE FAVAIL	FILE IF1
IF2	FILE INST, FILE FACIL, FILE CRSE	FILE IF2
SCRRSORT	FILE IF2	FILE IF2
IF3	FILE IAVAIL, FILE FAVAIL	FILE IF3
IF4	FILE CRSE	FILE IF4
COMB	FILE IF1, FILE IF2, FILE IF3, FILE IF4	MATRIX1 DATA
SCRR1	MATRIX1 DATA, SCRR RUN, SCRRFORM LNKLIB	SCRR OUTPUT
ASSIGN	FILE INST, FILE CRSE, FILE IAVAIL	ASSIGN LISTING
MODAVAIL	MATRIX1 DATA	MATRIX1 DATA
REQMT	RAMIS files MODCOURSE and MODFACIL	FILE FACIL, FILE INST, FILE CRSE
FIXCONV	MATRIX1 DATA	MATRIX1 DATA
MAXCONV	MATRIX1 DATA	MATRIX1 DATA

TABLE IV-2

SCRR EXEC DESCRIPTION

The purpose of executive SCRR is to execute all SCRR model-related executives through a single keyboard entry.

Upon entry, a test is made to determine if core size is equal to or greater than 320K. If core size is less than 320K, a message directing the user to SET CORE 320 is issued and SCRR EXEC is terminated. If the core requirement is met, a message describing the objective of the EXEC is printed and the user is given the alternative of proceeding with model execution or terminating the SCRR EXEC at this point. If the user elects to proceed with SCRR model execution, the following EXECs are executed serially:

RAMSCRR
BLANK
IF1
IF2
SCRRSORT
IF3
IF4
COMB
SCRR1

Each of these executives is described in detail on the following pages.

SCRR EXEC FLOWCHART




FIGURE IV-2

SCRR PROGRAM LISTING

SCRR EXEC
 VP/CSS

```
&IF &CORE GE 320 &SKIP 3
&PRI REQUIRED CORE IS 320K. PLEASE TYPE: SET CORE 320
&PRI THEN REISSUE COMMAND: SCRR
&EXIT
&PRI THIS PROGRAM PERFORMS THE LINEAR PROGRAMMING OPTIMIZATION
&PRI OF THE RESOURCE DATA CURRENTLY STORED IN THE SCRATCH DATA FILES.
&PRI NO FURTHER USER INTERVENTION WILL BE REQUIRED.
&PRI DO YOU WISH TO PROCEED? (YES/NO)
&READ ARGS
&IF &1 NE YES &GOTO -EXIT
&STACK KT
EXEC RAMSCRR
EXEC BLANK
EXEC IF1
EXEC IF2
EXEC SCRRSORT
&STACK KT
EXEC IF3
EXEC IF4
EXEC COMB
EXEC SCRR1
-EXIT &EXIT
```

TABLE IV-3

RAMSCRR EXEC DESCRIPTION

All interface between the SCRR model and the DOTS data base is performed by the RAMSCRR EXEC. RAMSCRR utilizes a series of RAMIS data base procedures to retrieve (and to calculate when required) instructor and facility requirements and availabilities and course parameters from the three RAMIS data files MODINST, MODCOURSE, and MODFACIL.

Initial RAMSCRR statements suppress all terminal output and gain access to RAMIS data base software. Then the output file FILE INST is established for the RAMIS procedure SCRR INST, and SCRR INST is executed. Similarly, output files FILE FACIL, FILE FAVAIL, FILE IAVAIL, and FILE CRSE are defined and RAMIS procedures SCRR FACIL, SCRR FAVAIL, SCRR IAVAIL, and SCRR CRSE are executed. RAMSCRR EXEC concludes by removing the RAMIS software disk from the user's virtual machine.

SCRR INST DESCRIPTION. The purpose of the RAMIS procedure SCRR INST is to calculate instructor requirements in hours by course and by instructor. The basic data required to determine instructor requirements are stored in the RAMIS course file MODCOURSE.

SCRR INST first calculates the total number of contact hours required (TOT&HRS) for each student/instructor ratio (SIR) within each course (CDP). The class capacity is multiplied by the historical course utilization percentage to determine average class size. Average class size is divided by the SIR to determine the number of instructors (NO&INST) required at each SIR. NO&INST is multiplied by the required contact hours at each SIR to arrive at TOT&HRS.

The number of instructors physically assigned at each SIR is determined by summing the value of ASN (1 = assigned, 0 = not assigned). TOT&HRS is then divided by the sum of ASN to determine the number of hours required per instructor per SIR (INST&HRS). Summing INST&HRS by course (CDP) and by instructor is the final step of the SCRR INST procedure. Output is written on FILE INST. The record format for FILE INST is shown below:

FIELD NAME	CDP NO	INST NAME	REQ'D HRS
TYPE	A	A	F
LENGTH	4	16	4.1
RELATIVE POS	1-4	5-20	21-25

SCRR FACIL DESCRIPTION. The purpose of the RAMIS procedures SCRR FACIL is to determine facility requirements in hours by course and by facility. These data are stored in the RAMIS facility file MODFACIL.

SCRR FACIL retrieves the required hours from MODFACIL by course and by building and room number. Output is written on FILE FACIL. The record format for FILE FACIL is shown below:

FIELD NAME	CDP NO.	BLDG.	RM	REQ'D HRS.
TYPE	A	A	A	F
LENGTH	4	5	3	5.1
RELATIVE POS.	1-4	5-9	10-12	13-18

SCRR FAVAIL DESCRIPTION. The purpose of the RAMIS procedure SCRR FAVAIL is to determine facility availability. Annual availability is stored in the RAMIS facility file MODFACIL by building and room.

A building and room combination may appear in the MODFACIL file more than once. Annual available hours is included on each MODFACIL record. SCRR FAVAIL retrieves the available hours associated with only the first appearance of each facility in the file. Output is written on FILE FAVAIL. The record format for FILE FAVAIL is shown below:

FIELD NAME	BLDG.	RM	AVAIL HRS.
TYPE	A	A	I
LENGTH	5	3	4
RELATIVE POS.	1-5	6-8	9-12

SCRR IAVAIL DESCRIPTION. The purpose of the RAMIS procedure SCRR IAVAIL is to determine instructor availability for classroom instruction. The basic information from which availability is calculated is stored in the RAMIS instructor file MODINST.

Actual classroom instruction time by course is recorded and entered into the DOTS data base on a weekly bases. In addition to the weekly totals, quarter-to-date and year-to-date totals are maintained. SCRR IAVAIL computes the number of days between the first data entry (the first day of the current fiscal year) and the last data entry, and divides this number into 365. The resulting factor (FAC) is multiplied by the year-to-date total classroom instruction hours to project annual classroom instruction time for each course. If no classroom instruction time has been recorded to date by an instructor, a default value of one (1) hour is entered. SCRR IAVAIL sums the projected annual instruction time for all courses by instructor. Output is written on FILE IAVAIL. The record format for FILE IAVAIL is shown below:

FIELD NAME	INST NAME	AVAIL HRS.
TYPE	A	I
LENGTH	16	4
RELATIVE POS.	1-16	17-20

SCRR CRSE DESCRIPTION. The purpose of the RAMIS procedure SCRR CRSE is to record the convening frequency and average class size for each course. The required data are stored in the RAMIS course file MODCOURSE.

SCRR CRSE first calculates average class size by multiplying class capacity by percent utilization. Convening frequency and class size are recorded by course. Output is written on FILE CRSE. The record format for FILE CRSE is shown below:

FIELD NAME	CDP NO.	CLASS SIZE	CONV
TYPE	A	I	I
LENGTH	4	3	I
RELATIVE POS.	1-4	5-7	8-10

RAMSCRR EXEC FLOWCHART




FIGURE IV-3

RAMSCRR PROGRAM LISTINGS

RAMSCRR EXEC
VP/CSS

```

LTYPE OFF
&STACK KT
FILEDEF 4 DSK FILE INST RE F LR 25
ATTACH RAMIS ALL BRIEF
EXEC RAMISIN SCRR INST
FILEDEF 4 DSK FILE IAVAIL RE F LR 20
EXEC RAMISIN SCRR IAVAIL
FILEDEF 4 DSK FILE CRSE RE F LR 10
EXEC RAMISIN SCRR CRSE
FILEDEF 4 DSK FILE FACIL RE F LR 22
EXEC RAMISIN SCRR FACIL
FILEDEF 4 DSK FILE FAVAIL RE F LR 13
EXEC RAMISIN SCRR FAVAIL
DETACH RAMIS ALL BRIEF

```

SCRR INST (RAMIS PROCEDURE)

```

DEFINE
FILE MODCOURSE
AVG&CLAS/I3 = (CAP1 * UCAP * .01) + .5
NO&INST/I3 = MAX (1.0, (AVG&CLAS / SIR) + .5)
TOT&HRS = NO&INST * CHRS
FLAG/I1 = ASN
END
TABLE
FILE MODCOURSE
STORE TOT&HRS AND FLAG BY CDP BY SIR BY NME
IF DEL IS 1
RUN
FILE MODCOURSE
SUM ASN AND HOLD BY CDP BY SIR
END
DEFINE
FILE HOLD
INST&HRS/F5.1 = TOT&HRS / ASN
END
TABLE
FILE HOLD
SUM INST&HRS AND SAVE BY CDP BY NME
IF FLAG IS-MORE-THAN 0
IF NME IS-NOT '
END

```

368

TABLE IV-4

IV-12

SCRR FACIL (RAMIS PROCEDURE)

TABLE
FILE MODFACIL
PRINT REQHRS AND SAVE BY CDP BY BLDG BY RM
END

SCRR FAVAIL (RAMIS PROCEDURE)

TABLE
FILE MODFACIL
SUM FST*AVHRS AND SAVE BY BLDG BY RM
END

SCRR IAVAIL (RAMIS PROCEDURE)

DEFINE
FILE MODINST
DAYS/14 = YMD (LDTE, 750701)
FAC/F4.1 = 365 / DAYS
AVAIL / 14 = MAX ((FAC * YTD), 1)
END
TABLE
FILE MODINST
SUM AVAIL AND SAVE BY NME
IF TT IS A1
END

SCRR CRSE (RAMIS PROCEDURE)

DEFINE
FILE MODCOURSE
CLASIZE/13 = (CAP1 * UCAP * .01) + .5
END
TABLE
FILE MODCOURSE
PRINT CLASIZE AND CONV1 AND SAVE BY CDP
IF DEL IS 1
END

TABLE IV-4 (CONTINUED)

BLANK EXEC DESCRIPTION

MPS III linear programming software requires that variable names should be eight characters or less in length and also should not contain embedded blanks. Building and room numbers are stored in the data base as two separate fields - a five character building name and a three character room name. Concatenation of these two names will result in a variable containing embedded blanks if the building name is less than five characters.

The purpose of the executive BLANK is to delete all embedded blank characters in the eight character facility designation contained in the files FILE FACIL and FILE FAVAIL.

Initial statements of BLANK EXEC suppress all terminal output and specify libraries to be searched upon execution of subsequent PLI load commands. The input file FAVAIL for the PLI program BLANK is identified as FILE FAVAIL and the PLI program BLANK is executed. Then the input file FACIL for the PLI program CONCAT is identified as FILE FACIL and CONCAT is executed.

BLANK PLI DESCRIPTION. The input file is FILE FAVAIL. The first eight characters of each thirteen character record are the building number and the room number. BLANK reads each record and determines the index (I) of the first blank occurring in the building number. The first I-1 characters of the record are then substituted for the building number in the eight character building/room designation. The room number from the input record is then concatenated to the I-1 character building number in the output record. The output record which now contains no embedded blanks is then substituted for the input record in FILE FAVAIL.

CONCAT PLI DESCRIPTION. The only difference between CONCAT and BLANK is the name of the input file and the input file record format. CONCAT removes embedded blanks from the eight character building/room designator located in position five of each 22 character record in FILE FACIL.

BLANK EXEC FLOWCHART




FIGURE IV-4

CHART TITLE - PROC BLANK OPTIONS (MAIN)




FIGURE IV-4 (CONTINUED)

372

IV-16

BLANK PROGRAM LISTINGS

BLANK EXEC
 VP/CSS

```
&STACK KT
&TYPE OFF
GLOBAL MACLIB
GLOBAL TXTLIB
GLOBAL LNKLIB
GLOBAL TXTLIB PLILIB SYSLIB
GLOBAL LNKLIB PLILIB SYSLIB
FILEDEF FAVAIL DSK FILE FAVAIL RECFM F LRECL 12
LOAD BLANK (CLEAR LIBE) PLILIB
START
FILEDEF FACIL DSK FILE FACIL RE F LR 22
LOAD CONCAT (CLEAR LIBE) PLILIB
START
```

TABLE IV-5

INPUT LISTING		AUTOFLOW CHART SET - FINAL	PL/I - BLANK - FLOWCHARTS
PL/I MODULE	ILIST,NANSQ,SOURCEQ1		
CARD NO	****	CONTENTS	****
1	OPTION PACKIF,COMPRESS		00000100
2	BLANK: PROC OPTIONS (MAIN) :		00000200
3	/* READ FILE PAVAIL & ELIM EMBEDDED BLANKS FROM BLDG/RN */		00000300
4			00000400
5	DECLARE (IREC,OREC) CHAR (13),		00000500
6	BLDG CHAR (5) DEF IREC POS (1),		00000600
7	RN CHAR (3) DEF IREC POS (6),		00000700
8	RLDGRM CHAR (8) DEF OREC POS (1);		00000800
9			00000900
10	BEGIN:		00001000
11	OPEN FILE (PAVAIL) RECCRD UPDATE;		00001100
12	ON ENDFILE (PAVAIL) GO TO FIN;		00001200
13			00001300
14	LOOP:		00001400
15	READ FILE (PAVAIL) INTO (IREC) :		00001500
16	OREC = IREC :		00001600
17	PTR = INDEX (BLDG, ' ') :		00001700
18	IF PTR = 0 THEN PTR = 6 :		00001800
19	PTR = PTR - 1 :		00001900
20	RLDGRM = SUBSTR (BLDG,1,PTR) RN :		00002000
21	REWRITE FILE (PAVAIL) FROM (OREC) :		00002100
22	GO TO LOOP :		00002200
23			00002300
24	FIN :		00002400
25	CLOSE FILE (PAVAIL) :		00002500
26	END BLANK :		00002600

TABLE IV-5 (CONTINUED)


INTERFACE (IF1, IF2, IF3, and IF4) EXECS OVERVIEW

The purpose of the four interface executives IF1, IF1, IF3, and IF4 is to create a card image input data file to be processed by the MPS III linear programming routines. The linear programming input data file consists of data cards that are grouped according to data types or function. Each such group is called a segment. A segment is introduced and identified in the file by an indicator card containing the segment name. Data cards containing the data for the segment follow the indicator card.

The first card in the input data file is a NAME card containing the file name FTCNORVA. The file FTCNORVA contains ROWS, COLUMNS, RHS and BOUNDS segments. The purpose of each segment is defined below:

- A. ROWS Segment: defines row names and types. The NAME card and the ROWS segment is generated by IF1 EXEC.
- B. COLUMNS Segment: defines column names and matrix coefficients. The COLUMNS segment is generated by IF2 EXEC.
- C. RHS Segment: defines right-hand-side names and coefficients. The RHS segment is generated by IF3 EXEC.
- D. BOUNDS Segment: defines the column bounds set. The BOUNDS segment is generated by IF4 EXEC.

The organization of the LP data input file FTCNORVA is shown below.



370

DATA BASE INTERFACE EXEC FLOWCHART




FIGURE IV-5

IF1 EXEC DESCRIPTION

The purpose of IF1 EXEC is to generate both the file name card and the ROW segment of the LP data file. The segment consists of a ROWS indicator card followed by one ROW data card for each row to be defined. The ROW data card contains both the type (N = unconstrained row, for the objective function; or L = less-than-or-equal-to row, for all other rows in the SCRR model LP input matrix) and the row name. One row is defined for each specific resource requirement. The row name will be either an instructor name or a facility name. The ROW data card format is shown below:

CARD COLUMNS	2	5-12
DATA CONTENTS	L or N	ROW NAME

Initial IF1 EXEC statements suppress all terminal output. Then Data Set Reference Numbers (DSRN) are associated with each of the input and output files as follows:

	<u>DSRN</u>	<u>FILENAME</u>	<u>FILETYPE</u>
Input	1	FILE	IAVAIL
	2	FILE	FAVAIL
Output	6	FILE	IF1

Then IF1 FORTRAN IS executed.

IF1 FORTRAN DESCRIPTION. IF1 FORTRAN first writes the LP input file NAME card, the ROWS segment indicator card, and the objective function ROW data card on output file FILE IF1. Then the first eight characters of each instructor name are read from FILE IAVAIL. One ROW data card image is written on FILE IF1 for each instructor name. Each ROW data card image has an L in column 2 and the instructor names in columns 5 - 12. After the last instructor name has been read from FILE IAVAIL and a corresponding data card written on FILE IF1, IF1 FORTRAN reads facility names from FILE FAVAIL and creates a ROW data card for each facility on FILE IF1. IF1 FORTRAN concludes by writing the COLUMNS segment indicator card as the final card image on FILE IF1.

CHART TITLE - PROCEDURES




FIGURE IV-6

AUTOFLOW CHART SET - FINAL -BFI- FLOWCHARTS

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

REAL*8 A(2)
99  FORMAT ('NAME',10X,'FTCNDORVA'/'ROWS'/' N THRU PUT')
100  FORM / (AB,8X,I4)
101  FORMAT (' L ',AB)
102  FORMAT (AB,I5)
103  FORMAT (' L ',AB)
104  FORMAT ('COLUMNS')
    
```

FIGURE IV-6 (CONTINUED)

IF1 PROGRAM LISTINGS

IF1 EXEC
 VP/CSS

 E OFF
STACK KT
FILEDEF 1 DSK FILE IAVAIL
FILEDEF 2 DSK FILE FAVAIL
FILEDEF 6 DSK FILE IF1 RE F LR 80
RUN IF1

TABLE IV-6

INPUT LISTING		AUTOFLOW CHART SET - FINAL		-1F1- FLOWCHARTS
FORTRAN MODULE		(LIST, NAME, SOURCE, SEQ)		
CARD NO	****	CONTENTS		****
1		REAL*8 A(2)		00000100
2				00000200
3	C	C**GENERATE NAME & ROW DATA FOR LP INPUT		00000300
4	C			00000400
5		WRITE (6,99)		00000500
6	99	FORMAT ('NAME',10X,'FTCNORVA','ROWS',' M THRUPUT')		00000600
7	5	READ (1,100,END = 10) A		00000700
8	100	FORMAT (A8,BX,14)		00000800
9		WRITE (6,101) A(1)		00000900
10	101	FORMAT (' L ',A8)		00001000
11		GO TO 5		00001100
12	10	READ (2,102,END = 15) A		00001200
13	102	FORMAT (A8,15)		00001300
14		WRITE (6,103) A(1)		00001400
15	103	FORMAT (' L ',A8)		00001500
16		GO TO 10		00001600
17	15	WRITE (6,104)		00001700
18	104	FORMAT ('COLUMNS')		00001800
19		STOP		00001900
20		END		00002000

TABLE IV-6 (CONTINUED)

IF2 EXEC DESCRIPTION.

The purpose of IF2 EXEC is to generate the COLUMN segment of the LP data file. The COLUMN segment consists of a COLUMNS indicator card followed by at least one COLUMN data card image for each course in the RAMIS course file MODCOURSE. Each COLUMN data card image must contain the column name (course CDP number), the row name (instructor or facility name), and the matrix element associated with that column and row. A second row name and matrix element on the same COLUMN card is optional. The COLUMN data card format is shown below:

CARD COLUMNS	5-12	15-22	23-36	40-47	50-61
DATA CONTENTS	COLUMN NAME	ROW NAME	MATRIX ELEMENT	ROW NAME	MATRIX ELEMENT

OPTIONAL

Initial IF2 EXEC statements suppress all terminal output. Then Data Set Reference Numbers (DSRN) are associated with each of the input and output files as follows:

	<u>DSRN</u>	<u>FILENAME</u>	<u>FILETYPE</u>
Input	1	FILE	INST
	2	FILE	FACIL
	3	FILE	CRSE
Output	6	FILE	IF2

Then INTERFAC FORTRAN is executed.

INTERFAC FORTRAN DESCRIPTION. INTERFAC FORTRAN formats and writes the COLUMN segment of the LP data file on file IF2 using the data contained in the three files FILE INST, FILE FACIL, and FILE CRSE. INTERFAC minimizes the size of the COLUMN segment by writing two row names and matrix elements on each COLUMN data card image written for columns which have two or more matrix elements.

After initializing a five column array and several indexing variables, the CDP number, instructor name and contact hours are read from FILE INST. The CDP number is compared with the last CDP number entered into column one of the array.

If the CDP numbers do not match, the CDP number, instructor name and contact hours are written in the first three columns of the next array row. If the CDP numbers match, the contents of column four are examined. If column four contains a zero, then the instructor name and contact hours are written in columns four and five. If column four is not zero, then the CDP number, instructor name and contact hours are written in the first three columns of the next row. After the last record from FILE INST has been read and entered into the array, the array contents are formatted and written on FILE IF2.

The array and indexing variables are then reset and the above procedure is repeated for FILE FACIL. After the last record of FILE FACIL has been read, the array contents are again formatted and written on FILE IF2.

FILE CRSE contains only one record for each CDP number. INTERFAC FORTRAN reads FILE CRSE, then formats and writes the CDP number and class size on FILE IF2.

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -INTERFAC- FLOWCHARTS

CHART TITLE - PROCEDURES




FIGURE IV-7

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -INTERFAC- FLOWCHARTS

CHART TITLE - PROCEDURES






FIGURE IV-7 (CONTINUED)

AUTOFLOW CHART SET - FINAL -INTERFAC- FLOWCHARTS

• READ AND FORMAT FILE
FACIL
• ADD FACIL
REQUIREMENTS TO LP
COL DATA



TAEG REPORT NO. 29

CHART TITLE - PROCEDURES

AUTOPLOW CHART SET - FINAL -INTERFAC- FLOWCHARTS




CHART TITLE - NON-PROCEDURAL STATEMENTS

AUTOPLOW CHART SET - FINAL -INTERFAC- FLOWCHARTS

```

REAL*8 A(13),M(100,5)/1500*0.0/
200  FORMAT (A4,AB,8X,P5.1)
201  FORMAT (4X,A4,6X,AB,9X,P5.1,3X,AB,9X,P5.1)
202  FORMAT (4X,A4,6X,AB,9X,P5.1,25X)
203  FORMAT (A4,AB,P6.1,4X)
204  FORMAT (4X,A4,6X,AB,8X,P6.1,3X,AB,8X,P6.1)
205  FORMAT (4X,A4,6X,AB,8X,P6.1,25X)
206  FORMAT (A4,I3,I3)
207  FORMAT (4X,A4,6X,'THRUPT',9X,I3)
  
```

FIGURE IV-7 (CONTINUED)

IF2 PROGRAM LISTINGS

IF2 EXEC
 VP/CSS

&TYPE OFF
&STACK KT
FILEDEF 1 DSK FILE INST
FILEDEF 2 DSK FILE FACIL
FILEDEF 3 DSK FILE CRSE
FILEDEF 6 DSK FILE IF2 RECFM F LRECL 80
RUN INTERFAC

TABLE IV-7

TAEG REPORT NO. 29

INPUT LISTING		AUTOFLOW CHART SET - FINAL		-INTERFAC- FLOWCHARTS	
FORTRAN MODULE		(LIST,NAMSQ,SOURCE)			
CARD NO	****	CONTENTS		****	
1		REAL*8 A(3),M(300,5)/1500*0.0/		00000100	
2		C**READ AND FORMAT FILE INST		00000200	
3		C**ADD INST REQUIREMENTS TO LP COL DATA		00000300	
4		IRC = 0		00000400	
5		IR = 1		00000500	
6		ASSIGN 5 TO IBR		00000600	
7	5	READ(1,200,END = 100) A		00000700	
8	200	FORMAT (A4,AB,8X,F5.1)		00000800	
9	10	IF (A(1) .EQ. M(1R,1)) GO TO 30		00000900	
10		IF (M(1R,1) .NE. 0.0) IR = IR + 1		00001000	
11	15	IRC=IRC + 1		00001100	
12		DO 20 I=1,3		00001200	
13	20	M(1R,I) = A(I)		00001300	
14		GO TO IBR, (5,320)		00001400	
15	25	IR = IR + 1		00001500	
16		GO TO 15		00001600	
17	30	IF (M(1R,4) .NE. 0.0) GO TO 25		00001700	
18		DO 35 I=2,3		00001800	
19	35	M(1R,I+2) = A(I)		00001900	
20		IR = IR + 1		00002000	
21		GO TO IBR, (5,320)		00002100	
22	100	IND = 1		00002200	
23	110	IF (M(IND,4) .EQ. 0.0) GO TO 120		00002300	
24		WRITE (6,201) (M(IND,I),I=1,5)		00002400	
25	201	FORMAT (4X,A4,6X,AB,9X,F5.1,3X,AB,9X,F5.1)		00002500	
26	115	IND = IND + 1		00002600	
27		IF (IND .GT. IRC) GO TO 300		00002700	
28		GO TO 110		00002800	
29	120	WRITE (6,202) (M(IND,I),I=1,3)		00002900	
30	202	FORMAT (4X,A4,6X,AB,9X,F5.1,25X)		00003000	
31		GO TO 115		00003100	
32		C**READ AND FORMAT FILE FACIL		00003200	
33		C**ADD FACIL REQUIREMENTS TO LP COL DATA		00003300	
34	300	IRC = 0		00003400	
35		IR = 1		00003500	
36		ASSIGN 320 TO IBR		00003600	
37		DO 310 I=1,300		00003700	
38		DO 310 J=1,5		00003800	
39	310	M(I,J) = 0.0		00003900	
40	320	READ (2,203,END = 350) A		00004000	
41	203	FORMAT (A4,AB,F6.1,4X)		00004100	
42		GO TO 10		00004200	
43	350	IND = 1		00004300	
44	360	IF (M(IND,4) .EQ. 0.0) GO TO 370		00004400	
45		WRITE (6,204) (M(IND,I),I=1,5)		00004500	
46	204	FORMAT (4X,A4,6X,AB,9X,F6.1,3X,AB,8X,F6.1)		00004600	
47	365	IND = IND + 1		00004700	
48		IF (IND .GT. IRC) GO TO 400		00004800	
49		GO TO 360		00004900	
50	370	WRITE (6,205) (M(IND,I),I=1,3)		00005000	
51	205	FORMAT (4X,A4,6X,AB,9X,F6.1,25X)		00005100	
52		GO TO 365		00005200	
53		C**READ AND FORMAT FILE CRSE		00005300	
54		C**ADD OPJ FUNC COEFF TO LP COL DATA		00005400	
55	400	READ (3,206,END = 405) A		00005500	
56	206	FORMAT (A4,I3,I3)		00005600	
57		WRITE (6,207) (A(I),I=1,2)		00005700	
58	207	FORMAT (4X,A4,6X,THRUPT,9X,I3)		00005800	
59		GO TO 400		00005900	
60	405	STOP		00006000	
61		END		00006100	

TABLE IV-7 (CONTINUED)

SCRRSORT EXEC DESCRIPTION

INTERFAC FORTRAN first writes instructor data by course, then facility data by course, and finally course data by course on FILE IF2. The purpose of SCRRSORT is to sort FILE IF2 by course thereby combining all records associated with each course on FILE IF2.

SCRRSORT EXEC utilizes the NCSS SORT command which moves the records from FILE IF2 to .FILE IF2 arranging them in ascending order according to sort key fields 5 - 8 which contain the course CDP number. The filename .FILE is then changed to FILE using the NCSS ALTER command.

SCRRSORT PROGRAM LISTING

SCRRSORT EXEC
VP/CSS

```
&TYPE OFF
&STACK 5 8
SORT FILE IF2 (BRIEF)
ERASE FILE IF2
ALTER .FILE IF2 P FILE * *
```

TABLE IV-8

IF3 EXEC DESCRIPTION

The purpose of IF3 EXEC is to generate the RHS segment of the LP data file. The RHS segment consists of a RHS indicator card followed by RHS data card images which contain the RHS vector name and RHS elements. RHS elements are identified by row name (instructor or facility name). The RHS data card format is the same as the COLUMN data card format.

Initial IF3 EXEC statements suppress all terminal output. Then DSRN's are specified for each of the input and output files as follows:

	<u>DSRN</u>	<u>FILENAME</u>	<u>FILETYPE</u>
Input	1	FILE	IAVAIL
	2	FILE	FAVAIL
Output	6	FILE	IF3

Then IF3 FORTRAN is executed.

IF3 FORTRAN DESCRIPTION. IF3 FORTRAN first writes the RHS indicator card on the output file FILE IF3. Then two records each containing an instructor name and available hours are read from FILE IAVAIL and are formatted to form a single RHS data card, which is written on FILE IF3. After the last record is read from FILE IAVAIL, two records each containing a facility name and available hours are read from FILE FAVAIL and are formatted to form a single RHS data card, which is also written on FILE IF3. The process is repeated until all records are read from FILE FAVAIL.

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -IF3- FLOWCHARTS

CHART TITLE - PROCEDURES




FIGURE IV-8

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -IF3- FLOWCHARTS

CHART TITLE - NON-PROCEDURAL STATEMENTS

```
REAL*8 A(2),B(2)
99      FORMAT ('RH5')
100     FORMAT (A8,8X,I4)
101     FORMAT (4X,'AVAIL',5X,A8,8X,I4,5X,A8,8X,I4)
102     FORMAT (4X,'AVAIL',5X,A8,8X,I4)
103     FORMAT (A8,I5)
```

FIGURE IV-8 (CONTINUED)

IF3 PROGRAM LISTINGS

IF3 EXEC
 VP/CSS

&TYPE OFF
&STACK KT
FILEDEF 1 DSK FILE IAVAIL
FILEDEF 2 DSK FILE FAVAIL
FILEDEF 6 DSK FILE IF3 RE F LR 80
RUN IF3

TABLE IV-9

TAEG REPORT NO. 29

INPUT LISTING		AUTOFLOW CHART SET - FINAL		-IF3- FLOWCHARTS
FORTRAN MODULE	(LIST, NAME, SOURCE, SEQ)			
CARD NO	*****	CONTENTS	*****	
1	REAL*8 A(2),B(2)		00000100	
2	C		00000200	
3	C**GENERATE RHS DATA SECTION		00000300	
4	C FILE 1 = FILE 1AVAIL		00000400	
5	C FILE 2 = FILE 2AVAIL		00000500	
6	C FILE 3 = FILE 3F3		00000600	
7	C		00000700	
8	WRITE (6,99)		00000800	
9	99 FORMAT ('RHS')		00000900	
10	5 READ (1,100,END = 15) A		00001000	
11	100 FORMAT (A8,8X,14)		00001100	
12	READ (1,100,END = 10) B		00001200	
13	WRITE (6,101) A,B		00001300	
14	101 FORMAT (4X,'AVAIL',5X,A8,8X,14,5X,A8,8X,14)		00001400	
15	GO TO 5		00001500	
16	10 WRITE (6,102) A		00001600	
17	102 FORMAT (4X,'AVAIL',5X,A8,8X,14)		00001700	
18	15 READ (2,103,END = 25) A		00001800	
19	103 FORMAT (A8,15)		00001900	
20	READ (2,103,END = 20) B		00002000	
21	WRITE (6,101) A,B		00002100	
22	GO TO 15		00002200	
23	20 WRITE (6,102) A		00002300	
24	25 STOP		00002400	
25	END		00002500	

TABLE IV-9 (CONTINUED)

IF4 EXEC DESCRIPTION

The purpose of IF4 EXEC is to generate the BOUNDS segment of the LP data input. The BOUNDS segment consists of a BOUNDS indicator card followed by BOUNDS data card images that contain lower bounds on the number of annual course convenings for each course. The upper bound is automatically set to $+\infty$. The BOUNDS data card format is shown below:

CARD COLUMN	2-3	5-9	15-22	25-36
DATA CONTENTS	LO	SCHED	COLUMN NAME	BOUND VALUE

Initial IF4 EXEC statements suppress all terminal output. Then DSRN's are specified for the input and output files as follows:

	<u>DSRN</u>	<u>FILENAME</u>	<u>FILETYPE</u>
Input	1	FILE	CRSE
Output	6	FILE	IF4


Then, IF4 FORTRAN is executed.

IF4 FORTRAN DESCRIPTION. IF4 FORTRAN first formats the BOUNDS indicator card on FILE IF4. Then the course CDP numbers and the number of annual course convenings are read from each record of FILE CRSE. The record is reformatted and written on FILE IF4. IF4 FORTRAN concludes by formatting an ENDATA card on FILE IF4.

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -IF4- FLOWCHARTS

CHART TITLE - PROCEDURES



AUTOFLOW CHART SET - FINAL -IF4- FLOWCHARTS

CHART TITLE - NON-PROCEDURAL STATEMENTS

	REAL*8 A(2)
99	FORMAT ('BOUND\$')
100	FORMAT ('A4,3X,13')
101	FORMAT ('1 LO SCHED',5X,A4,13X,13')
192	FORMAT ('ENDATA')

FIGURE IV-9

IF4 PROGRAM LISTINGS

IF4 EXEC
 VP/CSS

&TYPE OFF
&STACK KT
FILEDEF 1 DSK FILE CRSE
FILEDEF 6 DSK FILE IF4 RE F LR 80
RUN IF4

TABLE IV-10

TAEK REPORT NO. 29

INPUT LISTING		AUTOFLOW CHART SET - FINAL -IF4- FLOWCHARTS	
FORTRAN MODULE (LIST,HAMSQ,SOURCEQ)			
CARD NO	*****	CONTENTS	*****
1	REAL*8 A(2)		00000100
2	C		00000200
3	C**GENERATE BOUNDS DATA SECTION		00000300
4	C FILE 1 = FILE CRSE		00000400
5	C FILE 6 = FILE IF4		00000500
6	C		00000600
7	WRITE (6,99)		00000700
8	99 FORMAT ('BOUNDS')		00000800
9	5 READ (1,100, END = 10) A		00000900
10	100 FORMAT (A4,3X,13)		00001000
11	WRITE (6,101) A		00001100
12	101 FORMAT (' LD SCHED',5X,A4,13X,13)		00001200
13	GO TO 5		00001300
14	10 WRITE (6,192)		00001400
15	192 FORMAT ('ENDATA')		00001500
16	STOP		00001600
17	END		00001700

TABLE IV-10 (CONTINUED)

COMB EXEC DESCRIPTION

The purpose of COMB EXEC is to combine the four output files created by the interface executives into a single input file suitable for processing by MPS III/OL.

COMB EXEC first uses the NCSS command ERASE to delete the existing copy of the file MATRIX1 DATA from writable disk. Then MATRIX1 DATA is recreated using the NCSS command COMBINE which joins the four files FILE IF1, FILE IF2, FILE IF3 and FILE IF4 to form MATRIX1 DATA.

COMB PROGRAM LISTING

COMB EXEC
 VP/CSS

&TYPE OFF

ERASE MATRIX1 DATA

COMBINE MATRIX1 DATA P FILE IF1 P FILE IF2 P FILE IF3 P FILE IF4 P

TABLE IV-11

SCRR1 EXEC DESCRIPTION

The purpose of SCRR1 EXEC is to attach and initialize the MPS III/OL system and execute a series of Terminal Control Language (TCL) statements contained in the SCRR RUN file. MPS III is an advanced Mathematical Programming System (MPS) which has been designed to solve linear programming (LP) problems. The MPS III On-line System (MPS III/OL) is adapted for interactive use under VP/CSS, the National CSS, Inc. time-sharing system. TCL is similar to many computer programming languages (such as FORTRAN), but is oriented specifically to the solution of mathematical programming problems.

Upon entry, existing core size is checked. If core size is less than 320K, a message directing the user to SET CORE 320 is printed and the EXEC is terminated. If minimum core size requirements are met, SCRR1 EXEC then suppresses both offline print and terminal output commands contained within the MPS III/OL system. The file MPSOUT LISTING which contains a detailed record of the LP computational process is then erased. (MPSOUT LISTING is regenerated each time the SCRR model is executed). Output files for both the MPS III LP solution output and the SCRR model output are established by the FILEDEF commands.

The command ATTACH MPSIII accesses a VP/CSS system EXEC file that attaches the necessary disks, loads the Terminal Executor and requests information regarding the location of the scratch desk for work files, the sysin file filename, probfile names, card image filenames, and actfile names. Responses to these requests are stored in a special area of user storage called the CSS stack. The stack containing the MPS III file initialization information is generated by SCRR1 EXEC. The information is read from the stack each time the system EXEC requests file data. The file information is formed into an argument list and a START MPSIII TMLX command is issued. The system prompting messages,

MPS 'III, ON-LINE VERSION, READY
MPS COMMAND:

are then printed out at the terminal. At this point the RUN SCRR command, which has also been stacked, is executed. SCRR1 EXEC concludes by printing a message which explains how to obtain a listing of the SCRR model output.

SCRR RUN DESCRIPTION. The purpose of SCRR RUN is to calculate the LP optimal solution and the post-optimal sensitivity analysis for the problem formulated and written on the file MATRIX1 DATA. SCRR RUN is a series of TCL statements which control the execution sequence of the LP problem.

TITLE ' ' AND TERM OFF. These two TCL commands are used to suppress MPS III/OL printed output at the user's terminal.

SET XDONFS = 16. This command is used to alter the value of the MPS III/OL Communications Region (CR) cell XDONFS. XDONFS originally contained the address of the standard procedure which terminates MPS III/OL prior to filing the solution matrix when a no-feasible-solution condition is encountered during optimization. Altering the address of the XDONFS procedure to RUN program statement 16 enables the solution output to be filed for both optimal and non-feasible-solution conditions.

CALL ASSIGN FT04F001 FT04F001 COMM. This statement specifies that MPS III/OL output is to be written on the FORTRAN file 4 in communications format.

CALL PREPOUT FT04F001. This statement positions the communications file FT04F001 to the beginning of the area to receive data and opens that file for output.

CALL ASSIGN FT07F001 FT07F001 CARD. This statement specifies that FORTRAN file 7 is to be written in card-image format.

ROUTE SYSPRINT MPSOUT. This command causes the detailed record of the LP computational process to be written on the file MPSOUT LISTING. All MPS III/OL error messages (when an error condition is encountered) will be stored on MPSOUT LISTING and will not be printed at the terminal during model execution.

SET XDATA = FTCNORVA, XPBNAME = SCRR1. This instruction alters the value of the CR location referenced by the name XDATA to the input data set name FTCNORVA, and alters the value of the location XPBNAME to the problem file name SCRR1. This allows the files to be referenced later by control program statements. The location of both the input data set and the problem file is required by the CONVERT and SETUP procedures.

CALL CONVERT. CONVERT provides the basic means of problem input. The procedure reads the input data, converts them to packed binary format, and writes them on the PROBFIL. The PROBFIL is a disk storage unit that contains the internal representation of the LP problem. While the problem is being generated, comprehensive error checks are made, and the statistics of the model are calculated for use by the SETUP procedure.

SET XOBJ - THRUPUT, XRHS = AVAIL. This instruction alters the value of the XOBJ CR location to the name of the LP objective function THRUPUT, and alters the value of the location XRHS to the name of the right-hand-side vector AVAIL.

CALL SETUP, BOUND = SCHED, MAX. SETUP reads the LP problem created by CONVERT on PROBFIL. The SETUP procedure then analyzes the model's statistics, types of input/output devices, and solution strategy to be used. The available memory is dynamically allocated for efficient problem solution and all work files used by the computational procedures are produced. SETUP also determines the initial LP basic solution. The SETUP parameter, BOUND, indicates the name of the BOUND vector in the original input data. The MAX parameter calls for the maximization of the objective function. The procedure SETUP writes the following output on the file MPSOUT LISTING:

- a. Table of files that have been defined
- b. Storage allocation tables
- c. Table of statistics regarding the matrix variables.

CALL VARIFORM. VARIFORM is the main optimization procedure. It attempts to find a feasible solution, followed by an optimal solution. If the problem has no feasible solution, i.e., when requirements are larger than availability, an appropriate message is printed on MPSOUT LISTING and VARIFORM is terminated. Upon termination of VARIFORM, the control program branches to statement 16 which causes only the SOLUTION output to be written on FORTRAN file 4.

VARIFORM uses a composite algorithm and the revised simplex method. It progresses from the initial basis to the optimal basis by a series of vector interchanges; one vector is introduced into the basis and one is removed.

VARIFORM outputs on MPSOUT LISTING an iteration log which notes for each iteration number, the vector number removed from the basis, the vector number entered into the basis, the reduced cost of the incoming vector, and the sum of remaining infeasibilities or value of the objective function.

CALL SOLUTION FILE FT04F001 RSECTION, 2/4/7, CSECTION, 2/4/5/6. SOLUTION outputs in communications format a summary of the present LP problem and its current solution during the computational procedure if the solution is infeasible, or after the computational procedure if the solution is optimal. SOLUTION writes three arrays named SOLUTION, RSECTION and CSECTION on FORTRAN file 4. The SOLUTION array contains problem identification data. RSECTION array contains four data columns: row name (2), activity (4), slack activity (5), and upper limit (7). CSECTION array also contains four data columns: column name (2), activity (4), input cost (5), and lower limit (6).

CALL RANGE FILE FT04F001 RSECTION, 1/2/3/5, CSECTION, 2/3/4/5. Range is used post-optimally to generate and output an analysis of the current solution. The analysis includes:

- a. The effects of changes in class size on optimum convening levels.
- b. The impact on student throughput of changing the number of course convenings from optimum level, and the total range of course convenings for which the impact is valid.
- c. The impact on student throughput of modifying a resource level and the interval for which this input is valid.

These data are tabulated in five arrays named RANGE, SECTION1, SECTION2, SECTION3, and SECTION4 and written on FORTRAN file 4. RANGE is a single row section containing information identifying the problem, model, and progress of the computation. SECTION1 and SECTION3 are row arrays each containing seven columns of data: row name (1), upper and lower activity range (2), unit cost associated with both upper and lower range value (3), and the limiting process associated with each range value (5). SECTION2 and SECTION4 are column arrays which include nine columns of data: seven columns are identical to those contained in the row arrays; column arrays also contain upper and lower cost values (4).

SKIP 1. This statement causes the next statement in the run file to be bypassed.

CALL PREPIN FT04F001. This statement positions the communications file FT04F001 to the start of the data and opens the file for input.

CSS ALTER SCRRFORM.....CALL USERPROC.....CSS ALTER USERPROC.....This series of statements changes the name of SCRRFORM LNKLIB to USERPROC LNKLIB, executes USERPROC, then changes the LNKLIB file name back to SCRRFORM.

SCRRFORM LNKLIB contains both the relocatable object program for SCRRFORM FORTRAN and the READCOMM library. READCOMM (Read Communications Format) transfers to the SCRRFORM FORTRAN procedures the data previously filed in MPS III Communications format.

EXIT. The EXIT command terminates the MPS III/OL run and returns the user to the VP/CSS command level. The system responds to the EXIT command by printing out "MPSIII TERMINATING".

SCRRFORM FORTRAN DESCRIPTION. The purpose of SCRRFORM FORTRAN is to read the MPS III/OL output which has been filed on FORTRAN file 4 in communications format, reformat the LP output, and write the results on file SCRR OUTPUT.

All MPS III/OL filed outputs are written in communications format, which cannot be read directly by the FORTRAN READ statement. Read Communications Format (READCOMM) subroutines are required to retrieve and transfer the data contained in arrays filed in Communications Format by MPSIII. SCRRFORM utilizes three READCOMM subroutines:

POSITN - positions a communications format file to a specified array.

ARRAY - initializes READCOMM to read the data contained in the array.

VECTOR - transfers a row of elements from the filed array to the calling program.

These subroutines act as an interface between the FORTRAN procedures under the control of the MPSIII executor and the Communications Format subroutines of MPSIII.

Upon entry, SCRRFORM initializes several variables, vectors and arrays. Then the RSECTION array is read from FORTRAN file 4 into the first four columns of the array R. After the last row vector has been read from RSECTION, SCRRFORM searches file 4 for the row-related arrays created by the MPSIII sensitivity analysis, SECTION1 and SECTION3. SECTION1 contains data for rows at their upper limit; SECTION3 contains data for rows at an intermediate level. If the current problem has an infeasible solution, the arrays will not exist, and the program branches to the resource (row) output format routine. If the sensitivity analysis has been performed, SCRRFORM first reads the data from SECTION1 array one row at a time. Row names are stored in column one of the array R and in column one of SECTION1. The row names in both arrays are in sorted sequence. Each row name from SECTION1 is compared with the row name in R until a match is found. Then columns two through seven of SECTION1 are read into columns five through ten of array R. The process is repeated until all rows from SECTION1 have been read into R. SCRRFORM then positions file 4 to the SECTION3 array. Row names are matched and SECTION3 data is transferred to the array R. After the last row has been read from SECTION3 and entered into R, each row of R will have ten columns of data associated with it. SCRRFORM then branches to the resource (row) output format routine, which writes column headings, and reformats the contents of R on output file SCRR OUTPUT.

After the last row of resource data has been formatted and written on the output file, SCRRFORM branches to the column section routines. Data from CSECTION are transferred to a twelve column array C, and data from SECTION2 and SECTION4 arrays (if the sensitivity analysis has been performed) are added to C, using an algorithm similar to that used to construct the row output data. Column headings are generated and the course (column) data output is appended to the resource data output on the file SCRR OUTPUT.

SCRR1 EXEC FLOWCHART




FIGURE IV-10

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

-SCNRFORM- FLOWCHARTS

PAGE 01

CHART TITLE - SUBROUTINE FORMAT





FIGURE IV-10 (CONTINUED)

407


CHART TITLE - SUBROUTINE FORMAT



408 FIGURE IV-10 (CONTINUED)

CHART TITLE - SUBROUTINE FORMAT

GET CSECTION ARRAY



GET SECTION2 ARRAY




FIGURE IV-10 (CONTINUED)

CHART TITLE - SUBROUTINE FORMAT




FIGURE IV-10 (CONTINUED)

CHART TITLE - SUBROUTINE FORMAT





FIGURE IV-10 (CONTINUED)

CHART TITLE - SUBROUTINE FORMAT




PAGE 07

FORMAT COURSE OUTPUT



CHART TITLE - SUBROUTINE FORMAT



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

-SCRRFORM- FLOWCHARTS

PAGE 09

CHART TITLE - SUBROUTINE FORMAT








TABLE IV-10 (CONTINUED)

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -SCRRFORM- FLOWCHARTS

PAGE 11

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

REAL*8 A(1)/990.0,0,NAME,RIS0,101/5000*0.0,C1150,121/1800*0.0/
REAL*8 SEC1/'SECTION1',RSEC/'RSECTION',CSEC/'CSECTION'/
REAL*8 SEC2/'SECTION2',SEC3/'SECTION3',SEC4/'SECTION4'/
INTEGER FILE/4/

500 FORMAT (51X,'RESOURCE THROUGHPUT'/ 12X,'ANNUAL    ANNUAL    ',
' HOURS    PERCENT    UTIL.    CHANGE    LIMITING'/1X,'RESOURCE',
' AVAIL.    UTIL.    UNDER',6X,'UTIL.    RANGE    PER UNIT ',
' VARIABLE'/ 12X,'(HRS)',5X,'(HRS)    UTILIZED',12X,'MINIMUM ',
' RESOURCES'/ 51X,'MAXIMUM    CHANGE')

501 FORMAT (1X,AB,2X,16,4X,16,4X,16,6X,14,3X,F0.1,3X,
F7.3,3X,AB/ 50X,F0.1,3X,F7.3,3X,AB)

502 FORMAT (1X,AB,2X,16,2(4X,16),6X,14,3X,F0.1,6X,'-INF',3X,AB/
50X,F0.1,3X,F7.3,3X,AB)

503 FORMAT (1X,AB,2X,16,2(4X,16),6X,14,3X,F0.1,3X,F7.3,3X,AB/
50X,F0.1,6X,'-INF',3X,AB)

520 FORMAT (1X,AB,2X,16,2(4X,16),6X,14,3X,F0.1,6X,'-INF',37'-AB/
50X,F0.1,6X,'-INF',3X,AB)

517 FORMAT (1X,AB,2X,16,2(4X,16),6X,14/' ')

504 FORMAT (1/' '/' '/' /42X,'ANNUAL THROUGHPUT CLASS'/2X,'COURSE',
' MAXIMUM CURRENT AVERAGE CONVEN CHANGE SIZE ',
' LIMITING'/ 2X,'CDP NO. ANNUAL SCHEDULED CLASS RANGE',
' PER COURSE RANGE VARIABLE'/ 12X,'CONVEN CONVEN ',
' SIZE MINIMUM CONVEN MINIMUM'/ 41X,'MAXIMUM ',
' CHANGE MAXIMUM')

505 FORMAT (3X,A4,4X,F0.1,2(6X,14),3(4X,F0.1),4X,AB/
37X,3(4X,F0.1),4X,AB)

506 FORMAT (3X,A4,4X,F0.1,2(6X,14),3(4X,F0.1),4X,AB/
37X,2(4X,F0.1),6X,'+INF',4X,AB)

507 FORMAT (3X,A4,4X,F0.1,2(6X,14),3(4X,F0.1),4X,AB/
37X,4X,F0.1,6X,'-INF',4X,F0.1,4X,AB)

508 FORMAT (3X,A4,4X,F0.1,2(6X,14),3(4X,F0.1),4X,AB/ 37X,4X,F0.1,
6X,'-INF',6X,'+INF',4X,AB)

509 FORMAT (3X,A4,4X,F0.1,2(6X,14),2(4X,F0.1),6X,'-INF',4X,AB/
37X,3(4X,F0.1),4X,AB)

510 FORMAT (3X,A4,4X,F0.1,2(6X,14),2(4X,F0.1),6X,'-INF',4X,AB/
37X,4X,F0.1,6X,'+INF',4X,AB)

511 FORMAT (3X,A4,4X,F0.1,2(6X,14),6X,'-INF',2(4X,F0.1),4X,AB/
37X,3(4X,F0.1),4X,AB)

512 FORMAT (3X,A4,4X,F0.1,2(6X,14),6X,'-INF',2(4X,F0.1),4X,AB/
37X,2(4X,F0.1),6X,'+INF',4X,AB)

513 FORMAT (3X,A4,4X,F0.1,2(6X,14),6X,'-INF',2(4X,F0.1),4X,AB/
37X,4X,F0.1,6X,'-INF',4X,F0.1,4X,AB)

514 FORMAT (3X,A4,4X,F0.1,2(6X,14),6X,'-INF',2(4X,F0.1),4X,AB/
37X,4X,F0.1,6X,'-INF',6X,'+INF',4X,AB)

515 FORMAT (3X,A4,4X,F0.1,2(6X,14),6X,'-INF',4X,F0.1,6X,'-INF',
4X,AB/ 37X,3(4X,F0.1),4X,AB)

516 FORMAT (3X,A4,4X,F0.1,2(6X,14),6X,'-INF',4X,F0.1,6X,'-INF',
4X,AB/ 37X,4X,F0.1,6X,'-INF',4X,F0.1,4X,AB)

518 FORMAT (3X,A4,4X,F0.1,2(6X,14)/' ')

519 FORMAT (1000 READCOM END OF FILE ERROR|||||)

```

FIGURE IV-10 (CONTINUED)

IV-60 416

SCRR1 PROGRAM LISTINGS

SCRR1 EXEC
 VP/CSS

&TYPE OFF
ROUTE E REMOTE
ERASE MPSOUT LISTING
FILEDEF FT04F001 DSK FILE FT04F001
FILEDEF FT07F001 DSK SCRR OUTPUT RECFM UA BLKSIZE 132
&STACK KT
&STACK N
&BEGSTACK

&ENDSTACK
&STACK KT
&STACK MATRIX1
&BEGSTACK

FT04F001 FT07F001

Y
&ENDSTACK
&STACK RUN SCRR
ATTACH MPSIII ALL BRIEF
DETACH MPSIII ALL BRIEF
&PRI TO PRINT SCRR MODEL OUTPUT, TYPE:
&PRI P SCRR OUTPUT
&EXIT

TABLE IV-12

TAEG REPORT NO. 29

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-SCARFORM- FLOWCHARTS

FORTRAN MODULE I(LIST,NAMSQ,SOURCEQ)

CARD NO	*****	CONTENTS	*****
1		SUBROUTINE FORMAT	00000100
2		REAL*8 A(1)/9*0.0/,NAME,R(500,10)/5000*0.0/,C(150,12)/1800*0.0/	00000200
3		REAL*8 SEC1/'SECTION1'/,RSEC/'RSECTION'/,CSEC/'CSECTION'/	00000300
4		REAL*8 SEC2/'SECTION2'/,SEC3/'SECTION3'/,SEC4/'SECTION4'/	00000400
5		INTEGER FILE/4/	00000500
6	C		00000600
7	C	GET RSECTION ARRAY	00000700
8	C		00000800
9		CALL POSITN(FILE,I,2)	00000900
10		CALL ARRAY(FILE,I,NAME,N)	00001000
11		IF (I .EQ. 1) GO TO 600	00001100
12		IR = 1	00001200
13		IRCTA = 0	00001300
14	5	CALL VECTOR (FILE,I,A)	00001400
15		IF (I .EQ. 1) GO TO 20	00001500
16		IRCTA = IRCTA + 1	00001600
17		DO 10 I=1,4	00001700
18	10	R(IR,I) = A(I)	00001800
19		IR = IR + 1	00001900
20		GO TO 5	00002000
21	C		00002100
22	C	GET SECTION1 ARRAY	00002200
23	C		00002300
24	20	CALL POSITN(FILE,I,5)	00002400
25		CALL ARRAY(FILE,I,NAME,N)	00002500
26		IF (I .EQ. 1) GO TO 200	00002600
27		IF (NAME .EQ. RSEC) GO TO 200	00002700
28		IF (NAME .NE. SEC1) GO TO 65	00002800
29	C		00002900
30	C	ADD SENSITIVITY ANALYSIS DATA TO RESOURCE MATRIX	00003000
31	C		00003100
32	25	IR = 1	00003200
33	30	CALL VECTOR(FILE,I,A)	00003300
34		IF (I .EQ. 1) GO TO 60	00003400
35		DO 40 I=IR,IRCTA	00003500
36		IF (A(I) .EQ. R(I,I)) GO TO 50	00003600
37	40	IR = IR + 1	00003700
38	50	DO 55 I = 1,6	00003800
39	55	R(IR,4+I) = A(1+I)	00003900
40		IR = IR + 1	00004000
41		GO TO 30	00004100
42	60	IF (NAME .NE. SEC1) GO TO 200	00004200
43		IF (NAME .EQ. SEC3) GO TO 200	00004300
44	C		00004400
45	C	GET SECTION3 ARRAY	00004500
46	C		00004600
47	65	IA = 7	00004700
48		IF (NAME .EQ. SEC1) GO TO 68	00004800
49		IA = 6	00004900
50	68	CALL POSITN(FILE,I,IA)	00005000
51		CALL ARRAY(FILE,I,NAME,N)	00005100
52		IF (I .EQ. 1) GO TO 600	00005200
53		GO TO 25	00005300
54	C		00005400
55	C	GET CSECTION ARRAY	00005500
56	C		00005600
57	70	CALL POSITN(FILE,I,3)	00005700
58		CALL ARRAY(FILE,I,NAME,N)	00005800
59		IF (I .EQ. 1) GO TO 600	00005900
60		IR = 1	00006000
61		IRCTC = 0	00006100
62	75	CALL VECTOR(FILE,I,A)	00006200
63		IF (I .EQ. 1) GO TO 90	00006300
64		IRCTC = IRCTC + 1	00006400
65		DO 80 I = 1,4	00006500
66	80	C(I,I) = A(I)	00006600
67		IR = IR + 1	00006700
68		GO TO 75	00006800
69	C		00006900
70	C	GET SECTION2 ARRAY	00007000
71	90	CALL POSITN(FILE,I,6)	00007100
72		CALL ARRAY(FILE,I,NAME,N)	00007200
73		IF (I .EQ. 1) GO TO 300	00007300
74		IF (NAME .EQ. CSEC) GO TO 300	00007400
75		IF (NAME .NE. SEC2) GO TO 130	00007500
76	C		00007600
77	C	ADD SENSITIVITY ANALYSIS DATA TO COURSE MATRIX	00007700
78	C		00007800
79	95	IR = 1	00007900
80	100	CALL VECTOR(FILE,I,A)	00008000
81		IF (I .EQ. 1) GO TO 150	00008100
82		DO 110 I = IR,IRCTC	00008200
83		IF (A(I) .EQ. C(I,I)) GO TO 120	00008300
84	110	IR = IR + 1	00008400
85	120	DO 125 I = 1,8	00008500
86	125	C(IR,4+I) = A(1+I)	00008600
87		IR = IR + 1	00008700
88		GO TO 100	00008800
89	130	CALL POSITN(FILE,I,5)	00008900
90		CALL ARRAY(FILE,I,NAME,N)	00009000
91		IF (I .EQ. 1) GO TO 600	00009100
92		IF (NAME .EQ. SEC2) GO TO 95	00009200
93	C		00009300
94	C	GET SECTION4 ARRAY	00009400
95	C		00009500
96	150	IF (NAME .EQ. SEC4) GO TO 300	00009600
97		CALL POSITN(FILE,I,4)	00009700
98		CALL ARRAY(FILE,I,NAME)	00009800
99		IF (NAME .EQ. SEC4) GO TO 95	00009900
100		IF (NAME .EQ. SEC3) GO TO 300	00010000
101		CALL POSITN(FILE,I,7)	00010100
102		CALL ARRAY(FILE,I,NAME)	00010200
103		IF (NAME .EQ. SEC4) GO TO 95	00010300
104		CALL POSITN(FILE,I,8)	00010400
105		CALL ARRAY(FILE,I,NAME)	00010500
106		IF (I .EQ. 1) GO TO 300	00010600
107		GO TO 95	00010700
108	E		00010800
109	C	FORMAT RESOURCE OUTPUT	00010900

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

-SCARFOM- FLOWCHARTS

[illegible]

TAEG REPORT NO. 29

INPUT LISTING		AUTOFLOW CHART SET - FINAL	-SCRRFORM- FLOWCHARTS
CARD NO	****	CONTENTS	****
222	375	WRITE(7,516) C(1R,1),C(1R,2),I4,I3,C(1R,6),C(1R,9),C(1R,9),	00022200
223		1C(1R,11),C(1R,12)	00022300
224	516	FORMAT (3X,A4,4X,F6.1,2(6X,I4),6X,'-INF',4X,F6.1,6X,'-INF',	00022400
225		14X,A8/ 37X,4X,F6.1,6X,'-INF',4X,F6.1,4X,A8)	00022500
226		GO TO 315	00022600
227	400	WRITE (7,518) C(1R,1),C(1R,2),I4,I3	00022700
228	518	FORMAT (3X,A4,4X,F6.1,2(6X,I4)/' ')	00022800
229		GO TO 315	00022900
230	600	WRITE (7,519)	00023000
231	519	FORMAT('*** READCOHM END OF FILE ERROR!!!!!!')	00023100
232		END	00023200

TABLE IV-12 (CONTINUED)

ASSIGN EXEC DESCRIPTION

The purpose of ASSIGN EXEC is to generate an instructor assignment listing which contains the following data for each instructor:

- o assigned courses
- o projected average class size
- o contact hour requirement per convening
- o scheduled convenings per year
- o total annual contact hour requirement per course
- o projected annual availability

Initial ASSIGN EXEC statements suppress all terminal output. Then DSRN's are associated with each of the input and output files as follows:

	<u>DSRN</u>	<u>FILENAME</u>	<u>FILETYPE</u>
Input	1	FILE	INST
	2	FILE	CRSE
Output	9	FILE	ASSIGN

After DSRN specification, ASSIGN1 FORTRAN is executed. ASSIGN1 FORTRAN output file FILE ASSIGN is then sorted by instructor using the NCSS SORT command. The sort key fields are 11-18. DSRN's are then reassigned as follows:

	<u>DSRN</u>	<u>FILENAME</u>	<u>FILETYPE</u>
Input	1	FILE	ASSIGN
	2	FILE	IAVAIL
Output	8	ASSIGN	LISTING

ASSIGN2 FORTRAN is then executed and instructions on how to obtain output are printed.

ASSIGN1 FORTRAN DESCRIPTION. The purpose of ASSIGN1 FORTRAN is to combine class size and convening data from FILE CRSE with each FILE INST record. FILE INST contains one record for each instructor assigned to a course. FILE CRSE contains one record for each course. Both files are sorted by CDP number.

ASSIGN1 reads the first record from both FILE INST and FILE CRSE. If both records contain the same CDP number, the data from both records are combined to form a single record which is written on FILE ASSIGN. The next record is then read from FILE INST. The CDP number is compared with the CDP number in the last record read from FILE CRSE. If they are identical, the data are combined and a single record is written on the output file. If the CDP numbers are not the same, the next record is read from FILE CRSE and the CDP comparison is repeated.

Records are read from both files, combined and rewritten on FILE ASSIGN until the last record is read from FILE INST.

ASSIGN2 FORTRAN DESCRIPTION. The purpose of ASSIGN2 FORTRAN is to combine instructor requirements and availability data and to format the data on the output file ASSIGN listing. Both input files FILE ASSIGN and FILE IAVAIL are sorted by instructor.

Upon entry, ASSIGN2 FORTRAN writes a heading on ASSIGN LISTING. Then the first record is read from FILE ASSIGN. Total contact hour requirements are calculated by multiplying the hours per convening by the number of convenings. The next record is read, total hours calculated, and the instructor name is compared with the instructor name of the prior record. If the names are different, availability is read from FILE IAVAIL, the former record is reformatted and written on ASSIGN LISTING, and the process is repeated.

If the names are identical, the first record is formatted and written on the output file, the next record read from FILE ASSIGN, and the instructor names are again compared. If the names are the same, the process is repeated. If the names are different, the former record is formatted and written on ASSIGN LISTING. Then availability is read from FILE IAVAIL, and a summary record, which includes total contact hours for all course assignments and total availability, is written on the output file.

Records are read from FILE ASSIGN, names compared, and output records written (format is a function of single vs. multiple assignments) until the last record is read from FILE ASSIGN.

ASSIGN EXEC FLOWCHART





FIGURE IV-11

CHART TITLE - PROCEDURES



AUTOFLOW CHART SET - FINAL

-ASSIGN1- FLOWCHARTS

PAGE 03

CHART TITLE - NON-PROCEDURAL STATEMENTS

```
REAL*8 A(3),B(3)
500  FORMAT (A4,A8,BX,F9.1)
501  FORMAT (A4,13,13)
502  FORMAT (A4,13,13,A8,F9.1)
```

FIGURE IV-11 (CONTINUED)

CHART TITLE - PROCEDURES





CHART TITLE - PROCEDURES



TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -ASSIGN2- FLOWCHARTS

PAGE 04

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

REAL*8 A(5),B(5),C(2)
100  FORMAT (1' INSTRUCTOR COURSE CLASIZE CONV HRS/CONV',
      ' TOT HRS AVAIL HRS'/' ----- '
      '-----')
99   FORMAT (A4,I3,I3,A8,F5.1)
101  FORMAT (2X,A8,4X,A4,5X,I3,4X,I3,5X,F5.1,4X,F6.1)
102  FORMAT (16X,A4,5X,I3,4X,I3,5X,F5.1,4X,F6.1)
104  FORMAT (A8,8X,I4)
105  FORMAT (2X,A8,4X,A4,5X,I3,4X,I3,5X,F5.1,4X,F6.1,4X,I4/)
106  FORMAT (49X,'-----'/43X,'TOT = ',F6.1,4X,I4/)

```

FIGURE IV-11 (CONTINUED)

ASSIGN PROGRAM LISTINGS

ASSIGN EXEC
 VP/CSS

&TYPE OFF
&STACK KT
FILEDEF 1 DSK FILE INST
FILEDEF 2 DSK FILE CRSE
FILEDEF 9 DSK FILE ASSIGN
RUN ASSIGN1
&STACK 11 18
SORT FILE ASSIGN (BRIEF)
ERASE FILE ASSIGN
ALTER .FILE ASSIGN P FILE * *
FILEDEF 1 DSK FILE ASSIGN
FILEDEF 2 DSK FILE IAVAIL
FILEDEF 8 DSK ASSIGN LISTING
RUN ASSIGN2
&PRI TO PRINT INSTRUCTOR ASSIGNMENTS, TYPE:
&PRI P ASSIGN LISTING

TABLE IV-13

TAEG REPORT NO. 29

INPUT LISTING		AUTOFLOW CHART SET - FINAL		-ASSIGN1- FLOWCHARTS
FORTRAN MODULE	(LIST,NAMSQ,SOURCEQ)			
CARD NO	****	CONTENTS		****
1		REAL*8 A(3),B(3)		00000100
2		C**COMBINES INST AND CRSE DATA INTO SINGLE FILE		00000200
3		C FILE 1 = FILE INST		00000300
4		C FILE 2 = FILE CRSE		00000400
5		C FILE 7 = FILE ASSIGN		00000500
6		C		00000600
7		READ (1,500) A		00000700
8	500	FORMAT (A4,A8,8X,F5.1)		00000800
9	10	READ (2,501, END = 25) B		00000900
10	501	FORMAT (A4,I3,I3)		00001000
11	15	IF (A(1) .EQ. B(1)) GO TO 20		00001100
12		GO TO 10		00001200
13	20	WRITE (9,502) A(1),B(2),B(3),A(2),A(3)		00001300
14	502	FORMAT (A4,I3,I3,A8,F5.1)		00001400
15		READ (1,500, END = 25) A		00001500
16		GO TO 15		00001600
17	25	STOP		00001700
18		END		00001800

INPUT LISTING		AUTOFLOW CHART SET - FINAL		-ASSIGN2- FLOWCHARTS
FORTRAN MODULE	(LIST,NAMSQ,SOURCEQ)			
CARD NO	****	CONTENTS		****
1		REAL*8 A(5),B(5),C(2)		00000100
2		C		00000200
3		C**FORMATS INST ASSIGNMENT DATA FOR OUTPUT		00000300
4		C FILE 1 = FILE ASSIGN		00000400
5		C FILE 2 = FILE IAVAIL		00000500
6		C FILE 8 = ASSIGN LISTING		00000600
7		C		00000700
8		WRITE (8,100)		00000800
9	100	FORMAT (1' INSTRUCTOR COURSE CLASIZE CONV MRS/CONV',		00000900
10		1' TOT MRS' AVAIL MRS'/'		00001000
11		1'-----')		00001100
12		READ (1,99) A(1),A(2),IA,A(4),A(5)		00001200
13	99	FORMAT (A4,I3,I3,A8,F5.1)		00001300
14		A(3) = IA		00001400
15		TA = A(3) * A(5)		00001500
16		TOT = TA		00001600
17	10	READ (1,99, END = 150) B(1),B(2),IB,B(4),B(5)		00001700
18		B(3) = IB		00001800
19		TB = B(3) * B(5)		00001900
20		IF (A(4) .NE. B(4)) GO TO 50		00002000
21		WRITE (8,101) A(4),A(1),A(2),IA,A(5),TA		00002100
22	101	FORMAT (2X,A4,8X,A4,5X,I3,4X,I3,5X,F5.1,4X,F6.1)		00002200
23	25	TOT = TOT + TB		00002300
24		DO 30 I=1,5		00002400
25	30	A(I) = B(I)		00002500
26		IA = IB		00002600
27		TA = TB		00002700
28		READ (1,99, END = 175) B(1),B(2),IB,B(4),B(5)		00002800
29		B(3) = IB		00002900
30		TB = B(3) * B(5)		00003000
31		IF (A(4) .NE. B(4)) GO TO 90		00003100
32		WRITE (8,102) A(1),A(2),IA,A(5),TA		00003200
33	102	FORMAT (16X,A4,5X,I3,4X,I3,5X,F5.1,4X,F6.1)		00003300
34		GO TO 25		00003400
35	50	READ (2,104) C		00003500
36	104	FORMAT (A8,8X,I4)		00003600
37		WRITE (8,105) A(4),A(1),A(2),IA,A(5),TA,C(2)		00003700
38	105	FORMAT (2X,A8,8X,A4,5X,I3,4X,I3,5X,F5.1,4X,F6.1,4X,I4/)		00003800
39	55	DO 60 I=1,5		00003900
40	60	A(I) = B(I)		00004000
41		IA = IB		00004100
42		TA = TB		00004200
43		TOT = TA		00004300
44		GO TO 10		00004400
45	90	READ (2,104) C		00004500
46		WRITE (8,102) A(1),A(2),IA,A(5),TA		00004600
47		WRITE (8,104) TOT,C(2)		00004700
48	106	FORMAT (49X,'-----'/43X,'TOT = ',F6.1,4X,I4/)		00004800
49		GO TO 55		00004900
50	150	READ (2,104) C		00005000
51		WRITE (8,105) A(4),A(1),A(2),IA,A(5),TA,C(2)		00005100
52		CALL EXIT		00005200
53	175	READ (2,104) C		00005300
54		WRITE (8,102) A(1),A(2),IA,A(5),TA		00005400
55		WRITE (8,104) TOT,C(2)		00005500
56		CALL EXIT		00005600
57		END		00005700

TABLE IV-13 (CONTINUED)

MODAVAIL EXEC DESCRIPTION

The purpose of MODAVAIL EXEC is to modify the number of available hours associated with either an instructor or a facility in the LP input data file MATRIX1 DATA. MODAVAIL uses the CSS EDIT command to effect the file change. The EDIT command copies the MATRIX1 DATA file into core. Subsequent edit requests examine and modify the core image of the file and then write the file to disk.

The initial EXEC statement suppresses printing of all CSS command statements and all EXEC control statements. Next the output file for the FORTRAN program MODIFY is specified and MODIFY is executed. The EXEC file CHG which has been created by MODIFY is then executed. CHG EXEC uses the CSS EDIT command to modify the file MATRIX1 DITTA. First, the line containing the specified instructor or facility name is located in the file by the LOCATE request. Then the available hour figure contained in the file is replaced with a new figure using the EDIT command CHANGE request. An error in data entry will result in a NO CHANGE message, which indicates that MATRIX1 DATA has not been changed. The final statement in the CHG EXEC writes the updated MATRIX1 DATA file to a writable disk. CHG EXEC is erased following execution. If the user indicates that additional availability modifications are required, MODAVAIL EXEC branches to statement two and reexecutes MODIFY and CHG EXEC. If further changes are not required, a message informing the user how to rerun the SCRR model is printed.

MODIFY FORTRAN DESCRIPTION. The purpose of MODIFY FORTRAN is to create the CHG EXEC file containing the user-specified availability information.

The user specifies the name of the instructor or facility, current available hours, and the new available hours. This information is formatted within several CSS EDIT command request statements and written on output file CHG EXEC. The CHG EXEC file created by MODIFY is shown below.

CHG EXEC

```
&STACK KT
&BEGSTACK
L. /RHS/
L /NAME/
C /NAME          CHRS/NAME          NHRS/
FILE
&ENDSTACK
EDIT MATRIX1 DATA
```


MODAVAIL EXEC FLOWCHART




FIGURE IV-12

CHART TITLE - PROCEDURES




FIGURE IV-12 (CONTINUED)

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL -MODIFY- FLOWCHARTS

PAGE 02

CHART TITLE - NON-PROCEDURAL STATEMENTS

```
REAL*8 RES
9      FORMAT ('ENTER NAME OF INSTRUCTOR OR FACILITY: ')
10     FORMAT (A8)
11     FORMAT ('ENTER CURRENT AVAILABLE HOURS, NEW AVAILABLE HOURS: ')
12     FORMAT (2I99)
13     FORMAT ('ESTACK KT'/'EBEGSTACK'/'L. /RHS'/'L /',AB,'/'/'C /',AB,
14     BX,IA,'/'',AB,BX,IA,'/'/'FILE'/'SENDSTACK'/'EDIT MATRIX1 DATA')
15     FORMAT ('AVAILABLE HOURS LIMITED TO FOUR (4) DIGIT NUMBER TRY ',
16     'AGAIN.')
```

FIGURE IV-12 (CONTINUED)

MODAVAIL PROGRAM LISTINGS

MODAVAIL EXEC
VP/CSS

```
&TYPE OFF
-CHG FILEDEF 8 DSK CHG EXEC
FILEDEF 6 CONO
RUN MODIFY
EXEC CHG
CSS ERASE CHG EXEC
&PRI ANY MORE CHANGES? (YES/NO)
&READ ARGS
&IF &1 NE NO &GOTO -CHG
&PRI CHANGES TO AVAILABLE HOURS HAVE BEEN INCORPORATED.
&PRI TO RERUN SCRR MODEL TYPE: SCRR1
&EXIT
```

FIGURE IV-14

TAEG REPORT NO. 29

INPUT LISTING		AUTOFLOW CHART SET FINAL		-MODIFY- FLOWCHARTS
FORTRAN MODULE		(LIST, NAME, SOURCE)		
CARD NO	****	CONTENTS	****	
1		REAL*8 RES	00000100	
2		WRITE(6,9)	00000200	
3	9	FORMAT ('ENTER NAME OF INSTRUCTOR OR FACILITY: ')	00000300	
4		READ (5,10) RES	00000400	
5	10	FORMAT (A8)	00000500	
6	5	WRITE (6,11)	00000600	
7	11	FORMAT ('ENTER CURRENT AVAILABLE HOURS, NEW AVAILABLE HOURS: ')	00000700	
8		READ (5,12) ICHR,INHR	00000800	
9	12	FORMAT (2I99)	00000900	
10		IF (ICHR.GT. 9999) GO TO 20	00001000	
11		IF (INHR.GT. 9999) GO TO 20	00001100	
12		WRITE (6,13) RES,RES,ICHR,RES,INHR	00001200	
13	13	FORMAT ('STACK RT//BEGSTACK//L. /RHS//L /'AB,/'/'C /'AB,	00001300	
14		IBX,14,/'AB,IBX,14,/'/'FILE//ENDSTACK//EDIT MATRIX DATA')	00001400	
15		CALL EXIT	00001500	
16	20	WRITE (6,15)	00001600	
17	15	FORMAT ('AVAILABLE HOURS LIMITED TO FOUR (4) DIGIT NUMBER TRY ',	00001700	
18		'AGAIN.')	00001800	
19		GO TO 5	00001900	
20		END	00002000	

TABLE IV-14 (CONTINUED)

REQMT EXEC DESCRIPTION

The purpose of REQMT EXEC is to provide the model user with the capability to modify course utilization, class capacity, and course length expressed in contact hours to assess the impact of these changes on total instructor and facility requirements. The EXEC utilizes three RAMIS RUN EXECUTIVE procedures to retrieve data from two RAMIS data files MODCOURSE and MODFACIL. The RUN EXECs extract current utilization, capacity and length data from the data files and then factor these data by the user-specified percentage changes prior to calculating and filing instructor and facility requirements. RUN EXECUTIVES are cataloged RAMIS procedures capable of accepting variable parameter input values.

The initial REQMT EXEC statement suppresses printing of all CSS command statements and all EXEC control statements. The user is then asked if program operating instructions should be printed. If the response is positive, several lines of text are printed prior to each data request. A negative response will cause all text statements to be bypassed. Values are then requested for the utilization percent change, capacity change, and the length change.

After the requested data have been entered, output files are specified, RAMIS is attached, and three RAMIS RUN EXECUTIVES are executed. REQMT uses all three parameters (utilization, capacity, and length) and generates the file FILE INST which contains instructor contact hour requirements by instructor by course. REQMT1 uses only the utilization and capacity parameters and generates the file FILE CRSE which contains the class size and number of convenings by course. REQMT2 uses the course length parameter and generates the file FACIL which contains the contact hours requirements by facility by course. After REQMT2 has been executed, RAMIS is detached and a message which indicates that the required output files have been generated is printed.

REQMT RUNEXEC DESCRIPTION. The purpose of the REQMT RUNEXEC is to calculate instructor requirements in hours by course and by instructor incorporating the course parameter deltas as specified by the user through the REQMT EXEC. The basic data required to determine instructor requirements are stored in the RAMIS course file MODCOURSE.

REQMT RUNEXEC is based on the RAMIS procedure SCRR INST described earlier. The primary difference between the two procedures is that the RUNEXEC factors the data retrieved from the course file by the user-specified percentages. REQMT output is written on FILE INST.


REQMT RUNEXEC is a cataloged procedure stored in the RAMIS file RAMEXEC. Maintenance of the RAMEXEC file to change a procedure can be performed in the UPDATE mode or in the SCAN mode through the usual RAMIS facilities. Alternately the file REQMT RUNEXEC can be modified, and the procedure recataloged by using the RAMIS command RAMISIN REQMT RUNEXEC.

REQMT1 RUNEXEC DESCRIPTION. The purpose of the REQMT1 RUNEXEC is to record the convening frequency and average class size for each course incorporating the user-specified course parameter deltas. The required data are stored in the RAMIS course file MODCOURSE.

REQMT1 RUNEXEC is based on the RAMIS procedure SCRR CRSE described earlier. The primary difference between the two procedures is that the RUNEXEC factors the data retrieved from the course file by the user-specified percentages. REQMT1 output is written on FILE CRSE.

REQMT2 RUNEXEC DESCRIPTION. The purpose of the REQMT2 RUNEXEC is to determine facility requirements in hours by course and by facility incorporating the course length delta specified by the user. The basic data are stored in the RAMIS facility file MODFACIL.

REQMT2 RUNEXEC is based on the RAMIS procedure SCRR FACIL described earlier. The primary difference between the two procedures is that the RUN EXEC factors the data retrieved from the facility file by the user-specified percentages. REQMT2 output is written on FILE FACIL.



REQMT PROGRAM LISTINGS

REQMT EXEC
 VP/CSS

```

&TYPE OFF
&PRINT DO YOU WISH INSTRUCTIONS TO BE PRINTED? (YES/NO) :
&READ ARGS
&DIR = &1
&IF &DIR NE YES &GOTO -U
&PRINT THIS PROGRAM PROVIDES THE CAPABILITY TO MODIFY COURSE
&PRINT UTILIZATION, CLASS CAPACITY, AND COURSE LENGTH EXPRESSED
&PRINT IN CONTACT HOURS TO ASSESS THE IMPACT ON TOTAL INSTRUCTOR
&PRINT REQUIREMENTS.
&PRINT * TO INCREASE UTILIZATION 20% ENTER: .20
&PRINT * TO DECREASE UTILIZATION 10% ENTER: -.10
&PRINT * IF NO CHANGE IS DESIRED ENTER: 0
-U &PRINT ENTER UTILIZATION DELTA:
&READ ARGS
&UDEL = &1
&IF &DIR NE YES &GOTO -C
&PRINT * TO INCREASE CLASS CAPACITIES 20% ENTER: .20
&PRINT * TO DECREASE CLASS CAPACITIES 10% ENTER: -.10
&PRINT * IF NO CHANGE IS DESIRED ENTER: 0
-C &PRINT ENTER CLASS CAPACITY DELTA:
&READ ARGS
&CDEL = &1
&IF &DIR NE YES &GOTO -L
&PRINT * TO INCREASE COURSE LENGTH 20% ENTER: .20
&PRINT * TO DECREASE COURSE LENGTH 10% ENTER: -.10
&PRINT * IF NO CHANGE IS DESIRED ENTER: 0
-L &PRINT ENTER COURSE LENGTH DELTA:
&READ ARGS
&LDEL = &1
&STACK KT
&STACK EXEC REQMT &UDEL , &CDEL , &LDEL
FILEDEF 6 MSG KILL
FILEDEF 4 DSK FILE INST RE F LR 25
ATTACH RAMIS ALL BRIEF
EXEC RAMIS
DETACH RAMIS ALL BRIEF
&STACK KT
&STACK EXEC REQMT1 &UDEL , &CDEL
FILEDEF 4 DSK FILE CRSE RE F LR 10
ATTACH RAMIS ALL BRIEF
EXEC RAMIS
DETACH RAMIS ALL BRIEF
&STACK KT
&STACK EXEC REQMT2 &LDEL
&STACK FIN
FILEDEF 4 DSK FILE FACIL RE F LR 22
ATTACH RAMIS ALL BRIEF
EXEC RAMIS
DETACH RAMIS ALL BRIEF
ERASE MSG KILL
FILEDEF 6 CONO
&PRI REQUESTED CHANGES HAVE BEEN INCORPORATED.
&PRI TO RERUN SCRR MODEL TYPE: SCRR2

```

TABLE IV-15

REQMT RUNEXEC
VP/CSS

```

DELETE
FILE RAMEXEC
1=OUT=REQMT.3
END
CATALOG REQMT
DEFINE
FILE MODCOURSE
UCAP1 / F4.2 = MIN (1.0, (UCAP * .01) + (UCAP * .01 * (&1)))
CLASIZE / I3 = (CAP1 * UCAP1 * ((&2) + 1.0)) + .5
NOINST / I3 = MAX (1.0, (CLASIZE / SIR) + .5)
TOTHR / F6.1 = NOINST * CHRS * (&3 + 1.0)
FLAG / I1 = ASN
END
TABLE
FILE MODCOURSE
STORE TOTHR AND FLAG BY CDP BY SIR BY NME
IF DEL IS 1
RUN
FILE MODCOURSE
SUM ASN AND HOLD BY CDP BY SIR
END
DEFINE
FILE HOLD
INSTHR / F5.1 = TOTHR / ASN
END
TABLE
FILE HOLD
SUM INSTHR AND SAVE BY CDP BY NME
IF FLAG IS-MORE-THAN 0
IF NME IS-NOT '
END
FIN
END CATALOG

```

TABLE IV-15 (CONTINUED)

REQMT1 RUNEXEC
VP/CSS

```
DELETE
FILE RAMEXEC
1=OUT=REQMT1.$
END
CATALOG REQMT1
DEFINE
FILE MODCOURSE
UCAP1 / F4.2 = MIN (1.0, (.01 * UCAP) + (UCAP * .01 * (&1)))
CLASIZE / I3 = (CAP1 * UCAP1 * ((&2) + 1.0)) + .5
END
TABLE
FILE MODCOURSE
PRINT CLASIZE AND CONVL AND SAVE BY CDP
IF DEL IS 1
END
FIN
END CATALOG
```

- REQMT2 RUNEXEC
VP/CSS

```
DELETE
FILE RAMEXEC
1=OUT=REQMT2.$
END
CATALOG REQMT2
DEFINE
FILE MODFACIL
RHRS / F6.1 = REQHRS + (REQHRS * (&1))
END
TABLE
FILE MODFACIL
PRINT RHRS AND SAVE BY CDP BY BLDG BY RM
END
FIN
END CATALOG
```

TABLE IV-15 (CONTINUED)

SCRR2 EXEC DESCRIPTION

The purpose of the SCRR2 EXEC is to incorporate the resource requirement changes requested through the REQMT EXEC into the LP input data matrix and then rerun the SCRR model.

REQMT EXEC regenerates three RAMIS interface files - FILE INST, FILE FACIL, and FILE CRSE. To incorporate the data from these files into the LP data matrix, it is necessary to execute those executives which require any of these files as input. Therefore, the following executives are serially executed by the SCRR2 EXEC:

BLANK
IF2
SCRRSORT
COMB
SCRR1

SCRR2 PROGRAM LISTING

SCRR2 EXEC
 VP/CSS

&PRI THIS EXECUTIVE WILL INCORPORATE THE CHANGES
&PRI REQUESTED BY THE REQMT EXECUTIVE INTO THE LP
&PRI INPUT AND RERUN THE SCRR MODEL
&TYPE OFF
EXEC BLANK
EXEC IF2
EXEC SCRRSORT
EXEC COMB
EXEC SCRR1

TABLE IV-16

FIXCONV EXEC DESCRIPTION

The purpose of the FIXCONV EXEC is to modify the LP input data MATRIX1 DATA to fix the number of course convenings at the current level.

The MATRIX1 DATA file contains one BOUND data card image for each course in the current problem formulation. Columns 2-3 of this card image contain the bound type indicator. The indicator LO indicates that the number of convenings specified in columns 25-36 is a lower bound. This is equivalent to adding a constraint to the LP problem formulation specifying that the number of convenings must be greater than or equal to the number specified on the BOUND data card. FIXCONV EXEC uses the NCSS EDIT command to change the BOUND type indicator LO on all BOUND data cards in MATRIX1 DATA to the type indicator FX. FX indicates that the number of convenings specified on the BOUND data card is a fixed value.

FIXCONV PROGRAM LISTING

FIXCONV EXEC
VP/CSS

```
&BEGSTACK
KT
C /LO/FX/ * *
FILE
&ENDSTACK
EDIT MATRIX1 DATA SB
&PRI COURSE CONVENINGS FIXED AT THE CURRENT LEVEL.
&PRI TO RERUN SCRR MODEL TYPE : SCRR1
&EXIT
```

TABLE IV-17

MAXCONV EXEC DESCRIPTION

The purpose of the MAXCONV EXEC is to modify the LP input data MATRIX1 DATA to remove the upper bound on course convenings previously established through the execution of FIXCONV EXEC.

MAXCONV EXEC reverses the data change made by FIXCONV EXEC. MAXCONV uses the NCSS EDIT command to change the BOUND type indicator FX on all BOUND data cards on MATRIX1 DATA to the type indicator LO.

If the type indicator is not FX when MAXCONV is executed, the program will respond with the message NO CHANGE.

MAXCONV PROGRAM LISTING

MAXCONV EXEC
VP/CSS

```
&BEGSTACK
KT
C /FX/LO/ * *
FILE
&ENDSTACK
EDIT MATRIX1 DATA SB
```

TABLE IV-18

TAEG REPORT NO. 29

(THIS PAGE INTENTIONALLY LEFT BLANK)

SECTION V

TRAINING PROCESS FLOW MODEL

MODEL DESCRIPTION

The objectives of the Training Process Flow model system are to provide training management with the ability to assess the effects upon the training system of changes in demand, scheduling, and capacities, and to present the model output data so that effective decisions can be made for maximizing the utilization of training command resources. The Training Process Flow model system consists of the TPF model and those support programs and executive which interface with the DOTS data base, provide "what if" capability, control model execution, and provide terminal output capabilities. The overall flow of the TPF model system is shown in Figure V-1. The support programs and their associated executives are described first, with the description of the TPF model last.

SUPPORT PROGRAMS. The TPF support programs fall into three categories: those necessary to interface the TPF model with the DOTS data base, those required to support the "what if" capability of the TPF model, and those required to support selective report capability for terminal operation.

TPF MODEL - SIMPLIFIED SYSTEM FLOW




FIGURE V-1

DATA BASE INTERFACE PROGRAMS

All data used for TPF model execution are stored in the DOTS DATA BASE (master or scratch) using the RAMIS system. A series of executives and programs is provided to facilitate unloading of the RAMIS data base, and recopying these data in a format compatible to the TPF model. The flow of these support programs and executives is shown in Figure V-2. All data used by the DOTS system are stored in the DOTS Master data base. These data can be extracted or modified, and is stored in the DOTS Scratch data base. All procedures concerning the use and manipulation of these data bases are discussed in Section II.

Data from the DOTS data base must be copied into TPF compatible files prior to execution of the TPF model. The executive that controls this function is called TPF COPY. The logic flow for this executive is shown in Figure V-4. When this executive is called, the parameter MASTER or SCRATCH may be provided to direct execution to the proper data base, if not, it will be asked for. The first step in the executive is to assure that the users core is set to at least 320K Bytes, due to RAMIS requirements. If the core storage provided is not sufficient, an appropriate error message is displayed, core storage is set to the proper value, and the executive terminates. The executive must be restarted, as any set core operation causes a re-IPL of the user's system, which terminates any ongoing operation. The executive tests &INDEX for the number of parameters passed to the executive by the user. If no parameters are provided, the user is prompted to enter MASTER or scratch. The executive then tests for the appropriate response, and will stay in this loop until one of these two keywords is provided.

The executive then attempts to attach the DISK associated with IBM/CKF so that the data base can be accessed. This disk is attached as unit 193 (U) in the writable mode. BRIEF is specified so that no messages are displayed during this attach and &INDEXØ contains a Ø if the attach is successful. If the attach fails, an appropriate message is displayed the the executive terminates, restoring core to 256K.

RAMIS is invoked next, and a FILEDEF command indicates that a disk data set, TPF INPUT, will be used as the temporary storage for the unloaded data base. The executive then runs procedure RE48 RAM if the master data base is to be unloaded, or RE48X RAM if the scratch data base is to be unloaded. These RAMIS procedures are identical with the exception that RE48 RAM accesses file COURSE, or the master file, while RE48X RAM accesses file MODCOURSE, or the scratch file. Two characteristics of these procedures should be mentioned. First, RAMDATA DATA must be specified as "U" to override the default "P" specification, as the DATA BASE files are attached as 193 (U). Secondly, only the file up to the variable UCAP is unloaded for each course.

The format of the data unloaded into file TPF INPUT is shown in Table V-1 with two records per course. Executive TPF COPY then invokes an executive COPY, which in turn invokes FORTRAN program COPY. This program merely reads the data unloaded from the RAMIS data base now stored as TPF INPUT, and rewrites it as either TPF MASTER or TPF SCRATCH, in a format compatible with the TPF model system. The format for these files is shown in Figure V-3, A and B. The data are stored as two 80 byte records per course. No flow diagrams are shown for either the COPY executive or FORTRAN program due to their simplicity.

TPF MODEL - DATA BASE INTERFACE




FIGURE V-2

RAMIS DUMP FORMAT (MASTER OR SCRATCH)

+ EBCDIC RECORD LENGTH 80 CHARACTERS

<u>FIELD NAME</u>	<u>FORMAT</u>	<u>LENGTH</u>
SCH	A 4	4
CDP	A 4	4
DEL	A 1	1
CTLG	A 10	10
CRS	A 16	16
CONV1	I 3	3
LEN1	F4 .1	4
CAP1	I 3	3
BCAP1	I 3	3
DMD1	I 5	5
BDMD1	I 5	5
OFST	I 2	2
PFAIL	F5 .3	5
NADIS	F5 .3	5
NOSHOW	F5 .3	5
SETB	F5 .3	5
		X 0
BKLG	I 4	4
JNO	A 4	4
CONV2	I 3	3
LEN2	F4 .1	4
CAP2	I 3	3
BCAP2	I 3	3
DMD2	I 5	5
BDMD2	I 5	5
CHWK2	I 3	3
CONV3	I 3	3
LEN3	F4 .1	4
CAP3	I 3	3
BCAP3	I 3	3
DMD3	I 5	5
BDMD3	I 5	5
CHWK3	I 3	3
PAOB	I 4	4
AFAIL	F5 .3	5
PRTY	I 2	2
CTYPE	A 2	2
PNEC	A 4	4
UCAP	I 3	3

TABLE V-1

TPF INPUT FORMATS

[illegible]

452

FLOW - EXECUTIVE TPF COPY




FIGURE V-4

FLOW - EXECUTIVE TPF COPY (CONTINUED)




FIGURE V-4 (CONTINUED)

TAEG REPORT NO. 29
TPFCOPY EXEC

```

&TYPE OFF
&IF &CORE GE 320 &GOTO -OK
&PRINT CORE WAS NOT 320 K - USER MUST RESTART PROCEDURE
SET CORE 320
&EXIT
-OK &INDEX1 = 1
&IF &INDEX EQ 0 &GOTO -NONE
&IF &1 EQ MASTER &GOTO -RUNIT
&INDEX1 = 2
&IF &1 EQ SCRATCH &GOTO -RUNIT
-NONE &PRINT REPLY MASTER OR SCRATCH
&READ ARGS
&GOTO -OK
-RUNIT ATTACH IBMCKF DOTS 191 AS 193 W BR
&IF &INDEX0 EQ 0 &GOTO -FREE
&PRINT IBMCKF IN USE- WAIT TILL CLEAR AND RETRY
SET CORE 256
&EXIT
-FREE ATTACH RAMIS ALL BR
FILEDEF RAMUTIL1 DSK TPF INPUT
&STACK KT
&INDEX2 = 1
&IF &INDEX1 EQ 1 EXEC RAMISIN RE48 RAM
&IF &INDEX1 EQ 2 EXEC RAMISIN RE48X RAM
&IF &INDEX0 NE 0 &INDEX2 = 10
DETACH RAMIS BR
DETACH 193 BR
&IF &INDEX2 LT 5 &GOTO -RAMOK
&STACK RT
&PRINT FILE NOT DUMPED- RAMIS ERROR
SET CORE 256
&EXIT
-RAMOK FILEDEF * CLEAR
&STACK RT
&IF &INDEX1 EQ 1 EXEC COPY MASTER
&IF &INDEX1 EQ 2 EXEC COPY SCRATCH
&EXIT

```

COPY EXEC

```

&TYPE OFF
FILEDEF 9 DSK TPF INPUT
FILEDEF 10 DSK TPF MASTER
&IF &INDEX EQ 0 &GOTO -MASTER
&IF &1 NE SCRATCH &GOTO -MASTER
FILEDEF 10 DSK TPF SCRATCH
&PRINT TPF SCRATCH FILE BEING UPDATED
RUN COPY
SET CORE 256
&EXIT
-MASTER &PRINT TPF MASTER FILE BEING UPDATED
RUN COPY
SET CORE 256
&EXIT

```

TAEG REPORT NO. 29

RE48 RAM

```
USE
RAMDATA DATA U
END
DUMP
FILE COURSE
PRINT UCAP AND SAVE
END
```

RE48X RAM

```
USE
RAMDATA DATA U
END
DUMP
FILE MODCOURSE
PRINT UCAP AND SAVE
END
```

COPY FORTRAN

```
C PROGRAM TO CONVERT RAMIS UNLOADED DB TO TPF FORMAT 03JUN75
  IMPLICIT INTEGER*2 ($)
  INTEGER*4 $1,$16,$35,$36
  REAL*4 $5,$11,$12,$13,$14,$18,$25,$31,$32
  REAL*8 $2A,$3A,$3B
  I = 0
1 READ (9,2,END=999) $36,$1,$2A,$2B,$3A,$3B,$4,$5,$6,$7,$8,$9,$10
  *, $11,$12,$13,$14,$15,$16,$17,$18,$19,$20,$21,$22,$23,$24,$25,$26
  *, $27,$28,$29,$30,$31,$32,$33,$34,$35
2 FORMAT (2A4,1X,A8,A2,2A8,I3,F4.1,2I3,2I5,I2,4F5.3,/
  * 14,A4,2(I3,F4.1,2I3,2I5,I3),F4.1,F5.3,2A2,A4,4X)
  WRITE (10,516) $1,$2A,$2B,$3A,$3B,$4,$5,$6,$7,$8,$9,$10,
  *, $11,$12,$13,$14,$15,$16,$17,$18,$19,$20,$21,$22,
  *, $23,$24,$25,$26,$27,$28,$29,$30,$31,$32,$33,$34,$35,$36
516 FORMAT (A4,A8,A2,2A8,I3,F3.0,2I3,2I5,I2,4F4.3,14,A4,2X,/,A4,
  * 2(I3,F3.0,2I3,2I5,I3),2F4.1,2A2,2A4)
  I = I + 1
  GO TO 1
999 WRITE (6,99) I
99 FORMAT (/' END TPF DB FILE UPDATE-',I3,' COURSES UPDATED'/)
  STOP
END
```

TABLE V-3

"WHAT IF" SUPPORT PROGRAMS

The TPF model user normally will use the TPF system first to examine a school or center under normal, or baseline, conditions, and then to modify certain input parameters and observe the changes to the outputs that occur. Three approaches are available to the user to modify these input data. See Figure V-5. The first is to use the RAMIS facilities to modify the baseline data and create a DOTS scratch data base. The use of RAMIS to accomplish this is discussed in Section II of this report. The second method is to execute program TPFMOD1, which allows the user to make modifications to individual courses for study, or to insert new or upcoming courses in order to observe their effects on the overall system. Finally, program PARAM can be used to make modifications to a certain type of data for all courses; i.e., reducing the demand for all courses by 10%.

COURSE MODIFICATIONS. Executive TPFMOD, in conjunction with program TPFMOD1, is used to control the "what if" capability of the TPF system for modifications to individual courses or the study or inclusion of new courses to the center.

Executive TPFMOD. Executive TPFMOD is quite straight forward, and its flow is shown in Figure V-6. This executive sets up the program to access either the TPF MASTER or TPF SCRATCH data base created by copying and reformatting the data stored in the DOTS data base. A third file, TPF VFY, shown in Figure V-5, is available to the TPF model for verification purposes, but cannot be accessed by TPFMOD1. Three features of executive TPFMOD should be explained. First, &INDEX contains the number of parameters passed the executive during the call (or parameter read), and &1 ... &10 contain the parameters. It is important to test that there are parameters before testing the value of the parameters as the executive will ABEND on a value test if none are present. Secondly, &INDEX0 contains the condition code of the last program run. In this case, it is used to test the condition code of the STOP command in program TPFMOD1, which will be 0 if the user desires to save the data created, and 999 if it is not to be saved. Finally, program TPFMOD1 overrides the normal error checking for input/output errors of the System/370, and this error checking must be reset by the SET SPIE ON command to allow normal processing to continue. Failure to reset this SPIE may cause subsequent programs to loop during execution of I/O commands, resulting in excessive consumption of computer time and charges.

Program TPFMOD1. Program TPFMOD1 is actually a load module obtained by combining main program TPFMOD with subroutines COMND, CONVRT, MSG, DECODE, and SHOW. The FORTRAN program TPFMOD is discussed first, with each subroutine discussed separately.

Program TPFMOD has two purposes. The first is to allow the user to access specific courses from the TPF data base (master or scratch), make alterations to any of the data elements, and to store the modified course data for TPF model execution. The second purpose is to allow the user to create new courses, prompted by the program, and again store them for TPF execution. Program TPFMOD (main) controls the sequence of execution to accomplish this. This control program can be broken into three parts: The first part controls the "COPY" option, the second controls the "NEW" option, while the third section controls the "MOD" option. Several features are consistent throughout this main program and the various subroutines. First, all data set input uses the direct access method of FORTRAN read. This is to allow the user to skip through the files without

TPF MODEL - "WHAT IF," AND OUTPUT DISPLAY




FIGURE V-5

the need to open and close them on each read. A CALL ERRSET command is declared at the beginning of the program to override error checking during this I/O operation. Should the user specify a course CDP number not in file, inline subroutine RANGE will be invoked to recover the error and allow processing to continue.

Secondly, most terminal I/O uses the 10A1 format. This is to allow the user to intermix alpha, numeric, and decimal characters on the same read operation and to allow entry of a variable number of parameters during the same read. Subroutine CONVRT is used to change the results of this read back to internally usable data. Finally, during any terminal read operation, terms such as HELP, QUIT, SHOW, DONE, etc., may be entered, and subroutine MSG will provide the proper action.

The COPY option allows the user to copy all data for a particular course into core storage for subsequent modification and finally execution by the TPF model. The course is called by the CDP number, and either file TPF MASTER or TPF SCRATCH is searched for that course. The course data are stored in the order they are accessed rather than by CDP number. This is to allow evaluation of a course under several conditions during a single model run, hence the same course can be copied several times. However, due to the pointer method of storage, the sequence of operation must be COPY, MODIFY, COPY, MODIFY...as it is impossible to modify course data after a new course has been read in.

The NEW option allows the user to create new courses in the file. The user is prompted for the proper data and format for only those data elements required for TPF execution. This prompting is accomplished through a DO loop, which repetitively calls subroutine DECODE, handing off the proper parameter. The course counter is incremented once a new course has been inserted in the file.

The MOD option allows the user to modify data for a course inserted in the file, whether through the COPY or NEW option. The user is prompted to enter a field name. Subroutine DECODE then validates the field name and prompts for the data in the proper format. Subroutine DECODE also accepts the field name, followed by a blank and then the data to speed up the operation by an experienced operator. The field names in this program are identical to the field names used in the DOTS data base, and may be displayed by entering HELP and asking for the field names.

The wrapup of this program allows the user to bypass storage of the file created if errors occurred, and also supports the HELP option. The HELP option allows the user to display the field names or commands available, without reference to an operation manual. Processing returns to the point at which HELP was entered upon completion of this option.

Subroutine DECODE has three purposes. The first is to support the NEW option by prompting for proper field data. The second is to support the MOD option, by verifying field names, and prompting for and verifying the field data. Finally, the subroutine supports the STAT command, and will display the current value of any field for the course in process. Communication with the main program, or other calling subroutines, is accomplished through parameters passed with the subroutine call for control and return codes, and through COMMON storage for data elements. DECODE is called in the form:

CALL DECODE (I, N, RESP, IN, IN2)

where: All data elements are of the form INTEGER*2

I contains the valid field number if known (usually through the new option), a zero if it is not known, or a 9999 if the STAT option is in effect (from subroutine SHOW).

N is a pointer at the data in storage for the course being processed.

RESP contains the return code (0 for valid operation, 99 for an invalid operation, or the subroutine MSG return code if the operator keyed in a valid message during execution).

IN and IN2 are 5 element arrays containing the data to be converted. IN contains the field name, while IN2 contains the data.

Subroutine DECODE contains the type of data (integer, alpha, or decimal) for each field in an array called TYPE, and the limiting value for each field in an array called SIZE. This allows error checking of data elements and allows prompting of the user if no data are entered with the field name or an error occurs. During execution of subroutine DECODE, if any data entered are invalid or not recognized, subroutine MSG is called to ascertain if a valid message was entered, and if so, subroutine DECODE terminates, using the message number as a return code.

Subroutine CONVRT is a FORTRAN subroutine called by TPFMOD MAIN and subroutine DECODE, as well as other programs elsewhere in the TPF system. The purpose of CONVRT is to convert data read into storage in the A format to a data form compatible with internal processing. The A format is used in the TPF system for terminal inputs to allow intermixing of data, messages, and field names, allow blank delimited input, to allow intermixing of integer and decimal data, and to eliminate the need for right or left justification for data input. This subroutine is called in the form:

CALL CONVRT (IN, ANS, CODE, DECMAL)

where: IN is in the form INTEGER*2 and is a 5 element array containing the data to be converted.

ANS is in the form INTEGER*4 and contains the integer conversion.

CODE is in the form INTEGER*2 and contains the return code for the subroutine (0 for integer conversion, 5 for decimal conversion, 10 for invalid conversion).

DECMAL is in the form REAL*4 and contains both the real and fractional portion of the answer for a decimal conversion.

Basic operation of this subroutine is quite simple. Each digit of the number to be converted was read into storage using the A1 format. Thus, the number 1 is stored in an INTEGER*2 location as hexadecimal F140, rather than the desired 0001, and is thus not valid for processing. To convert each digit to a processable number the value F000 is first subtracted from the number, in this case

leaving 0140. The number is then divided by 256, which causes a shift right 2, leaving 0001. An equivalence statement is used, making the work area for this operation an INTEGER*4, to prevent underflows. Traps are provided to recognize multiple decimals. The five individual values decoded are then combined into a single decimal or integer value.

Subroutine MSG is a short FORTRAN subroutine used to decode one of 9 valid text messages passed from the calling program or subroutine. It is called in the form:

CALL MSG (IN, CODE)

where: IN is in the form INTEGER*2 and is a 5 element array containing the message to be decoded.

CODE is in the form INTEGER*2 and contains one of the following return codes:

QUIT(1), DONE(2), HELP(3), STAT(4), SHOW(5),
COPY(6), NEW(7), ALL(8), MOD(9), NOT RECOGNIZED(99).

Subroutine SHOW is a FORTRAN subroutine to provide display of all elements for the course in process. This subroutine is called in the form:

CALL SHOW (N)

where: N is in the form INTEGER*2 and contains a pointer to the course in the data matrix in process.

The user is allowed to specify a specific field to be displayed, or call for all fields by means of a CR when prompted. The format of the data displayed is similar to that used for the TPF model. However, the student backlog figure used in the TPF model is found during model initialization, while the figure used here is calculated, with the possibility that in a few cases the backlog figure may differ slightly. No return code is provided for in this subroutine, hence messages cannot be decoded. This subroutine also has the BLOCK DATA subroutine attached, which accomplishes initialization of all data in COMMON storage prior to program execution.

Subroutine COMND is an assembly language subroutine whose execution causes the screen of the Hazeltine display to be cleared. It has no effect on most other terminals. It is called in the form:

CALL COMND (I, J)

where: I and J are INTEGER*2 variables, I must contain a 6 to cause a clear operations and J contains the return code (0 for valid operation, 1 or 2 for error).

The return code is not tested. This subroutine is used by most FORTRAN and PL/I programs in the TPF system.

ACROSS THE BOARD MODIFICATIONS. Program PARAM, in conjunction with executive

TPF, is used to support "what if" capability of the TPF system for "across the board" modifications to input data. This is accomplished through manipulation of data set TPF PARM which is an input to the TPF model, and through the use of FILEDEF commands in the executive to direct the input/output for the TPF model.

Executive TPF. Executive TPF controls execution of both program PARAM and the TPF model. The executive requests which data sets are to be used as input and sets up the necessary flags in &INDEX1 and &INDEX2. An option exists to enter the word SAVE as the second parameter when the input file is requested, and if present, will set a flag in &INDEX3. Normally center and school output data for the TPF model will be written in OUT3 FILE, and detailed course data will be written in OUT4 FILE, overwriting data already written there. If the SAVE option is specified, output will be directed to OUT1 FILE for center and school data, and OUT2 FILE for course data. Also, the TST DATA file, created by program TPFMOD1 can be concatenated with any other input data set at this time.

Program PARAM. Program PARAM is a PL/I program called by the executive TPF, and is used to modify the contents of data set TPF PARM. This data set contains a single 80 byte record that is used as input data by the TPF model to control execution. The format of this data set is shown in Figure V-3 C. This method of control for the TPF model was chosen to facilitate off-line or batch execution, as well as on-line terminal applications. The program reads the current record from data set TPF PARM, displays the active elements, allows the user to make changes, and then rewrites the record. The first four elements (input, first year, last year, and AOB constant) are always active and their values will be displayed. The next 10 fields are active only if a number greater than zero appears in the flag column. Finally, the last 10 fields contain flags, and an indication will be displayed if their value is non-zero. Use of this parameter data are discussed in the TPF LOGIC DESIGN section. The program runs in a manner similar to the other support programs in this section, and accepts most commands, such as HELP, QUIT, and SHOW as the other program. Internally, most of the field location and data assignment tasks are done using the substring feature of the PL/I language. This is to allow the variable display format desired for the active fields, and assist in decoding and locating fields for data entry. The COMND subroutine is used to provide the clear display feature at the beginning of the program and PL/I subroutine IHESARC is used to pass a return code to bypass execution of the TPF model if the user so directs.

FLOW - EXECUTIVE TPFMOD




FIGURE V-6

463




FIGURE V-6 (CONTINUED)

CHART TITLE - PROCEDURES

AUTOFLOW - PROGRAM TPFMD




FIGURE V-7

465

CHART TITLE - PROCEDURES

***** COPY *****
COPY EXISTING COURSE
FROM FILE 3

02.10--> 01
100 1

WRITE TO DEV
VIA FORMAT
101

03.21--> 02
102 1

READ FROM DEV
VIA FORMAT
103
INTO THE LIST

/00004200/ NOTE 03
LIST TEXT

/00004400/ 04

TEXT .EQ. QUIT

TRUE

FALSE

/00004500/ 05

TEXT .EQ. DOME

TRUE

FALSE

/00004600/ 06

TEXT .EQ. NEW

TRUE

FALSE

/00004700/ 07

TEXT .EQ. ALL

TRUE

FALSE

02.12--> 08
300 1

WRITE TO DEV
VIA FORMAT
301

3.09

**** ALL **** HERE
IF COPY ALL

WRITE TO DEV
VIA FORMAT
301

2.04
1000

03.07--> 09
/00004800/

TEXT .EQ. HELP

TRUE

FALSE

/00004800/ 10

11 1

10 1

11 1

TEXT .EQ. HELP

TRUE

FALSE

HERE IF DIDNT
RECOGNIZE MESSAGE-
SEE IF IS IN COP FILE

/00005100/ NOTE 12

BEGIN DO LOOP

110 1 = 1, 400, 2

03.18--> 13

READ DEV 3
TCO 1
VIA FORMAT
103
INTO THE LIST

/00005200/ NOTE 14

LIST = TCO

/00005200/ 15

ERROR?

YES

NO

115

/00005300/ 16

TRUE

NGR .GT. 0

FALSE

/00005400/ 17

TCOP .EQ. TEXT

TRUE

FALSE

110 1

END OF DO
LOOP?

YES

13

HERE IF ERROR OR NOT
IN FILE

03.15--> 19

115 1

NGR = 0

/00005800/ 20

WRITE TO DEV
VIA FORMAT
116
FROM THE LIST

/00005800/ NOTE 21

LIST = TEXT

3.02

102

FIGURE V-7 (CONTINUED)

466

AUTOFLOW CHART SET - FINAL -TPFWDD- FLOWCHARTS

PAGE 04

08/14/73

CHART TITLE - PROCEDURES




FIGURE V-7 (CONTINUED)

467

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-TPFNOO- FLOWCHARTS

PAGE 05

CHART TITLE - PROCEDURES




FIGURE V-7 (CONTINUED)

TAEG REPORT NO. 29

08/16/75

AUTOFLOW CHART SET - FINAL -TPFROD- FLOWCHARTS

PAGE 06

CHART TITLE - PROCEDURES




FIGURE V-7 (CONTINUED)

TAEG REPORT NO. 29

08/14/79

AUTOFLOW CHART SET - FINAL

-TPFMOD- FLOWCHARTS

PAGE 07

CHART TITLE - PROCEDURES




FIGURE V-7 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-TPPMOD- FLOWCHARTS

PAGE 08

CHART TITLE - PROCEDURES




FIGURE V-7 (CONTINUED)

TAEQ REPORT NO. 29

08/14/79

AUTOFLOW CHART SET - FINAL

-TPFROD- FLOWCHARTS

PAGE 09

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (0)
INTEGER*4 81,816,835,836
REAL*4 85,811,812,813,814,818,825,831,832
REAL*8 82A,83A,83B
INTEGER*2 YES/'Y'/, NO/'N'/
COMMON /A/ 81(144),82A(144),83A(144),84(144),85(144),86(144)
COMMON /A/ 87(144),88(144),89(144),90(144),91(144),92(144)
COMMON /A/ 93(144),94(144),95(144),96(144),97(144),98(144)
COMMON /A/ 99(144),100(144),101(144),102(144),103(144),104(144)
COMMON /A/ 105(144),106(144),107(144),108(144),109(144),110(144)
COMMON /A/ 111(144),112(144),113(144),114(144),115(144),116(144)
COMMON /A/ 117(144),118(144),119(144),120(144),121(144),122(144)
COMMON /A/ 123(144),124(144),125(144),126(144),127(144),128(144)
COMMON /A/ 129(144),130(144),131(144),132(144),133(144),134(144)
COMMON /A/ 135(144),136(144),137(144),138(144),139(144),140(144)
COMMON /A/ 141(144),142(144),143(144),144(144)
INTEGER*2 IN1(9) /9*0/, IN2 (9) /9*0/, CODE, NJ/4/,JN
COMMON NGR
INTEGER*4 NEW /'NEW' /, QUIT /'QUIT' /, DONE /'DONE' /, TEXT, TCDP
DEFINE FILE 3 (500,80,E,J3)
EXTERNAL RANGE
1  FORMAT (/ ' TPF COURSE CREATE/MODIFY PROGRAM' /)
3  FORMAT (/ ' ENTER 'NEW' OR 'COPY' ' /)
5  FORMAT (10A1)
6  FORMAT (1X, A4, ' *INVALID- RETRY' /)
101  FORMAT (/ ' *COPY EXISTING COURSE- ENTER CDP' /)
103  FORMAT (A4)
116  FORMAT (1X, A4, ' *NOT IN FILE- RETRY OR ENTER DONE' /)
188  FORMAT (A4,A8,A2,2A8,I3,F3.1,2I3,2I5,I2,4F4.3,I4,A4,2X,/,4X,
2(I3,F3.1,2I3,2I5,I3),2F4.1,2A2,2A4)
122  FORMAT (/ ' CDP ', A4, ' *COPIED- ENTER 'DONE' OR 'MOD' ' /)
202  FORMAT (/ ' CREATE NEW COURSE' /)
7  FORMAT (/ ' *INVALID- RETRY' /)
211  FORMAT (/ ' ENTER FOLLOWING DATA TO CREATE COURSE' /)
229  FORMAT (/ ' /)
232  FORMAT (/ ' KEY DATA ENTERED FOR CREATE- ENTER 'MOD' OR 'DONE'
' /)
301  FORMAT (/ ' *ALL' OPTION NOT SUPPORTED THIS PROGRAM' /)
401  FORMAT (/ ' MODIFY DATA FOR CDP ',A4)
403  FORMAT (/ ' *ENTER FIELD TO BE CHANGED' /)
413  FORMAT (/ ' MOD INVALID- NO COURSE IN FILE' /)
501  FORMAT (/ ' SAVE NEW DATA BASE? (Y OR N)' /)
516  FORMAT (A4,A8,A2,2A8,I3,F3.0,2I3,2I5,I2,4F4.3,I4,A4,2X,/,A4,
2(I3,F3.0,2I3,2I5,I3),2F4.1,2A2,2A4)

```

FIGURE V-7 (CONTINUED)

TAEG REPORT NO. 29

06/14/79

AUTOFLOW CHART SET - FINAL

-TPFNOD- FLOWCHARTS

PAGE 10

CHART TITLE - SUBROUTINE HELPI




FIGURE V-7 (CONTINUED)

TAEG REPORT NO. 29

08/14/79

AUTOFLOW CHART SET - FINAL -TPFMOD- FLOWCHARTS

PAGE 11

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

INTEGER**4 TEXT,QUIT/'QUIT'/,SKIP/'SKIP'/,FIEL/'FIEL'/,CODE/'CODE'/
INTEGER**4 DONE /'DONE'/
3  FORMAT (1/' *HELP CALLED- ENTER FIELD, CODES, OR SKIP' )
5  FORMAT (A4)
10  FORMAT (1X, A4, ' INVALID- RETRY')
101  FORMAT (///' TPF FIELDS ARE:'//
      ' CDP   CONV1 LEN1  CAP1  BCAP1 DMD1  BDM1  OFST'/
      ' CTLG  CONV2 LEN2  CAP2  BCAP2 DMD2  BDM2  CHWK1'/
      ' CRS   CONV3 LEN3  CAP3  BCAP3 DMD3  BDM3  CHWK2'/
      ' SCH   PFAIL NADIS NOSHO SETB  BKLG'/
      ' JND   PNEC  PAJB  AFAIL PRTY  CTYPE'//)
201  FORMAT (///' VALID CODES ARE:'//
      ' QUIT DONE HELP STAT SHOW COPY NEW ALL MOD'//)

```

08/14/79

AUTOFLOW CHART SET - FINAL -TPFMOD- FLOWCHARTS

PAGE 12

CHART TITLE - SUBROUTINE RANGE(RK,LL)




FIGURE V-7 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 02

CHART TITLE - SUBROUTINE DECODE(I,N,RESP,IN,IN2)

AUTOFLOW - SUBROUTINE DECODE




FIGURE V-8

TAEG REPORT NO. 29

08/14/79

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 03

CHART TITLE - SUBROUTINE DECODE(I,N,RESP,IN,IN2)




FIGURE V-8 (CONTINUED)

476 V-30

TAE G REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 114

CHART TITLE - SUBROUTINE DECODE(I,N,RESP,IN,IN2)




FIGURE V-B (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 05

CHART TITLE - SUBROUTINE DECODE(I,N,RESP,IN,IN2)




FIGURE V-8 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 06

CHART TITLE - SUBROUTINE DECODE(I,N,RESP,IN,IN2)




FIGURE V-8 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 27

CHART TITLE - SUBROUTINE DECODE(I,N,RESP,IN,IN2)




FIGURE V-8 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL -DECODE- FLOWCHARTS

PAGE 08

CHART TITLE - SUBROUTINE DECODE(I,N,RESP,IN,IN2)




FIGURE V-8 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 24

CHART TITLE - SUBROUTINE DECODE11,RESP:IN,INZ1




FIGURE V-8 (CONTINUED)

TAEg REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL - DECODE - FLOWCHARTS

PAGE 11

CHART TITLE - SUBROUTINE DECODE11,N,RESP,IN,IN21





















FIGURE V-8 (CONTINUED)

08/14/75

-DECODE- FLOWCHARTS

PAGE 11

f 322 f

|

10.19 ---> | 01

|

| AMS = 322(M) |



















|

|

...

.11.16.

... 400



V-38 484

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 12

CHART TITLE - SUBROUTINE DECODE11,N,RESP,IN,IN21




FIGURE V-8 (CONTINUED)

485

V-39

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 13

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (S)
INTEGER*4 S1,S16,S33,S36
REAL*4 S5,S11,S12,S13,S14,S18,S25,S31,S32
REAL*8 S2A,S3A,S3B
COMMON /A/ S1(144),S2A(144),S3A(144),S4(144),S5(144),S6(144)
COMMON /A/ S7(144),S8(144),S9(144),S10(144),S11(144),S12(144)
COMMON /A/ S13(144),S14(144),S15(144),S16(144),S17(144),S18(144)
COMMON /A/ S19(144),S20(144),S21(144),S22(144),S23(144),S24(144)
COMMON /A/ S25(144),S26(144),S27(144),S28(144),S29(144),S30(144)
COMMON /A/ S31(144),S32(144),S33(144),S34(144),S35(144),S36(144)
COMMON /A/ S2B(144),S3B(144)
INTEGER*2 NUM (5) /S*O/, CODE, TYPE (36), DEC, INT, ALPHA
DATA TYPE /30*'A', 7*'I', 4*'F', 'I', 'A', 15*'I', 'F', 4*'A'/
DATA ALPHA /'A', INT /'I', DEC /'F'/
REAL*8 ALPHA1, ALPHA2
INTEGER*4 AMS, A4 (2),QUIT/'QUIT',DONE/'DONE',HELP/'HELP',SHOW/
'SHOW'/
INTEGER*2 IN (5),IN2(5),F (5,36), CDP (5), CTLG (5), CRS (5)
INTEGER*2 CONV1 (5), LEN1 (5), CAP1 (5), BCAP1 (5), DMD1 (5)
INTEGER*2 BMD1 (5), OFST (5), PFAIL (5), NADIS (5), NOSHO (5)
INTEGER*2 SETB (5), BKLG (5), JMD (5), CONV2 (5), LEN2 (5)
INTEGER*2 CAP2 (5), BCAP2 (5), DMD2 (5), BMD2 (5), CHWK2 (5)
INTEGER*2 CONV3 (5), LEN3 (5), CAP3 (5), BCAP3 (5), DMD3 (5)
INTEGER*2 BMD3 (5), CHWK3 (5), PAOB (5), AFAIL (5), PRTY (5)
INTEGER*2 CTYPE (5), PNEC (5), SCH (5), BLANK /' '/
INTEGER*2 RESP, SIZE (36), A2 (4), NA2 (4)
DATA SIZE /4, 10, 16, 3, 4, 203, 205, 2, 405, 204, 3, 4,
203, 205, 203, 4, 203, 205, 3, 4, 5, 202, 204/
EQUIVALENCE (A2,ALPHA1), (A4,ALPHA1), (NA2,ALPHA2)
EQUIVALENCE (CDP, F(1,1)), (CTLG, F(1,2)), (CRS, F(1,3))
EQUIVALENCE (CONV1, F(1,4)), (LEN1, F(1,5)), (CAP1, F(1,6))
EQUIVALENCE (BCAP1, F(1,7)), (DMD1, F(1,8)), (BMD1, F(1,9))
EQUIVALENCE (OFST, F(1,10)), (PFAIL, F(1,11)), (NADIS, F(1,12))
EQUIVALENCE (NOSHO, F(1,13)), (SETB, F(1,14)), (BKLG, F(1,15))
EQUIVALENCE (JMD, F(1,16)), (CONV2, F(1,17)), (LEN2, F(1,18))
EQUIVALENCE (CAP2, F(1,19)), (BCAP2, F(1,20)), (DMD2, F(1,21))
EQUIVALENCE (BMD2, F(1,22)), (CHWK2, F(1,23)), (CONV3, F(1,24))
EQUIVALENCE (LEN3, F(1,25)), (CAP3, F(1,26)), (BCAP3, F(1,27))
EQUIVALENCE (DMD3, F(1,28)), (BMD3, F(1,29)), (CHWK3, F(1,30))
EQUIVALENCE (PAOB, F(1,31)), (AFAIL, F(1,32)), (PRTY, F(1,33))
EQUIVALENCE (CTYPE, F(1,34)), (PNEC, F(1,35)), (SCH, F(1,36))
DATA CDP/'C','D','P',' ',' ','CTLG','C','T','L','G',' '/
DATA CRS/'C','R','S',' ',' ','CONV1','C','O','N','V','1',' '/
DATA LEN1/'L','E','N','1',' ',' '/CAP1/'C','A','P','1',' ',' '/
DATA BCAP1/'B','C','A','P','1',' ','DMD1/'D','M','D','1',' ',' '/
DATA BMD1/'B','D','M','D','1',' ','OFST/'O','F','S','T',' ',' '/
DATA PFAIL/'P','F','A','I','L',' ','NADIS/'N','A','D','I','S',' '/
DATA NOSHO/'N','O','S','H','O',' ','SETB/'S','E','T','B',' ',' '/

```

FIGURE V-8 (CONTINUED)

486

V-40

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

PAGE 14

CHART TITLE - NON-PROCEDURAL STATEMENTS

```


DATA SCH/'S','C','M','I','/','B','K','L','G','/
DATA JMO/'J','M','O','/','CONV2/'C','D','N','V','2'/
DATA LEN2/'L','E','N','2','/','CAP2/'C','A','P','2'/
DATA BCAP2/'B','C','A','P','2','/','DMD2/'D','M','D','2'/
DATA BDMO2/'B','D','M','O','2','/','CHWK2/'C','H','W','K','2'/
DATA CONV3/'C','D','N','V','3','/','LEN3/'L','E','N','3'/
DATA CAP3/'C','A','P','3','/','BCAP3/'B','C','A','P','3'/
DATA DMD3/'D','M','D','3','/','BDMO3/'B','D','M','O','3'/
DATA CHWK3/'C','H','W','K','3','/','PAOB/'P','A','O','B'/
DATA AFAIL/'A','F','A','I','L','/','PRTY/'P','R','T','Y'/
DATA CTYPE/'C','T','Y','P','E','/','PNEC/'P','N','E','C'/
101  FORMAT (' *ENTER ',5A1, 2X, '!',A1, 12, '!')
102  FORMAT (10A1)
106  FORMAT (1X, 5A1, ' *INVALID- RETRY'/)
111  FORMAT (2A8)
1111  FORMAT (1X,2A8)
115  FORMAT (1X,A4)
116  FORMAT (1X,A2)
117  FORMAT (1X, A8, A2)
1120  FORMAT (1X,15, ' TOO LARGE- RETRY'/)
119  FORMAT (1X, 15)
120  FORMAT (F9.3)
500  FORMAT (/2X,5A1,1X,15/)
501  FORMAT (/2X,5A1,F9.3/)
504  FORMAT (/2X,5A1,2X,A4/)
502  FORMAT (/2X,5A1,A2,/)
510  FORMAT (/2X,5A1,A8,A2/)
516  FORMAT (/2X,5A1,A8,A8/)

```

FIGURE V-8 (CONTINUED)

CHART TITLE - SUBROUTINE CONVRT(IN,ANS,CODE,DECIMAL)

AUTOFLOW - SUBROUTINE CONVRT



TAEG REPORT NO. 29


08/14/75

AUTOFLOW CHART SET - FINAL

-CONVRT- FLOWCHARTS

PAGE 03

CHART TITLE - SUBROUTINE CONVRT(IN,AMS,CODE,DECHAL)



08/14/75

AUTOFLOW CHART SET - FINAL

-CONVRT- FLOWCHARTS

PAGE 04

CHART TITLE - NON-PROCEDURAL STATEMENTS

INTEGER=2 IN (5), WORK (10), CODE
 INTEGER=4 UPLIM, LOLIM, BLANK, MOLD (5), TEST, OUT (5), AMS, POINT
 EQUIVALENCE (MOLD, WORK)
 DATA WORK/10=0/,TEST/ZF000/,UPLIM/ZF940/,LOLIM/ZF040/,BLANK/Z4040/
 DATA POINT /Z4B40/

FIGURE V-9 (CONTINUED)

489

V-43

CHART TITLE - SUBROUTINE MSGIN.CODE1

AUTOFLOW - SUBROUTINE MSG




FIGURE V-10

TAEG REPORT NO. 29

08/14/78

AUTO LOW CHART SET - FINAL

-MSG- FLOWCHARTS

PAGE 10

CHART TITLE - NON-PROCEDURAL STATEMENTS


```

INTEGER*2 F(4,9), IN(5), CODE, QUIT(4), DONE(4), HELP(4), STAT(4)
INTEGER*2 SHOW(4), COPY(4), NEW(4), ALL(4), MOD(4)
EQUIVALENCE (QUIT,F(1,1)),(DONE,F(1,2)),(HELP,F(1,3)),(NEW,F(1,7))
EQUIVALENCE (SHOW,F(1,5)),(COPY,F(1,6)),(ALL,F(1,8)),(MOD,F(1,9))
EQUIVALENCE (STAT,F(1,4))
DATA QUIT /'Q','U','I','T'//, DONE /'D','O','N','E'/
DATA HELP /'H','E','L','P'//, SHOW /'S','H','O','W'//
DATA COPY /'C','O','P','Y'//, NEW /'N','E','W'//
DATA ALL /'A','L','L'//, MOD /'M','O','D'//
DATA STAT /'S','T','A','T'/
    
```

FIGURE V-10 (CONTINUED)

CHART TITLE - SUBROUTINE SHOW(1)

AUTOLOW - SUBROUTINE SHOW



TAEG REPORT NO. 29

08/14/77

AUTOFLOW CHART SET - FINAL

-SHOW- FLOWCHARTS

PAGE 13

CHART TITLE - SUBROUTINE SHOWING




FIGURE V-11 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL -SHOW- FLOWCHARTS

PAGE 34

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (8)
INTEGER*4 81,816,835,836
REAL*4 85,811,812,813,814,818,825,831,832
REAL*8 82A,83A,83B
COMMON /A/ 81(144),82A(144),83A(144),84(144),85(144),86(144)
COMMON /A/ 87(144),88(144),89(144),90(144),91(144),92(144)
COMMON /A/ 93(144),94(144),95(144),96(144),97(144),98(144)
COMMON /A/ 99(144),100(144),101(144),102(144),103(144),104(144)
COMMON /A/ 105(144),106(144),107(144),108(144),109(144),110(144)
COMMON /A/ 111(144),112(144),113(144),114(144),115(144),116(144)
COMMON /A/ 117(144),118(144),119(144),120(144),121(144),122(144)
COMMON /A/ 123(144),124(144),125(144),126(144),127(144),128(144)
COMMON /A/ 129(144),130(144),131(144),132(144),133(144),134(144)
COMMON /A/ 135(144),136(144),137(144),138(144),139(144),140(144)
COMMON /A/ 141(144),142(144),143(144),144(144),145(144),146(144)
INTEGER*2 IN (5) /500/, BLANK /' ', CODE
2    FORMAT (/ 'SHOW: ENTER ALL A FIELD NAME')
3    FORMAT (5A1)
11   FORMAT (1X,5A1,' *INVALID- RETRY')
4001 FORMAT (/1X,A4, 5X, 2A8, 4X, '---SCHEDULE DATA--  FY  FY+1  FY+
2    CRS BACKLOG')
4002 FORMAT (' ', T31, 'ANNUAL CONVENINGS', 15, 217, 4X, '0 STU', 15)
4003 FORMAT (' SCHL JND CATALOG NO  MEC  COURSE LENGTH DYS', F5.1,
2F7.1, 4X, '0 WKS', 15)
4004 FORMAT (' ', 2 (A4, 1X), A8, A2, 1X, A4, 4X, 'COURSE CAPACITY',
317)
4005 FORMAT (' ', T31, 'BUPERS CAPACITY', 317, 3X, 'FY+1 WK', 14)
4006 FORMAT (' P AOB PFAIL TYPE  PRTY  ANNUAL DEMAND', 2X, 317,
3X, 'FY+2 WK', 14)
4007 FORMAT (' ', F5.1, F6.1, '0', 3X, A2, 5X, A2, 5X, 'BUPERS DEMAND',
2X, 317, 3X, 'OFFSET', 15)
4008 FORMAT (/ 'RATES: FAIL', F5.1, '0', NADIS', F5.1, '0', NDSHOW', F5.1, '0
'////)
98   FORMAT (/1X,13,' COURSE NOT IN PROCESS- SHOW SKIPPED')

```

FIGURE V-11 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

-SHOW- FLOWCHARTS

PAGE 05

CHART TITLE - BLOCK DATA



08/14/75

AUTOFLOW CHART SET - FINAL

-SHOW- FLOWCHARTS

PAGE 06

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (B)
INTEGER*4 81,816,835,836
REAL*4 85,811,812,813,814,818,825,831,832
REAL*8 82A,83A,83B
COMMON /A/ 81(144),82A(144),83A(144),84(144),85(144),86(144)
COMMON /A/ 87(144),88(144),89(144),910(144),911(144),912(144)
COMMON /A/ 913(144),914(144),915(144),916(144),917(144),918(144)
COMMON /A/ 919(144),920(144),921(144),922(144),923(144),924(144)
COMMON /A/ 925(144),926(144),927(144),928(144),929(144),930(144)
COMMON /A/ 931(144),932(144),933(144),934(144),935(144),936(144)
COMMON /A/ 92B (144),93B(144)
DATA 81,816,835,836/5760* '//,82A,83A,83B/4320* '//,92B/' '//
DATA 85,811,812,813,814,818,825,831,832 /129600./
DATA 84,86,87,88,89,910,915,917,919,920,921,922,923,924,926,
927, 928, 929, 930, 934 /2880 * 0/, 933 /' '//
    
```

FIGURE V-11 (CONTINUED)

FLOW - EXECUTIVE TPF




FIGURE V-12

CHART TITLE - PROC PARAM OPTIONS (MAIN)

AUTOFLOW - PROGRAM PARAM




FIGURE V-13

CHART TITLE - PROC PARAM OPTIONS (MAIN)




FIGURE V-13 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL

PL/1 -PARAM- FLOWCHARTS

PAGE 05

CHART TITLE - PROC PARAM OPTIONS (MAIN)




FIGURE V-13 (CONTINUED)

V-53 499

CHART TITLE - PROC PARAM OPTIONS (MAIN)




FIGURE V-13 (CONTINUED)

TAEG REPORT NO. 29

AUTOFLOW CHART SET - FINAL

PL/1 -PARAM- FLOWCHARTS

PAGE 05

08/14/75

CHART TITLE - PROC PARAM OPTIONS (MAIN)





FIGURE V-13 (CONTINUED)

TAEG REPORT NO. 29

08/14/79

AUTOFLOW CHART SET - FINAL

PL/1 -PARAM- FLOWCHARTS

PAGE 06

CHART TITLE - CALLED PROCEDURES - CROSS REFERENCE




FIGURE V-13 (CONTINUED)

LISTING - EXECUTIVE TPFMOD

```

&TYPE OFF
-FRST &IF &INDEX EQ 0 &GOTO -NONE
&IF &1 EQ MASTER &GOTO -OK
&IF &1 EQ SCRATCH &GOTO -OK
&IF &1 EQ QUIT &EXIT
-NONE &PRINT REPLY MASTER OR SCRATCH (INPUT FILE)
&READ ARGS
&GOTO -FRST
-OK FILEDEF " CLEAR
FILEDEF 3 DSK TPF MASTER
FILEDEF 4 DSK TST DATA
&IF &1 NE SCRATCH &GOTO -MASTER
FILEDEF 3 DSK TPF SCRATCH
&PRINT SCRATCH DATA BASE USED AS MOD INPUT
&GOTO -RUNIT
-MASTER &PRINT MASTER DATA BASE USED AS MOD INPUT
-RUNIT TPFMOD1
FILEDEF " CLEAR
SET SPIE ON
&IF &INDEX GE 999 &GOTO -QUIT
-READ &PRINT RUN TPF MODEL? (Y OR N)
&READ ARGS
&IF &1 EQ Y &GOTO -MODEL
&IF &1 EQ N &GOTO -SKIP
&IF &1 EQ QUIT &GOTO -SKIP
&GOTO -READ
-MODEL EXEC TPF TEST
-SKIP &EXIT
-QUIT &PRINT NOT SAVED AT OPERATORS REQUEST
&EXIT

```

TABLE V-4

TAEQ REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-TPFMOD- FLOWCHARTS

LISTING - PROGRAM TPFMOD

FORTRAN MODULE

LIST,NAMSQ,SOURCESEQ

CARD NO

CONTENTS

```

1 C TPF INPUT CREATE/MODIFY PROGRAM 13JUN75
2 C SUBROUTINES CALLED-MSG, CONVRT, DECODE, CONND
3 IMPLICIT INTEGER*2 (I)
4 INTEGER*2 I1,I18,835,836
5 REAL*4 I5,I11,I12,I13,I14,I18,825,831,832
6 REAL*8 I2A,I3A,I3B
7 INTEGER*2 YES/'Y'/, NO/'N'/
8 COMMON /A/ I1(144),I2A(144),I3A(144),I4(144),I5(144),I6(144)
9 COMMON /A/ I7(144),I8(144),I9(144),I10(144),I11(144),I12(144)
10 COMMON /A/ I13(144),I14(144),I15(144),I16(144),I17(144),I18(144)
11 COMMON /A/ I19(144),I20(144),I21(144),I22(144),I23(144),I24(144)
12 COMMON /A/ I25(144),I26(144),I27(144),I28(144),I29(144),I30(144)
13 COMMON /A/ I31(144),I32(144),I33(144),I34(144),I35(144),I36(144)
14 COMMON /A/ I37(144),I38(144),I39(144),I40(144),I41(144),I42(144)
15 INTEGER*2 INI5 /5*0/, IN2 (5) /5*0/, CODE, NJ/8/,JN
16 COMMON NGR
17 INTEGER*4 NEW /'NEW'/, QUIT /'QUIT'/, DONE /'DONE'/, TEXT, TCDP
18 DEFINE FILE 3 (500,80,E,J3)
19 EXTERNAL RANGE
20 CALL ERRSET (232,100,-1,1,RANGE)
21 CALL CONND (INJ,JN)
22 N = 0
23 NGR = 0
24 1000 WRITE (6,1)
25 1 FORMAT (/ ' TPF COURSE CREATE/MODIFY PROGRAM' /)
26 2 WRITE (6,3)
27 3 FORMAT (/ ' ENTER 'NEW' OR 'COPY' ' /)
28 4 READ (5,5) IN
29 5 FORMAT (10A1)
30 CALL MSG (IN, CODE)
31 IF (CODE .EQ. 2) GO TO 999
32 IF (CODE .EQ. 6) GO TO 100
33 IF (CODE .EQ. 7) GO TO 200
34 IF (CODE .EQ. 8) GO TO 300
35 IF (CODE .EQ. 9) GO TO 400
36 WRITE (6,6) IN
37 6 FORMAT (1X, 5A1, ' *INVALID- RETRY' /)
38 GO TO 2
39 C ***** COPY EXISTING COURSE FROM FILE 3
40 100 WRITE (6,101)
41 101 FORMAT (/ ' *COPY EXISTING COURSE- ENTER CDP' /)
42 102 READ (4,103) TEXT
43 103 FORMAT (1A1)
44 IF (TEXT .EQ. QUIT) GO TO 999
45 IF (TEXT .EQ. DONE) GO TO 1000
46 IF (TEXT .EQ. NEW) GO TO 200
47 IF (TEXT .EQ. ALL) GO TO 300
48 IF (TEXT .EQ. HELP) CALL HELP1
49 IF (TEXT .EQ. HELP) GO TO 100
50 C HERE IF DIDNT RECOGNIZE MESSAGE- SEE IF IS IN CDP FILE
51 DO 110 I = 1, 400, 2
52 READ (3,1, 103, ERR=115) TCDP
53 IF (NGR .GT. 0) GO TO 115
54 IF (TCDP .EQ. TEXT) GO TO 120
55 110 CONTINUE
56 C HERE IF ERROR OR NOT IN FILE
57 115 NGR = 0
58 WRITE (6,116) TEXT
59 116 FORMAT (1X, A1, ' *NOT IN FILE- RETRY OR ENTER DONE' /)
60 GO TO 102
61 C HERE IF FOUND CDP
62 120 CONTINUE
63 N = N + 1
64 J = 1
65 READ (3,1,100,ERR=115) I1(N),I2A(N),I2B(N),I3A(N),I3B(N),I4(N),I5,
66 I6(N),I7(N),I8(N),I9(N),I10(N),I11(N),I12(N),I13(N),I14(N),
67 I15(N),I16(N),I17(N),I18(N),I19(N),I20(N),I21(N),I22(N),I23(N),
68 I24(N),I25(N),I26(N),I27(N),I28(N),I29(N),I30(N),I31(N),
69 I32(N),I33(N),I34(N),I35(N),I36(N)
70 100 FORMAT (1A, A8, A2, 2A8, 13, F3.1, 213, 215, 12, 4F4.3, 14, A4, 2X, /, 4X,
71 * 213, F3.1, 213, 215, 13), 2F4.1, 2A2, 2A4)
72 121 WRITE (6,122) TEXT
73 122 FORMAT (/ ' CDP ' , A4, ' *COPIED- ENTER 'DONE' OR 'NOO' ' /)
74 123 READ (5,5) IN,IN2
75 CALL MSG (IN, CODE)
76 GO TO 1999, 1000, 124, 126, 123, 100, 200, 300, 400), CODE
77 WRITE (6,6) IN
78 GO TO 123
79 124 CALL HELP1
80 GO TO 121
81 125 CALL SHOW (N)
82 GO TO 121
83 126 I = 9999
84 CALL DECODE (I,N, CODE, IN, IN2)
85 IF (CODE .EQ. 0) GO TO 121
86 WRITE (6,6) IN2
87 GO TO 123
88 C ***** NEW ***** CREATE NEW COURSE- PROMPT FOR ENTRIES
89 200 CALL CONND (INJ,JN)
90 201 WRITE (6,202)
91 202 FORMAT (/ ' CREATE NEW COURSE' /)
92 N1 = N + 1
93 I = 1
94 CALL DECODE (I,N1, CODE, IN, IN2)
95 IF (CODE .EQ. 0) GO TO 210
96 GO TO 1999, 1000, 204, 203, 203, 100, 200, 300), CODE
97 203 WRITE (6,7)
98 7 FORMAT (/ 'INVALID- RETRY' /)
99 GO TO 201
100 204 CALL HELP1
101 GO TO 201
102 C HERE IF FOUND CDP- NOW INCREMENT COUNTER & CREATE COURSE
103 210 WRITE (6,211)
104 211 FORMAT (/ ' ENTER FOLLOWING DATA TO CREATE COURSE' /)
105 N = N + 1
106 DO 230 I = 3, 14
107 IF (I .EQ. 10) GO TO 230
108 IF (I .EQ. 14) GO TO 230
109 212 I1 = I

```

TABLE V-5

TAEG REPORT NO. 29

CARD NO	INPUT LISTING	AUTOFLOW CHART SET - FINAL	-TPFMOD- FLOWCHARTS
CARD NO	CONTENTS		
110	IF (I.EQ. 10) I = 30		00011000
111	CALL DECODE (I,N.CODE,IN,IN2)		00011100
112	IF (CODE.EQ. 0) GO TO 230		00011200
113	GO TO (999,1000,221,212,222,100,200,300,400), CODE		00011300
114	WRITE (6,6) IN		00011400
115	GO TO 212		00011500
116	221 CALL HELP1		00011600
117	GO TO 212		00011700
118	222 CALL SHOW (N)		00011800
119	GO TO 212		00011900
120	230 WRITE (6,220)		00012000
121	229 FORMAT (' ')		00012100
122	C END PROMPTED COURSE CREATE		00012200
123	231 WRITE (6,232)		00012300
124	232 FORMAT ('/' KEY DATA ENTERED FOR CREATE- ENTER '*'MOD*' OR '*'DONE*')		00012400
125	'')		00012500
126	236 READ (5,5) IN,IN2		00012600
127	CALL MSG (IN,IN2)		00012700
128	GO TO (999,1000,233,235,234,100,200,300,400), CODE		00012800
129	WRITE (6,6) IN		00012900
130	GO TO 236		00013000
131	233 CALL HELP1		00013100
132	GO TO 231		00013200
133	235 I = 9999		00013300
134	CALL DECODE (I,N.CODE,IN,IN2)		00013400
135	IF (CODE.EQ. 0) GO TO 231		00013500
136	WRITE (6,6) IN2		00013600
137	GO TO 236		00013700
138	234 CALL SHOW (N)		00013800
139	GO TO 231		00013900
140	C **** ALL **** HERE IF COPY ALL		00014000
141	300 WRITE (6,301)		00014100
142	301 FORMAT ('/' 'ALL' OPTION NOT SUPPORTED THIS PROGRAM' /)		00014200
143	GO TO 1000		00014300
144	C **** MOD **** HERE IF MOD CALLED		00014400
145	400 IF (IN.EQ. 0) GO TO 412		00014500
146	WRITE (6,401) 81 (N)		00014600
147	401 FORMAT ('/' MODIFY DATA FOR CDP ',A4)		00014700
148	402 WRITE (6,403)		00014800
149	403 FORMAT ('/' ENTER FIELD TO BE CHANGED')		00014900
150	404 READ (5,5) IN,IN2		00015000
151	I = 0		00015100
152	CALL DECODE (I,N.CODE,IN,IN2)		00015200
153	IF (CODE.EQ. 0) GO TO 402		00015300
154	GO TO (999,1000,410,402,411,100,200,300,400), CODE		00015400
155	WRITE (6,6) IN		00015500
156	GO TO 402		00015600
157	410 CALL HELP1		00015700
158	GO TO 402		00015800
159	411 CALL SHOW (N)		00015900
160	GO TO 402		00016000
161	412 WRITE (6,413)		00016100
162	413 FORMAT ('/' MOD INVALID- NO COURSE IN FILE')		00016200
163	GO TO 1000		00016300
164	C **** WRAPUP ****		00016400
165	999 WRITE (6,501)		00016500
166	501 FORMAT ('/' SAVE NEW DATA BASE? (Y OR N)')		00016600
167	READ (5,5) IN		00016700
168	IF (IN(1).EQ. YES) GO TO 510		00016800
169	IF (IN(1).EQ. NO) GO TO 1999		00016900
170	CALL MSG (IN,IN2)		00017000
171	GO TO (1999,1999,520,520,520,100,200,300,400), CODE		00017100
172	520 WRITE (6,6) IN		00017200
173	GO TO 999		00017300
174	510 NSAVE = N		00017400
175	DO 515 N = 1, NSAVE		00017500
176	515 WRITE (4,516) 81(N),82A(N),82B(N),83A(N),83B(N),84(N),85(N),		00017600
177	86(N),87(N),88(N),89(N),90(N),91(N),92(N),93(N),94(N),		00017700
178	95(N),96(N),97(N),98(N),99(N),100(N),101(N),102(N),103(N),		00017800
179	104(N),105(N),106(N),107(N),108(N),109(N),110(N),111(N),		00017900
180	112(N),113(N),114(N),115(N),116(N),117(N),118(N),119(N),		00018000
181	120(N),121(N),122(N),123(N),124(N),125(N),126(N),127(N),		00018100
182	128(N),129(N),130(N),131(N),132(N),133(N),134(N),135(N),		00018200
183	136(N),137(N),138(N),139(N),140(N),141(N),142(N),143(N),		00018300
184	144(N),145(N),146(N),147(N),148(N),149(N),150(N),151(N),		00018400
185	152(N),153(N),154(N),155(N),156(N),157(N),158(N),159(N),		00018500
186	160(N),161(N),162(N),163(N),164(N),165(N),166(N),167(N),		00018600
187	168(N),169(N),170(N),171(N),172(N),173(N),174(N),175(N),		00018700
188	176(N),177(N),178(N),179(N),180(N),181(N),182(N),183(N),		00018800
189	184(N),185(N),186(N),187(N),188(N),189(N),190(N),191(N),		00018900
190	192(N),193(N),194(N),195(N),196(N),197(N),198(N),199(N),		00019000
191	200(N),201(N),202(N),203(N),204(N),205(N),206(N),207(N),		00019100
192	208(N),209(N),210(N),211(N),212(N),213(N),214(N),215(N),		00019200
193	216(N),217(N),218(N),219(N),220(N),221(N),222(N),223(N),		00019300
194	224(N),225(N),226(N),227(N),228(N),229(N),230(N),231(N),		00019400
195	232(N),233(N),234(N),235(N),236(N),237(N),238(N),239(N),		00019500
196	240(N),241(N),242(N),243(N),244(N),245(N),246(N),247(N),		00019600
197	248(N),249(N),250(N),251(N),252(N),253(N),254(N),255(N),		00019700
198	256(N),257(N),258(N),259(N),260(N),261(N),262(N),263(N),		00019800
199	264(N),265(N),266(N),267(N),268(N),269(N),270(N),271(N),		00019900
200	272(N),273(N),274(N),275(N),276(N),277(N),278(N),279(N),		00020000
201	280(N),281(N),282(N),283(N),284(N),285(N),286(N),287(N),		00020100
202	288(N),289(N),290(N),291(N),292(N),293(N),294(N),295(N),		00020200
203	296(N),297(N),298(N),299(N),300(N),301(N),302(N),303(N),		00020300
204	304(N),305(N),306(N),307(N),308(N),309(N),310(N),311(N),		00020400
205	312(N),313(N),314(N),315(N),316(N),317(N),318(N),319(N),		00020500
206	320(N),321(N),322(N),323(N),324(N),325(N),326(N),327(N),		00020600
207	328(N),329(N),330(N),331(N),332(N),333(N),334(N),335(N),		00020700
208	336(N),337(N),338(N),339(N),340(N),341(N),342(N),343(N),		00020800
209	344(N),345(N),346(N),347(N),348(N),349(N),350(N),351(N),		00020900
210	352(N),353(N),354(N),355(N),356(N),357(N),358(N),359(N),		00021000
211	360(N),361(N),362(N),363(N),364(N),365(N),366(N),367(N),		00021100
212	368(N),369(N),370(N),371(N),372(N),373(N),374(N),375(N),		00021200
213	376(N),377(N),378(N),379(N),380(N),381(N),382(N),383(N),		00021300
214	384(N),385(N),386(N),387(N),388(N),389(N),390(N),391(N),		00021400
215	392(N),393(N),394(N),395(N),396(N),397(N),398(N),399(N),		00021500
216	400(N),401(N),402(N),403(N),404(N),405(N),406(N),407(N),		00021600
217	408(N),409(N),410(N),411(N),412(N),413(N),414(N),415(N),		00021700
218	416(N),417(N),418(N),419(N),420(N),421(N),422(N),423(N),		00021800
219	424(N),425(N),426(N),427(N),428(N),429(N),430(N),431(N),		00021900
220	432(N),433(N),434(N),435(N),436(N),437(N),438(N),439(N),		00022000
221	440(N),441(N),442(N),443(N),444(N),445(N),446(N),447(N),		00022100
222	448(N),449(N),450(N),451(N),452(N),453(N),454(N),455(N),		00022200
223	456(N),457(N),458(N),459(N),460(N),461(N),462(N),463(N),		00022300
224	464(N),465(N),466(N),467(N),468(N),469(N),470(N),471(N),		00022400
225	472(N),473(N),474(N),475(N),476(N),477(N),478(N),479(N),		00022500
226	480(N),481(N),482(N),483(N),484(N),485(N),486(N),487(N),		00022600
227	488(N),489(N),490(N),491(N),492(N),493(N),494(N),495(N),		00022700
228	496(N),497(N),498(N),499(N),500(N),501(N),502(N),503(N),		00022800
229	504(N),505(N),506(N),507(N),508(N),509(N),510(N),511(N),		00022900
230	512(N),513(N),514(N),515(N),516(N),517(N),518(N),519(N),		00023000
231	520(N),521(N),522(N),523(N),524(N),525(N),526(N),527(N),		00023100
232	528(N),529(N),530(N),531(N),532(N),533(N),534(N),535(N),		00023200
233	536(N),537(N),538(N),539(N),540(N),541(N),542(N),543(N),		00023300
234	544(N),545(N),546(N),547(N),548(N),549(N),550(N),551(N),		00023400
235	552(N),553(N),554(N),555(N),556(N),557(N),558(N),559(N),		00023500
236	560(N),561(N),562(N),563(N),564(N),565(N),566(N),567(N),		00023600
237	568(N),569(N),570(N),571(N),572(N),573(N),574(N),575(N),		00023700
238	576(N),577(N),578(N),579(N),580(N),581(N),582(N),583(N),		00023800
239	584(N),585(N),586(N),587(N),588(N),589(N),590(N),591(N),		00023900
240	592(N),593(N),594(N),595(N),596(N),597(N),598(N),599(N),		00024000
241	600(N),601(N),602(N),603(N),604(N),605(N),606(N),607(N),		00024100
242	608(N),609(N),610(N),611(N),612(N),613(N),614(N),615(N),		00024200
243	616(N),617(N),618(N),619(N),620(N),621(N),622(N),623(N),		00024300
244	624(N),625(N),626(N),627(N),628(N),629(N),630(N),631(N),		00024400
245	632(N),633(N),634(N),635(N),636(N),637(N),638(N),639(N),		00024500
246	640(N),641(N),642(N),643(N),644(N),645(N),646(N),647(N),		00024600
247	648(N),649(N),650(N),651(N),652(N),653(N),654(N),655(N),		00024700
248	656(N),657(N),658(N),659(N),660(N),661(N),662(N),663(N),		00024800
249	664(N),665(N),666(N),667(N),668(N),669(N),670(N),671(N),		00024900
250	672(N),673(N),674(N),675(N),676(N),677(N),678(N),679(N),		00025000
251	680(N),681(N),682(N),683(N),684(N),685(N),686(N),687(N),		00025100
252	688(N),689(N),690(N),691(N),692(N),693(N),694(N),695(N),		00025200
253	696(N),697(N),698(N),699(N),700(N),701(N),702(N),703(N),		00025300
254	704(N),705(N),706(N),707(N),708(N),709(N),710(N),711(N),		00025400
255	712(N),713(N),714(N),715(N),716(N),717(N),718(N),719(N),		00025500
256	720(N),721(N),722(N),723(N),724(N),725(N),726(N),727(N),		00025600
257	728(N),729(N),730(N),731(N),732(N),733(N),734(N),735(N),		00025700
258	736(N),737(N),738(N),739(N),740(N),741(N),742(N),743(N),		00025800
259	744(N),745(N),746(N),747(N),748(N),749(N),750(N),751(N),		00025900
260	752(N),753(N),754(N),755(N),756(N),757(N),758(N),759(N),		00026000
261	760(N),761(N),762(N),763(N),764(N),765(N),766(N),767(N),		00026100
262	768(N),769(N),770(N),771(N),772(N),773(N),774(N),775(N),		00026200
263	776(N),777(N),778(N),779(N),780(N),781(N),782(N),783(N),		00026300
264	784(N),785(N),786(N),787(N),788(N),789(N),790(N),791(N),		00026400
265	792(N),793(N),794(N),795(N),796(N),797(N),798(N),799(N),		00026500
266	800(N),801(N),802(N),803(N),804(N),805(N),806(N),807(N),		00026600
267	808(N),809(N),810(N),811(N),812(N),813(N),814(N),815(N),		00026700
268	816(N),817(N),818(N),819(N),820(N),821(N),822(N),823(N),		00026800
269	824(N),825(N),826(N),827(N),828(N),829(N),830(N),831(N),		00026900
270	832(N),833(N),834(N),835(N),836(N),837(N),838(N),839(N),		00027000
271	840(N),841(N),842(N),843(N),844(N),845(N),846(N),847(N),		00027100
272	848(N),849(N),850(N),851(N),852(N),853(N),854(N),855(N),		00027200
273	856(N),857(N),858(N),859(N),860(N),861(N),862(N),863(N),		00027300
274	864(N),865(N),866(N),867(N),868(N),869(N),870(N),871(N),		00027400
275	872(N),873(N),874(N),875(N),876(N),877(N),878(N),879(N),		00027500
276	880(N),881(N),882(N),883(N),884(N),885(N),886(N),887(N),		00027600
277	888(N),889(N),890(N),891(N),892(N),893(N),894(N),895(N),		00027700
278	896(N),897(N),898(N),899(N),900(N),901(N),902(N),903(N),		00027800
279	904(N),905(N),906(N),907(N),908(N),909(N),910(N),911(N),		00027900
280	912(N),913(N),914(N),915(N),916(N),917(N),918(N),919(N),		00028000
281	920(N),921(N),922(N),923(N),924(N),925(N),926(N),927(N),		00028100
282	928(N),929(N),930(N),931(N),932(N),933(N),934(N),935(N),		00028200
283	936(N),937(N),938(N),939(N),940(N),941(N),942(N),943(N),		00028300
284	944(N),945(N),946(N),947(N),948(N),949(N),950(N),951(N),		00028400
285	952(N),953(N),954(N),955(N),956(N),957(N),958(N),959(N),		00028500
286	960(N),961(N),962(N),963(N),964(N),965(N),966(N),967(N),		00028600
287	968(N),969(N),970(N),971(N),972(N),973(N),974(N),975(N),		00028700
288	976(N),977(N),978(N),979(N),980(N),981(N),982(N),983(N),		00028800
289	984(N),985(N),986(N),987(N),988(N),989(N),990(N),991(N),		00028900
290	992(N),993(N),994(N),995(N),996(N),997(N),998(N),999(N),		00029000
291	1000(N),1001(N),1002(N),1003(N),1004(N),1005(N),1006(N),		00029100
292	1007(N),1008(N),1009(N),1010(N),1011(N),1012(N),1013(N),		00029200
293	1014(N),1015(N),1016(N),1017(N),1018(N),1019(N),1020(N),		00029300
294	1021(N),1022(N),1023(N),1024(N),1025(N),1026(N),1027(N),		00029400
295	1028(N),1029(N),1030(N),1031(N),1032(N),1033(N),		

TAEG REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

LISTING - SUBROUTINE DECODE

FORTTRAN MODULE

(LIST,NAMSQ,SOURCE)

CARD NO

CONTENTS

```

1      C DECODE SUBROUTINE FOR TPF WHAT IF? 22MAY75
2      SUBROUTINE DECODE (I,RESP,IN,IN2)
3      IMPLICIT INTEGER*2 (I)
4      INTEGER*4 81,816,835,836
5      REAL*4 85,811,812,813,814,818,825,831,832
6      REAL*8 82A,83A,83B
7
8      C
9      COMMON /A/ 81(144),82A(144),83A(144),84(144),85(144),86(144)
10     COMMON /A/ 87(144),88(144),89(144),810(144),811(144),812(144)
11     COMMON /A/ 813(144),814(144),815(144),816(144),817(144),818(144)
12     COMMON /A/ 819(144),820(144),821(144),822(144),823(144),824(144)
13     COMMON /A/ 825(144),826(144),827(144),828(144),829(144),830(144)
14     COMMON /A/ 831(144),832(144),833(144),834(144),835(144),836(144)
15     COMMON /A/ 82B(144),83B(144)
16     INTEGER*2 NUM (5) /590/, CODE, TYPE (36), DEC, INT, ALPHA
17     DATA TYPE /3*'A', 7*'I', 4*'F', 1*'S', 'A', 13*'I', 'F', 4*'A' /
18     DATA ALPHA /'A'/'/' INT /'I'/'/' DEC /'F'/'/'
19     REAL*8 ALPHA1, ALPHA2
20     INTEGER*4 ANS, A4 (2),QUIT/'QUIT'/'',DONE/'DONE'/'',HELP/'HELP'/'',SHOW/'SHOW'/''
21     *SHOW/'/'
22     INTEGER*2 IN (5),IN2(5),F (5,36), COP (5), CTLG (5), CRS (5)
23     INTEGER*2 BOMD1 (5), C5T (5), PFAIL (5), NADIS (5), NOSHO (5)
24     INTEGER*2 SETB (5), BKLG (5), JND (5), CONV2 (5), LEN2 (5)
25     INTEGER*2 CAP2 (5), BCAP2 (5), DMD2 (5), BOMD2 (5), CHWK2 (5)
26     INTEGER*2 CONV3 (5), LEN3 (5), CAP3 (5), BCAP3 (5), DMD3 (5)
27     INTEGER*2 BOMD3 (5), CHWK3 (5), PAOB (5), AFAIL (5), PRTY (5)
28     INTEGER*2 CTYPE (5), PNEC (5), SCH (5), BLANK /' ' /
29     INTEGER*2 RESP, SIZE (36), A2 (4), NA2 (4)
30     DATA SIZE /4, 10, 18, 3, 4, 293, 295, 2, 495, 294, 3, 4,
31     * 293, 295, 293, 4, 293, 295, 3, 4, 3, 292, 294 /
32     EQUIVALENCE (A2,ALPHA1), (A4,ALPHA2), (NA2,ALPHA2)
33     EQUIVALENCE (COP, F(1,1)), (CTLG, F(1,2)), (CRS, F(1,3))
34     EQUIVALENCE (CONV1, F(1,4)), (LEN1, F(1,5)), (CAP1, F(1,6))
35     EQUIVALENCE (BCAP1, F(1,7)), (DMD1, F(1,8)), (BOMD1, F(1,9))
36     EQUIVALENCE (OFST, F(1,10)), (PFAIL, F(1,11)), (NADIS, F(1,12))
37     EQUIVALENCE (NOSHO, F(1,13)), (SETB, F(1,14)), (BKLG, F(1,15))
38     EQUIVALENCE (JND, F(1,16)), (CONV2, F(1,17)), (LEN2, F(1,18))
39     EQUIVALENCE (CAP2, F(1,19)), (BCAP2, F(1,20)), (DMD2, F(1,21))
40     EQUIVALENCE (BOMD2, F(1,22)), (CHWK2, F(1,23)), (CONV3, F(1,24))
41     EQUIVALENCE (LEN3, F(1,25)), (CAP3, F(1,26)), (BCAP3, F(1,27))
42     EQUIVALENCE (DMD3, F(1,28)), (BOMD3, F(1,29)), (CHWK3, F(1,30))
43     EQUIVALENCE (PAOB, F(1,31)), (AFAIL, F(1,32)), (PRTY, F(1,33))
44     EQUIVALENCE (CTYPE, F(1,34)), (PNEC, F(1,35)), (SCH, F(1,36))
45     DATA COP/'C','D','P','S',' ',' ',' ','CTLG/'C','T','L','G',' ',' /
46     DATA CRS/'C','R','S',' ',' ',' ','CONV1/'C','O','N','V','1',' /
47     DATA LEN1/'L','E','N','1',' ',' ','CAP1/'C','A','P','1',' ',' /
48     DATA BCAP1/'B','C','A','P','1',' ',' ','DMD1/'D','M','D','1',' ',' /
49     DATA BOMD1/'B','O','M','D','1',' ',' ','OFST/'O','F','S','T',' ',' /
50     DATA PFAIL/'P','F','A','I','L',' ',' ','NADIS/'N','A','D','I','S',' /
51     DATA NOSHO/'N','O','S','H','O',' ',' ','SETB/'S','E','T','B',' ',' /
52     DATA SCH/'S','C','H',' ',' ','BKLG/'B','K','L','G',' ',' /
53     DATA JND/'J','N','D',' ',' ','CONV2/'C','O','N','V','2',' /
54     DATA LEN2/'L','E','N','2',' ',' ','CAP2/'C','A','P','2',' /
55     DATA BCAP2/'B','C','A','P','2',' ',' ','DMD2/'D','M','D','2',' /
56     DATA BOMD2/'B','O','M','D','2',' ',' ','CHWK2/'C','H','W','K','2',' /
57     DATA CONV3/'C','O','N','V','3',' ',' ','LEN3/'L','E','N','3',' /
58     DATA CAP3/'C','A','P','3',' ',' ','BCAP3/'B','C','A','P','3',' /
59     DATA DMD3/'D','M','D','3',' ',' ','BOMD3/'B','O','M','D','3',' /
60     DATA CHWK3/'C','H','W','K','3',' ',' ','PAOB/'P','A','O','B',' /
61     DATA AFAIL/'A','F','A','I','L',' ',' ','PRTY/'P','R','T','Y',' /
62     DATA CTYPE/'C','T','Y','P','E',' ',' ','PNEC/'P','N','E','C',' /
63     RESP = 0
64     ISAVE = 1
65     NEWFL = 1
66     IF (I .EQ. 9999) I = 0
67     C IF I HAS VALUE ALREADY KNOW CODE- SKIP
68     IF (I .GT. 0) GO TO 100
69     C DONT KNOW IF FIELD OR MSG- SSE IF MSG
70     NEWFL = 0
71     CALL MSG (IN,CODE)
72     IF (CODE .GE. 98) GO TO 905
73     C HERE IF MSG- SEE IF STAT
74     IF (CODE .EQ. 4) GO TO 900
75     C NOT STAT- RETURN FROM SUBR WITH MSG CODE
76     RESP = CODE
77     GO TO 999
78     C **** STAT **** - LOAD IN2 INTO IN
79     900 DO 902 J = 1,5
80     902 IN(J) = IN2(J)
81     ISAVE = 9999
82     C SEARCH OUT FIELD NUMBER
83     905 DO 910 J = 1,36
84     910 K = 1,5
85     IF (IN(K) .NE. F (IN,J)) GO TO 910
86     911 CONTINUE
87     I = J
88     IF (ISAVE .EQ. 9999) GO TO 200
89     GO TO 930
90     910 CONTINUE
91     RESP = 99
92     GO TO 999
93     C FIELD VALID- TEST IF DATA IN SECOND WORD
94     950 DO 960 J = 1,5
95     IF (IN2(J) .NE. BLANK) GO TO 970
96     960 CONTINUE
97     C HERE IF BLANK FIELD- GO AND READ INPUT DATA
98     GO TO 100
99     C HERE IF SECOND DATA FIELD- BLANK DELIMIT
100    970 K = 0
101    DO 980 J = 1,5
102    980 J = BLANK
103    IF (IN2(J) .EQ. BLANK) GO TO 980
104    K = K + 1
105    NUM (K) = IN2 (J)
106    980 CONTINUE
107    GO TO 985
108    C **** PROMPT DATA ENTRY ****
109    100 WRITE (6,101) IF (J,1),J = 1,5), TYPE (I), SIZE (I)

```

TABLE V-6

V-60

500

TAEG REPORT NO. 29

08/16/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

CARD NO	*****	CONTENTS	*****
110		101 FORMAT (I) *ENTER 'SAL, 2X, '(I',A1, 12, '))	00011000
111		IF (TYPE (I) .EQ. ALPHA) GO TO 110	00011100
112		READ (5,102) NUM, INZ	00011200
113		102 FORMAT (10A1)	00011300
114		885 CALL CONVRT (NUM,ANS,CODE,DECIMAL)	00011400
115		IF (CODE .EQ. 10) GO TO 105	00011500
116		IF (CODE .EQ. 0) DECIMAL = ANS	00011600
117		GO TO 118	00011700
118		105 CALL MSG (NUM, CODE)	00011800
119		IF (CODE .LT. 98) GO TO 108	00011900
120		C HERE IF MSG DID NOT RECOGNIZE TEXT (CODE=99), PRINT ERROR	00012000
121		IF (NEWPL .GT. 0) GO TO 1106	00012100
122		DO 1107 J = 1,5	00012200
123		1107 IN (J) = NUM (J)	00012300
124		GO TO 905	00012400
125		1106 WRITE (6,106) NUM	00012500
126		106 FORMAT (1X, SA1, ' *INVALID- RETRY'/)	00012600
127		GO TO 100	00012700
128		108 RESP = CODE	00012800
129		IF (CODE .EQ. 4) GO TO 900	00012900
130		GO TO 999	00013000
131		110 READ (5,111) ALPHA1, ALPHA2	00013100
132		111 FORMAT (2AB)	00013200
133		RESP = 0	00013300
134		IF (A4 (1) .EQ. QUIT) RESP = 1	00013400
135		IF (A4 (1) .EQ. DONE) RESP = 2	00013500
136		IF (A4 (1) .EQ. HELP) RESP = 3	00013600
137		IF (A4 (1) .EQ. SHOW) RESP = 5	00013700
138		IF (RESP .NE. 0) GO TO 999	00013800
139		IF (SIZE (I) .EQ. 4) GO TO 112	00013900
140		IF (SIZE (I) .EQ. 2) GO TO 113	00014000
141		IF (SIZE (I) .EQ. 10) GO TO 114	00014100
142		IF (SIZE (I) .EQ. 16) WRITE (6,1111) ALPHA1, ALPHA2	00014200
143		1111 FORMAT (1X,2AB)	00014300
144		GO TO 121	00014400
145		112 WRITE (6,115) A4 (1)	00014500
146		115 FORMAT (1X,A4)	00014600
147		GO TO 121	00014700
148		113 WRITE (6,116) A2 (1)	00014800
149		116 FORMAT (1X,A2)	00014900
150		GO TO 121	00015000
151		114 WRITE (6,117) ALPHA1,ALPHA2 (1)	00015100
152		117 FORMAT (1X, AB, A2)	00015200
153		GO TO 121	00015300
154		118 IF (TYPE (I) .EQ. DEC) GO TO 1118	00015400
155		C HERE IF INTEGER	00015500
156		ITEST = 10 ** SIZE (I)	00015600
157		IF (ANS .GE. ITEST) GO TO 1119	00015700
158		IF (ANS .GT. 32768) GO TO 1119	00015800
159		WRITE (6,119) ANS	00015900
160		GO TO 121	00016000
161		1119 WRITE (6,120) ANS	00016100
162		120 FORMAT (1X,15, ' TOO LARGE- RETRY'/)	00016200
163		GO TO 100	00016300
164		1118 WRITE (6,120) DECIMAL	00016400
165		119 FORMAT (1X, 15)	00016500
166		120 FORMAT (F9,3)	00016600
167		121 CONTINUE	00016700
168		C **** WRITE TO CRS ****	00016800
169		IF (I .GT. 10) GO TO 710	00016900
170		GO TO (1,2,3,4,5,6,7,8,9,10),I	00017000
171		1 81(IN) = A4(I)	00017100
172		GO TO 999	00017200
173		2 82(IN) = A2(I)	00017300
174		82B(IN) = A2 (I)	00017400
175		GO TO 999	00017500
176		3 83A(IN) = ALPHA1	00017600
177		83B(IN) = ALPHA2	00017700
178		GO TO 999	00017800
179		4 84 (IN) = ANS	00017900
180		GO TO 999	00018000
181		5 85 (IN) = ANS	00018100
182		GO TO 999	00018200
183		6 86 (IN) = ANS	00018300
184		GO TO 999	00018400
185		7 87(IN) = ANS	00018500
186		GO TO 999	00018600
187		8 88 (IN) = ANS	00018700
188		GO TO 999	00018800
189		9 89(IN) = ANS	00018900
190		GO TO 999	00019000
191		10 910(IN) = ANS	00019100
192		GO TO 999	00019200
193		710 IF (I .GT. 20) GO TO 720	00019300
194		II = I - 10	00019400
195		GO TO (11,12,13,14,15,16,17,18,19,20),II	00019500
196		11 911(IN) = DECIMAL	00019600
197		GO TO 999	00019700
198		12 912(IN) = DECIMAL	00019800
199		GO TO 999	00019900
200		13 913(IN) = DECIMAL	00020000
201		GO TO 999	00020100
202		14 914(IN) = DECIMAL	00020200
203		GO TO 999	00020300
204		15 915 (IN) = ANS	00020400
205		GO TO 999	00020500
206		16 916(IN) = A4(I)	00020600
207		GO TO 999	00020700
208		17 917 (IN) = ANS	00020800
209		GO TO 999	00020900
210		18 918(IN) = ANS	00021000
211		GO TO 999	00021100
212		19 919(IN) = ANS	00021200
213		GO TO 999	00021300
214		20 920(IN) = ANS	00021400
215		GO TO 999	00021500
216		720 II = I - 20	00021600
217		GO TO (21,22,23,24,25,26,27,28,29,30,31,32,33,34,35,36),II	00021700
218		21 921(IN) = ANS	00021800
219		GO TO 999	00021900
220		22 922(IN) = ANS	00022000
221		GO TO 999	00022100

TABLE V-6 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

CARD NO

CONTENTS

222	23 823(N) = ANS	00022200
223	GO TO 999	00022300
224	24 824 (N) = ANS	00022400
225	GO TO 999	00022500
226	25 825(N) = ANS	00022600
227	GO TO 999	00022700
228	26 826(N) = ANS	00022800
229	GO TO 999	00022900
230	27 827(N) = ANS	00023000
231	GO TO 999	00023100
232	28 828(N) = ANS	00023200
233	GO TO 999	00023300
234	29 829(N) = ANS	00023400
235	GO TO 999	00023500
236	30 830(N) = ANS	00023600
237	GO TO 999	00023700
238	31 831(N) = ANS	00023800
239	GO TO 999	00023900
240	32 832 (N) = DECIMAL	00024000
241	GO TO 999	00024100
242	33 833(N) = ANS	00024200
243	GO TO 999	00024300
244	34 834(N) = A2(I)	00024400
245	GO TO 999	00024500
246	35 835(N) = A4(I)	00024600
247	GO TO 999	00024700
248	36 836(N) = A4(I)	00024800
249	GO TO 999	00024900
250	(** - STAT **** SHOW (STAT EQUATIONS - HERE IF HAVE FOUND FIELD	00025000
251	200 IF (I .GT. 10) GO TO 210	00025100
252	GO TO (301,302,303,304,305,306,307,308,309,310),I	00025200
253	301 A4(I) = 81(N)	00025300
254	GO TO 404	00025400
255	302 ALPHA1 = 82A(N)	00025500
256	NA2(I) = 82B (N)	00025600
257	GO TO 410	00025700
258	303 ALPHA1 = 83A(N)	00025800
259	ALPHA2 = 83B(N)	00025900
260	GO TO 416	00026000
261	304 ANS = 84 (N)	00026100
262	GO TO 400	00026200
263	305 DECIMAL = 85(N)	00026300
264	GO TO 401	00026400
265	306 ANS = 86(N)	00026500
266	GO TO 400	00026600
267	307 ANS = 87(N)	00026700
268	GO TO 400	00026800
269	308 ANS = 88(N)	00026900
270	GO TO 400	00027000
271	309 ANS = 89(N)	00027100
272	GO TO 400	00027200
273	310 ANS = 90(N)	00027300
274	GO TO 400	00027400
275	210 IF (I .GT. 20) GO TO 220	00027500
276	II = I - 10	00027600
277	GO TO (311,312,313,314,315,316,317,318,319,320),II	00027700
278	311 DECIMAL = 91(N)	00027800
279	GO TO 401	00027900
280	312 DECIMAL = 92(N)	00028000
281	GO TO 401	00028100
282	313 DECIMAL = 93(N)	00028200
283	GO TO 401	00028300
284	314 DECIMAL = 94(N)	00028400
285	GO TO 401	00028500
286	315 ANS = 95(N)	00028600
287	GO TO 400	00028700
288	316 A4(I) = 96(N)	00028800
289	GO TO 404	00028900
290	317 ANS = 97(N)	00029000
291	GO TO 400	00029100
292	318 DECIMAL = 98(N)	00029200
293	GO TO 401	00029300
294	319 ANS = 99(N)	00029400
295	GO TO 400	00029500
296	320 ANS = 100(N)	00029600
297	GJ TO 400	00029700
298	220 II = I - 20	00029800
299	GO TO (321,322,323,324,325,326,327,328,329,330,331,332,333,334,335,336,337,338,339,340,341,342,343,344,345,346,347,348,349,350,351,352,353,354,355,356,357,358,359,360,361,362,363,364,365,366,367,368,369,370,371,372,373,374,375,376,377,378,379,380,381,382,383,384,385,386,387,388,389,390,391,392,393,394,395,396,397,398,399,400),II	00029900
300	321 ANS = 101(N)	00030000
301	GO TO 400	00030100
302	322 ANS = 102(N)	00030200
303	GO TO 400	00030300
304	323 ANS = 103(N)	00030400
305	GO TO 400	00030500
306	324 ANS = 104(N)	00030600
307	GO TO 400	00030700
308	325 DECIMAL = 105(N)	00030800
309	GO TO 401	00030900
310	326 ANS = 106(N)	00031000
311	GO TO 400	00031100
312	327 ANS = 107(N)	00031200
313	GO TO 400	00031300
314	328 ANS = 108(N)	00031400
315	GO TO 400	00031500
316	329 ANS = 109(N)	00031600
317	GO TO 400	00031700
318	330 ANS = 110(N)	00031800
319	GO TO 400	00031900
320	331 DECIMAL = 111(N)	00032000
321	GO TO 401	00032100
322	332 DECIMAL = 112(N)	00032200
323	GO TO 401	00032300
324	333 A2(I) = 113(N)	00032400
325	GO TO 402	00032500
326	334 A2(I) = 114(N)	00032600
327	GO TO 402	00032700
328	335 A4(I) = 115(N)	00032800
329	GO TO 404	00032900
330	336 A4(I) = 116(N)	00033000
331	GO TO 404	00033100
332	400 WRITE (6,500) (F(J),J = 1,5),ANS	00033200
333		00033300

TABLE V-6 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-DECODE- FLOWCHARTS

CARD NO	*****	CONTENTS	*****
334	500	FORMAT (/2X,5A1,1X,15/)	00033400
335		GO TO 999	00033500
336	401	WRITE (6,501) (F (J,1),J = 1,5),DECIMAL	00033600
337	501	FORMAT (/2X,5A1,F9.3/)	00033700
338		GO TO 999	00033800
339	404	WRITE (6,504) (F (J,1),J = 1,5),A4(1)	00033900
340	504	FORMAT (/2X,5A1,2X,A4/)	00034000
341		GO TO 999	00034100
342	402	WRITE (6,502) (F (J,1),J = 1,5),A2(1)	00034200
343	502	FORMAT (/2X,5A1,A2,/)	00034300
344		GO TO 999	00034400
345	410	WRITE (6,510) (F (J,1),J = 1,5),ALPHA1,MA2(1)	00034500
346	510	FORMAT (/2X,5A1,A8,A2/)	00034600
347		GO TO 999	00034700
348	416	WRITE (6,516) (F (J,1),J = 1,5),ALPHA1,ALPHA2	00034800
349	516	FORMAT (/2X,5A1,A8,A8/)	00034900
350	999	RETURN	00035000
351		END	00035100

TABLE V-6 (CONTINUED)

TAEG REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-CONVRT- FLOWCHARTS

LISTING - SUBROUTINE CONVRT

FORTRAN MODULE

(LIST, NAME, SOURCE)

CARD NO

CONTENTS

1	C CONVERSION SUBROUTINE - UPDATE 20MAY75	00000100
2	C CONVERSION OF 5 DIGIT CHARACTER TO NUM	00000200
3	C RETURN CODE 0 FOR VALID CONVERT, 10 FOR INVALID	00000300
4	SUBROUTINE CONVRT (IN, ANS, CODE, DECHAL)	00000400
5	INTEGER*2 IN (5), WORK (10), CODE	00000500
6	INTEGER*4 UPLIN, LOLIN, BLANK, HOLD (5), TEST, OUT (5), ANS, POINT	00000600
7	EQUIVALENCE (HOLD, WORK)	00000700
8	DATA WORK/10*0/, TEST/ZF000/, UPLIN/ZF940/, LOLIN/ZF040/, BLANK/Z4040/	00000800
9	DATA POINT /Z4840/	00000900
10	ANS = 0	00001000
11	PLG = 0	00001100
12	FRAC = 0	00001200
13	J = 1	00001300
14	DO 33 I = 1, 5	00001400
15	K = I + 1	00001500
16	33 WORK (K) = IN (I)	00001600
17	K = 1	00001700
18	C CONVERT LOOP	00001800
19	35 DO 100 I = K, 5	00001900
20	IF (HOLD (I)) .EQ. BLANK) GO TO 200	00002000
21	IF (HOLD (I)) .NE. POINT) GO TO 40	00002100
22	IF (PLG .GT. 0) GO TO 300	00002200
23	PLG = 1	00002300
24	GO TO 200	00002400
25	40 IF (HOLD (I)) .GT. UPLIN) GO TO 300	00002500
26	IF (HOLD (I)) .LT. LOLIN) GO TO 300	00002600
27	C HERE IF VALID NUM	00002700
28	100 OUT (I) = (HOLD (I) - TEST) / 256	00002800
29	GO TO 210	00002900
30	C ASSEMBLE ANSWER-SET K IN CASE OF DECIMAL AT I	00003000
31	200 K = I + 1	00003100
32	201 I = I - 1	00003200
33	210 IF (PLG .GT. 1) GO TO 240	00003300
34	IF (I) 250, 250, 220	00003400
35	220 ANS = ANS + (OUT (I) * J)	00003500
36	J = J * 10	00003600
37	GO TO 201	00003700
38	C END ANSWER LOOP	00003800
39	C TEST IF REAL OR FRAC	00003900
40	250 IF (PLG .LE. 0) GO TO 295	00004000
41	C HERE IF HAVE DECODED REAL PORTION-NOW GET FRACTION	00004100
42	IF (K .GT. 5) GO TO 275	00004200
43	K1 = K	00004300
44	PLG = 2	00004400
45	GO TO 35	00004500
46	C FRACTION LOOP	00004600
47	240 A = 1	00004700
48	DO 270 L = K1, 1	00004800
49	IF (I - L) .LT. 0) GO TO 275	00004900
50	A = A * .1	00005000
51	270 FRAC = FRAC + (OUT (L) * A)	00005100
52	275 DECHAL = ANS + FRAC	00005200
53	CODE = 5	00005300
54	RETURN	00005400
55	C VALID INTEGER -RETURN	00005500
56	295 CODE = 0	00005600
57	RETURN	00005700
58	C ALPHA - SET ERROR	00005800
59	300 CODE = 10	00005900
60	RETURN	00006000
61	END	00006100

TABLE V-7 (CONTINUED)

TAEQ REPORT NO. 29

08/ 75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-MSG- FLOWCHARTS

LISTING - SUBROUTINE MSG

FORTAN MODULE

(LIST, NAME, SUBROUTINE)

CARD NO

CONTENTS

1	C SUBROUTINE TO DECODE TEXT MSG FOR 'WHAT IF' (TPF) 13JUN75	00000100
2	C CODE- QUIT (1), DONE (2), HELP (3), STAT (4), SHOW (5), COPY (6),	00000200
3	C NEW (7), ALL (8), MOD (9), CODE NOT RECOGNIZED (99)	00000300
4	SUBROUTINE MSG (IN, CODE)	00000400
5	INTEGER*2 F(4,9), IN(5), CODE, QUIT(4), DONE(4), HELP(4), STAT(4)	00000500
6	INTEGER*2 SHOW (4), COPY (4), NEW (4), ALL (4), MOD (4)	00000600
7	EQUIVALENCE (QUIT,F(1,1)), (DONE,F(1,2)), (HELP,F(1,3)), (NEW,F(1,7))	00000700
8	EQUIVALENCE (SHOW,F(1,5)), (COPY,F(1,6)), (ALL,F(1,8)), (MOD,F(1,9))	00000800
9	EQUIVALENCE (STAT,F(1,4))	00000900
10	DATA QUIT /'Q','U','I','T'/. DONE /'D','O','N','E'.	00001000
11	DATA HELP /'H','E','L','P'/. SHOW /'S','H','O','W'.	00001100
12	DATA COPY /'C','O','P','Y'/. NEW /'N','E','W',''.	00001200
13	DATA ALL /'A','L','L',''/. MOD /'M','O','D',''.	00001300
14	DATA STAT /'S','T','A','T'.	00001400
15	CODE = 99	00001500
16	DO 2 I = 1,9	00001600
17	DO 1 J = 1,4	00001700
18	IF (IN (J) .NE. F(I,J,1)) GO TO 2	00001800
19	1 CONTINUE	00001900
20	C HERE IF VALID COMPARE ON ALL 5 CHARACTERS	00002000
21	CODE = 1	00002100
22	GO TO 99	00002200
23	2 CONTINUE	00002300
24	99 RETURN	00002400
25	END	00002500

TABLE V-8

TAEQ REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-SHOW- FLOWCHARTS

LISTING - SUBROUTINE SHOW

FORTRAN MODULE

(LIST,NAMSQ,SOURCEQ)

CARD NO	CONTENTS	
1	C DISPLAY CURRENT COURSE (TPFMOD), N IS CRS NO IN FILE 13JUN75	00000100
2	SUBROUTINE SHOW (N)	00000200
3	IMPLICIT INTEGER*2 (I)	00000300
4	INTEGER*4 I1,I10,I35,I36	00000400
5	REAL*4 I5,I11,I12,I13,I14,I18,I25,I31,I32	00000500
6	REAL*8 I2A,I3A,I3B	00000600
7	COMMON /A/ I1(144),I2A(144),I3A(144),I4(144),I5(144),I6(144)	00000700
8	COMMON /A/ I7(144),I8(144),I9(144),I10(144),I11(144),I12(144)	00000800
9	COMMON /A/ I13(144),I14(144),I15(144),I16(144),I17(144),I18(144)	00000900
10	COMMON /A/ I19(144),I20(144),I21(144),I22(144),I23(144),I24(144)	00001000
11	COMMON /A/ I25(144),I26(144),I27(144),I28(144),I29(144),I30(144)	00001100
12	COMMON /A/ I31(144),I32(144),I33(144),I34(144),I35(144),I36(144)	00001200
13	COMMON /A/ I2B(144),I3B(144)	00001300
14	INTEGER*2 IN (5) /500/, BLANK // '//, CODE	00001400
15	I = N	00001500
16	IF (I .LE. 0) GO TO 998	00001600
17	IF (I .GT. 144) GO TO 998	00001700
18	1 WRITE (6,2)	00001800
19	2 FORMAT (17 'SHOW: ENTER ALL OR FIELD NAME')	00001900
20	READ (5,3) IN	00002000
21	3 FORMAT (5A1)	00002100
22	CALL MSG (IN, CODE)	00002200
23	GO TO (999,999,10,10,10,10,10,10,10,10), CODE	00002300
24	C HERE IF NOT RECOGNIZED-TEST IF BLANK(A RETURN)	00002400
25	IF (IN (1) .EQ. BLANK) GO TO 100	00002500
26	C NOT RECOGNIZED MSG OR BLANK-TEST IF FIELD NAME	00002600
27	NM = 9999	00002700
28	CALL DECODE (NM,N,CODE,IN)	00002800
29	IF (CODE .EQ. 0) GO TO 999	00002900
30	10 WRITE (6,11) IN	00003000
31	11 FORMAT (1X,5A1,' *INVALID- RETRY//')	00003100
32	GO TO 1	00003200
33	C ****SHOW ALL ****	00003300
34	100 I = N	00003400
35	C CALC STU BKLG- 84 CONV; 86 CAP; 87 BCAP; 815 BKLG WKS	00003500
36	NBKL = 0	00003600
37	IF (I4(1)) .LE. 0) GO TO 299	00003700
38	ICAP = I6(1) - I7(1)	00003800
39	IF (ICAP .LE. 0) GO TO 299	00003900
40	GNVB = 50. /I4(1)	00004000
41	NBKL = I5(1)/GNVB * ICAP	00004100
42	299 CONTINUE	00004200
43	C **** PRINT IT ****	00004300
44	WRITE (6,4001) I1(1),I3A(1),I3B(1)	00004400
45	WRITE (6,4002) I4(1),I7(1),I2A(1),NBKL	00004500
46	WRITE (6,4003) I5(1),I18(1),I25(1),I15(1)	00004600
47	WRITE (6,4004) I36(1),I16(1),I2A(1),I2B(1),I35(1)	00004700
48	* I36(1),I19(1),I26(1)	00004800
49	WRITE (6,4005) I7(1),I20(1),I27(1),I25(1)	00004900
50	WRITE (6,4006) I8(1),I21(1),I28(1),I30(1)	00005000
51	WRITE (6,4007) I31(1),I32(1),I34(1),I33(1),I9(1),I22(1),I29(1)	00005100
52	* I31(1)	00005200
53	RATEA = I11(1) * 100.	00005300
54	RATEB = I12(1) * 100.	00005400
55	RATEC = I13(1) * 100.	00005500
56	WRITE (6,4008) RATEA, RATEB, RATEC	00005600
57	4001 FORMAT (171X,A4, 5X, 2A8, 4X, '---SCHEDULE DATA-- FY FY+1 FY+2	00005700
58	2 CR5 BACKLOG')	00005800
59	4002 FORMAT (17 'T31, 'ANNUAL CONVENINGS', 15, 217, 4X, '8 STU', 15)	00005900
60	4003 FORMAT (17 'SCHL JMD CATALOG NO NEC COURSE LENGTH DYS', F5.1,	00006000
61	* 2F7.1, 4X, '8 WKS', 15)	00006100
62	4004 FORMAT (17 '2 (A4, 1X), A8, A2, 1X, A4, 4X, 'COURSE CAPACITY',	00006200
63	* 317)	00006300
64	4005 FORMAT (17 'T31, 'SUPERS CAPACITY', 317, 3X, 'FY+1 WK', 14)	00006400
65	4006 FORMAT (17 'P ROB PFAIL TYPE PRTY ANNUAL DEMAND', 2X, 317,	00006500
66	* 3X, 'FY+2 WK', 14)	00006600
67	4007 FORMAT (17 'F5.1, F6.1, 4X, 3X,A2,5X,A2,5X, 'SUPERS DEMAND',	00006700
68	* 2X, 317, 3X, 'OFFSET', 15)	00006800
69	4008 FORMAT (17 'RATES: FAIL',F5.1,'%: NADIS',F5.1,'%: NDSHOW',F5.1,'	00006900
70	*////)	00007000
71	GO TO 999	00007100
72	998 WRITE (6,98) I	00007200
73	98 FORMAT (1X,13,' COURSE NOT IN PROCESS- SHOW SKIPPED//')	00007300
74	999 RETURN	00007400
75	END	00007500
76	BLOCK DATA	00007600
77	IMPLICIT INTEGER*2 (I)	00007700
78	INTEGER*4 I1,I10,I35,I36	00007800
79	REAL*4 I5,I11,I12,I13,I14,I18,I25,I31,I32	00007900
80	REAL*8 I2A,I3A,I3B	00008000
81	COMMON /A/ I1(144),I2A(144),I3A(144),I4(144),I5(144),I6(144)	00008100
82	COMMON /A/ I7(144),I8(144),I9(144),I10(144),I11(144),I12(144)	00008200
83	COMMON /A/ I13(144),I14(144),I15(144),I16(144),I17(144),I18(144)	00008300
84	COMMON /A/ I19(144),I20(144),I21(144),I22(144),I23(144),I24(144)	00008400
85	COMMON /A/ I25(144),I26(144),I27(144),I28(144),I29(144),I30(144)	00008500
86	COMMON /A/ I31(144),I32(144),I33(144),I34(144),I35(144),I36(144)	00008600
87	COMMON /A/ I2B(144),I3B(144)	00008700
88	DATA I1,I10,I35,I36/5760* '//,I2A,I3A,I3B/4320* '//,I2B/' //	00008800
89	DATA I5,I11,I12,I13,I14,I18,I25,I31,I32 /129600, /	00008900
90	DATA I4,I9,I7,I8,I9,I10,I15,I17,I19,I20,I21,I22,I23,I24,I25,	00009000
91	I1,I27,I28,I29,I30,I34 /2880 * 0/, I33 /' //	00009100
92	END	00009200

TABLE V-9

512

V-66

SUBROUTINE COMND LISTING

COMND	START	
	STM	14,12,12(13)
	BALR	12,0
	USING	*,12
	LM	3,4,0(1)
	LH	5,0(3)
	C	5,=F'17'
	MVC	0(2,4),=X'0001'
	BC	2,END
	LA	7,TAB1
	AR	5,7
	MVC	MSG+1(1),0(5)
	LA	L,PLIST
	SVC	X'CA'
	DC	AL4(ERR)
	MVC	0(2,4),=X'0000'
	B	END
ERR	MVC	0(2,4),=X'0002'
END	MVI	12(13),X'FF'
	LM	14,12,12(13)
	SR	15,15
	BR	14
	DS	0F
PLIST	DC	AL8'TYPE'
	DC	X'81'
	DC	AL3(MSG)
	DC	C'B'
	DC	AL3(2)
MSG	DC	X'7L00'
TAB1	DC	X'718848C9995939B878F9FF030A00FFAF305'
	END	

TABLE V-10

TAEG REPORT NO. 29

LISTING - EXECUTIVE TPF

TPF EXEC

```

&TYPE OFF
-TESTIT &IF &INDEX EQ 0 &GOTO -NONE
&IF &1 EQ QUIT &GOTO -QUIT
&INDEX1 = 1
&IF &1 EQ MASTER &GOTO -GOTIT
&INDEX1 = 2
&IF &1 EQ SCRATCH &GOTO -GOTIT
&INDEX1 = 3
&IF &1 EQ VERIFY &GOTO -GOTIT
&INDEX1 = 4
&IF &1 EQ TEST &GOTO -TEST
&IF &1 EQ QUIT &EXIT
&IF &1 EQ COPY &PRINT TPF MODEL- COPY INVALID- ENTER QUIT TO EXIT
&IF &1 EQ MOD &PRINT TPF MODEL- MOD INVALID- ENTER QUIT TO EXIT
-NONE &PRINT REPLY MASTER, SCRATCH, OR TEST (INPUT DATA)
&READ ARGS
&GOTO -TESTIT
-TEST &PRINT COMBINE TEST FILE WITH MASTER OR SCRATCH? (Y OR N)
&INDEX2 = 1
&READ ARGS
&IF &1 NE Y &GOTO -GOTIT
&INDEX2 = 10
&PRINT REPLY MASTER OR SCRATCH
&READ ARGS
&GOTO -TESTIT
-GOTIT &PRINT
&PRINT INPUT THIS RUN:
&IF &INDEX1 EQ 1 &PRINT MASTER
&IF &INDEX1 EQ 2 &PRINT SCRATCH
&IF &INDEX1 EQ 3 &PRINT VERIFY
&IF &INDEX1 EQ 4 &PRINT TEST
&IF &INDEX2 EQ 10 &PRINT COMBINED WITH TEST
&IF &INDEX LT 2 &GOTO -NOSAVE
&IF &2 NE SAVE &GOTO -NOSAVE
&INDEX3 = 10
&PRINT SAVE OPTION IN EFFECT THIS RUN
-NOSAVE &PRINT ENTER CARRIAGE RETURN TO CONTINUE
&READ ARGS
&IF &INDEX EQ 0 &GOTO -PARAM
&IF &1 EQ QUIT &GOTO -QUIT
-PARAM FILEDEF " CLEAR
FILEDEF PARAM DSK TPF PARAM
PARAM
&IF &INDEX GE 2 &GOTO -QUIT
FILEDEF " CLEAR
FILEDEF 3 DSK TPF PARAM
FILEDEF 6 DUM
FILEDEF 8 DUM
&IF &INDEX EQ 1 FILEDEF 10 DSK TPF MASTER
&IF &INDEX EQ 2 FILEDEF 10 DSK TPF SCRATCH
&IF &INDEX EQ 3 FILEDEF 10 DSK TPF VFY
&IF &INDEX EQ 4 FILEDEF 10 DSK TST DATA
&IF &INDEX2 EQ 10 FILEDEF 10 DSK TST DATA CONCAT
&IF &INDEX3 EQ 10 &GOTO -SAVEOUT
FILEDEF 9 DSK OUT4 FILE LR 81
FILEDEF 11 DSK OUT3 FILE LR 81
&GOTO -MODEL
-SAVEOUT FILEDEF 9 DSK OUT2 FILE LR 81
FILEDEF 11 DSK OUT1 FILE LR 81
-MODEL RUN KEND (BRIEF)
FILEDEF " CLEAR
SET SPIE ON
&PRINT END TPF EXECUTION
&PRINT ENTER: CTRRUN FOR CENTER SUMMARY; CRSRUN FOR COURSE OUTPUTS
&EXIT
-QUIT FILEDEF " CLEAR
SET SPIE ON
&PRINT MODEL NOT RUN AT OPERATOR REQUEST
&EXIT

```

TABLE V-11

TAEK REPORT NO. 29

08/14/75

INPUT LISTEN

AUTOFLOW CHART SET - FINAL

PL/1 -PARAM- FLOWCHARTS

LISTING - PROGRAM PARAM

PL/1 MODULE

ILIST,NAMSQ,SOACSECI

CARD NO	*****	CONTENTS	*****
1	OPTION PACK1,F,COMPRESS		
2	PARAM: PROC OPTIONS (NAME) :		00000100
3	* TPF PARAMETER CARD MOD PROGRAM 13JUN75 *		00000200
4	DCL (PCARD,DATA) CHAR (80), REQ CHAR (10), LINE(8) C	NO VARYING,	00000300
5	FIELDS (24) CHAR (5) INITIAL		00000400
6	IFAIL, 'NDSHO', 'DMD', 'TREND', 'CONV', 'LEN', 'CAP', 'SETB',		00000500
7	'CDP', 'SCH', 'PRINT', 'WKS', 'TRAC', 'PRE', 'RELS', 'END', 'STAT',		00000600
8	'CRS', 'SCHL', 'CTR', 'INPUT', 'FVR', 'LYR', 'AOB',		00000700
9	LEN (10), 'FVR', 'BIN (8,0) INITIAL		00000800
10	((10,4),(10,1) 22,22,22,22,		00000900
11	COL(24) FIXED BIN (8,0) INITIAL (16,21,26,31,36,41,		00001000
12	46,56,61, 66,71,72,73,74,79,76,77,78,79,80,1,3,7,11),		00001100
13	(K,LP) 1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,17,18,19,20,21		00001200
14	DCL COMND EXTERNAL ENTRY:		00001300
15	DCL IMESARC ENTRY (FIXED BIN (13,0)):		00001400
16	DCL (11,JJ) FIXED BIN (15,0):		00001500
17	OPEN FILE (PARAM) RECORD UPDATE :		00001600
18	READ FILE (PARAM) INTO (PCARD) :		00001700
19	II = 61		00001800
20	CALL COMND (11,JJ):		00001900
21	INTRO:		00002000
22	DISPLAY ('TPF MODEL - WANT INSTRUCTIONS (Y OR N)') REPLY (DATA):		00002100
23	IF DATA = 'N' THEN GO TO PRERUN :		00002200
24	HELP: DISPLAY (' '):		00002300
25	DISPLAY ('ENTER: FNAME XXXX (SET FNAME TO VALUE)'):		00002400
26	DISPLAY (' ' FNAME DEACT (DEACT FNAME)'):		00002500
27	DISPLAY (' ' SHOW (SHOW RUN COND)'):		00002600
28	DISPLAY (' ' RUN (RUN MODEL)'):		00002700
29	DISPLAY (' '):		00002800
30	DISPLAY ('FIELDS: FVR (NNNN) LYR (NNNN) AOB (NNNN) CDP (AA00002900		00002900
31	AA) SCH (AAAA)'):		00003000
32	DISPLAY (' ' FAIL (NNNN) NDSHO (NNNN) DMD (NNNN) TREND (NN00003100		00003100
33	NN) CONV (NNNN)'):		00003200
34	DISPLAY (' ' LEN (NNNN) CAP (NNNN) SETB (NNNN)'):		00003300
35	DISPLAY (' '):		00003400
36	DISPLAY ('REPORTS: CRS (N) SCHL (N) CTR (N) PRINT (N)00003500		00003500
37	II:		00003600
38	PRERUN:		00003700
39	FLAG = 2:		00003800
40	GO TO TUBE_IT:		00003900
41	COME_BACK: FLAG = 0:		00004000
42	DISPLAY (' '):		00004100
43	DISPLAY ('ENTER RUN, QUIT, OR FIELD TO BE CHANGED'):		00004200
44	PARMS: DISPLAY (' '):		00004300
45	DISPLAY ('ENTER REQUEST:') REPLY (DATA) :		00004400
46	IF DATA = 'RUN' THEN GO TO FILE_IT :		00004500
47	IF DATA = 'FLAG' THEN GO TO FLG:		00004600
48	IF DATA = 'HELP' THEN GO TO HELP:		00004700
49	IF DATA = 'SHOW' THEN GO TO TUBE_IT :		00004800
50	IF DATA = 'QUIT' THEN GO TO QUIT:		00004900
51	P1 = INDEX (DATA, ' '):		00005000
52	P2 = INDEX (SUBSTR (DATA,P1+1), ' '):		00005100
53	REQ = SUBSTR (DATA,1,P1-1) :		00005200
54	DO I = 1 TO 24 :		00005300
55	IF REQ = FIELDS (I) THEN GO TO GOT_IT :		00005400
56	END:		00005500
57	DISPLAY ('FIELDNAME NOT RECOGNIZED') :		00005600
58	GO TO PARMS :		00005700
59	GOT_IT:		00005800
60	IF SUBSTR (DATA,P1+1,6) = 'DEACT' THEN GO TO DEAC :		00005900
61	IF SUBSTR (DATA,1,P1-1) = 'SCH' THEN		00006000
62	IF P2 < 5 THEN P2 = 5:		00006100
63	IF P2-1 < LEN(I) THEN GO TO ENR2 :		00006200
64	IF I < 10 THEN GO TO FLAG_AND_VALU :		00006300
65	SUBSTR (PCARD,COL(I),LEN(I)) = SUBSTR (DATA,P1+1,LEN(I)) :		00006400
66	GO TO PARMS :		00006500
67	TUBE_IT:		00006600
68	DISPLAY (' '):		00006700
69	DISPLAY ('PRESENT RUN CONDITIONS'):		00006800
70	DO K = 1 TO 8 :		00006900
71	LINE(K) = ' ':		00007000
72	END:		00007100
73	LP = 0 :		00007200
74	DO K = 1 TO 7 :		00007300
75	IF SUBSTR (PCARD,11+5*K,1) = '0' THEN DO :		00007400
76	LINE (LP/3 + 1) = LINE (LP/3 + 1) FIELDS(K)		00007500
77	' ' SUBSTR (PCARD,12+5*K,4) ' ' :		00007600
78	LP = LP + 1 :		00007700
79	END :		00007800
80	END :		00007900
81	DO K = 8 TO 10 :		00008000
82	IF SUBSTR (PCARD,16+5*K,1) = '0' THEN DO :		00008100
83	LINE (LP/3 + 1) = LINE (LP/3 + 1) FIELDS(K)		00008200
84	' ' SUBSTR (PCARD,17+5*K,4) ' ' :		00008300
85	LP = LP + 1 :		00008400
86	END :		00008500
87	END :		00008600
88	LP = (LP+3)/3 + 3:		00008700
89	LINE (LP / 3 + 1) = 'REPORTS: ':		00008800
90	FLAG1 = 0:		00008900
91	DO K = 11,18,19,20:		00009000
92	IF SUBSTR (PCARD,COL (K),1) = '0' THEN DO:		00009100
93	FLAG1 = 10:		00009200
94	LINE (LP/3 + 1) = LINE (LP/3 + 1) ' ' FIELDS (K):		00009300
95	END:		00009400
96	END:		00009500
97	IF FLAG1 = 10 THEN		00009600
98	LINE (LP/3 + 1) = LINE (LP/3 + 1) 'NO NONE ':		00009700
99	LP = LP + 3:		00009800
100	LINE (LP/3 + 1) = 'INPUT = ' SUBSTR (PCARD,1,2) ' FVR =		00009900
101	SUBSTR (PCARD,3,4) ' LYR = ' SUBSTR (PCARD,7,4)		00010000
102	' AOB = ' SUBSTR (PCARD,11,4) :		00010100
103	K = (LP/3) + 1:		00010200
104	DO I = 1 TO K :		00010300
105	DISPLAY (LINE(I)) :		00010400
106	END :		00010500
107	IF FLAG = 2 THEN GO TO COME_BACK:		00010600
108	GO TO PARMS :		00010700
109	FLAG_AND_VALU:		00010800

TABLE V-12

V-69 515

TAEG REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

PL/1 -PARAM- FLOWCHARTS

CARD NO

CONTENTS

110	SUBSTR (PCARD,COL(1),LEN(1)+1) =	00010900
111	*1* SUBSTR (DATA,PI+1,LEN(1)) :	00011000
112	GO TO PARMS :	00011100
113	DEAC :	00011200
114	IF I > 20 THEN GO TO ERR1 :	00011300
115	SUBSTR (PCARD,COL(1),1) = '0' :	00011400
116	GO TO PARMS :	00011500
117	ERR1 :	00011600
118	DISPLAY ('INVALID REQUEST') :	00011700
119	GO TO PARMS :	00011800
120	ERR2 :	00011900
121	DISPLAY ('INVALID DATA FORMAT') :	00012000
122	GO TO PARMS :	00012100
123	FLG: DISPLAY ('FLAGS - WKS TRAC PRE RELS END STAT YEAR PRINT INIT') :	00012200
124	GO TO PARMS :	00012300
125	QUIT: II = 8 :	00012400
126	CALL INESARC (III) :	00012500
127	FILE_IT :	00012600
128	REWRITE FILE (PARM) FROM (PCARD) :	00012700
129	CLOSE FILE (PARM) :	00012800
130	END PARAM :	00012900

TABLE V-12 (CONTINUED)

DISPLAY SUPPORT PROGRAM

The objective of the display support program is to allow the user to effectively interface with the large amounts of data that the TPF model may produce. This support package is general purpose in nature, and is useful for displaying the contents of other data sets as well.

EXECUTIVE DISP. Executive DISP is used to control the execution of program DISPLAY. This short executive accepts a parameter passed from the user or calling executive and uses this parameter to define the data set to be displayed. FORTRAN data set 7 is used as the output data set and is termed CONO by NCSS convention to label it the console or terminal device. This output data set is used rather than the conventional data set 6 so that FORTRAN I/O error messages will not be displayed. SET SPIE ON is specified in this executive as the FORTRAN I/O error checking is disabled by internal subroutines, and this condition must be reset. This executive is usually called by executives CTRRUN, CRSRUN, CENTER, or COURSE. These executives are three-line executives that merely pass the proper file name to the DISP exec. CTRRUN and CRSRUN are used to display center and course data respectively for TPF runs where the SAVE option is not specified, while CENTER and COURSE are used to display those data if SAVE was specified.

PROGRAM DISPLAY. Program DISPLAY is a FORTRAN program used to display the contents of TPF output data sets. The program ascertains the format of the output data, determines page size, and presents these data along with options to the user. A standard TPF output data set is in the form:

<u>CTL</u> <u>CHAR(1)</u>	<u>DATA (79)</u>
1	First line of page
Blank	Data (variable number of lines)
/	Last line of data
Blank	Null line
1	First line of next page

Program DISPLAY first searches the first column of each record for a "/", to determine if a TPF data set is to be displayed, and if so, to ascertain the size of each page. Next the program skips through the file to determine the number of pages in the file. Finally, if the file contains 25 lines per page, it is assumed to be a course file, and the CDP options are enacted. If the file is not a TPF file, the program defaults to 20 lines per page.

The user has the option of specifying the page number to be displayed, or entering a carriage return to display the next (or first) page. The user may also enter LOOK, followed by a blank and a page number to display only the first line of a page. Finally, if the file is a course file, the user may specify the CDP number of the course to be displayed.

Direct access I/O is used by this program in locating and displaying data so as to allow the user to browse back and forth through the data. All terminal responses are read in the "A" format as in program TPFMOD1 to allow the user to intermix alpha and numeric data and to avoid left or right justification. Subroutine CONVRT, detailed in the section describing TPFMOD1 is used to convert these input data to a machine processable form. Subroutine COMND, also described in that section is used to clear the display screen prior to a page

display. In-line subroutine RANGE is used to intercept FORTRAN errors should the user specify a page outside the boundaries of the input data set, while in-line subroutine ALPHA intercepts any I/O conversion errors in order to provide smooth operation to the user.

LISTING - DISPLAY EXECUTIVES

COURSE EXEC

&TYPE OFF
EXEC DISP OUT2
&EXIT

CENTER EXEC

&TYPE OFF
EXEC DISP OUT1
&LXIT

CRSRUN EXEC

&TYPE OFF
EXEC DISP OUT4
&EXIT

CTRRUN EXEC

&TYPE OFF
EXEC DISP OUT3
&EXIT

DISP EXEC

&TYPE OFF
FILEDEF * CLEAR
FILEDEF 3 DSK &1 FILE
FILEDEF 7 CONO
DISPLAY
SET SPIE ON
FILEDEF * CLEAR
&EXIT

TABLE V-13

TAEG REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

LISTING - PROGRAM DISPLAY

FORTRAN MODULE

(LIST, HANSQ, SOURCE)

CARD NO

CONTENTS

```

1 C TPF SUPPORT - UPDATE 22MAY75 00000100
2 C DISPLAY - DISPLAYS OUTPUT FILE FOR 3 MODES (AUTO SELECT OF STD/NON-STD) 00000200
3 C STANDARD FILE CONTAINS 1 IN COL 1 AT START OF PAGE, / AFTER LAST LINE 00000300
4 C 1. COURSE FILE (25 LINES/PAGE) SELECT BY PAGE OR CDP. 00000400
5 C 2. SCHOOL/CENTER FILE - SELECT BY PAGE NO. 00000500
6 C 3. NON STANDARD FILE - SELECT BY PAGE NO; DEFAULT TO 20 LINES/PAGE 00000600
7 INTEGER*2 IN(5), IN(15), CODE, TEST(4,5), SIZE, NSTART, NNN, ENDIT 00000700
8 DATA TEST/'Q','U','I','T','D','O','N','E','L','D','O','X', 00000800
9 1 'P','A','G','E','C','O','D','E' / 00000900
10 INTEGER*2 BLANK / 0 00001000
11 REAL*4 CDP, DONE, PAGE, QUIT, SELECT 00001100
12 REAL*8 LINE (10) 00001200
13 INTEGER*4 NUM 00001300
14 COMMON NGA, NGR 00001400
15 EXTERNAL RANGE 00001500
16 EXTERNAL ALPHA 00001600
17 DEFINE FILE 3 (2500, 81, E, J3) 00001700
18 DATA SLASH/'/', CDP/'CDP', /, DONE/'DONE', /, PAGE/'PAGE', /, QUIT/'QUIT' 00001800
19 CALL ERRSET (232, 100, -1, 1, RANGE) 00001900
20 CALL ERRSET (219, 100, -1, 1, ALPHA) 00002000
21 NGA = 0 00002100
22 NGR = 0 00002200
23 NSTART = -1 00002300
24 LOOKPL = 0 00002400
25 NSET = 2 00002500
26 NNN = 6 00002600
27 CALL COMND (NNN, J3) 00002700
28 C LOAD PAGE SIZE TO CALC POSITION 00002800
29 DO 20 I = 1, 26 00002900
30 READ (3, 15, ERR=999) CTLCAR 00003000
31 15 FORMAT (A1, BOX) 00003100
32 IF (CTLCAR .EQ. SLASH) GO TO 30 00003200
33 20 CONTINUE 00003300
34 C HERE IF NO SLASH IN 1 - INVALID FILE 00003400
35 WRITE (7, 25) 00003500
36 25 FORMAT (' NON STANDARD FILE TYPE - DEFAULT 20 LINES PER PAGE') 00003600
37 SIZE = 20 00003700
38 NSET = 0 00003800
39 GO TO 26 00003900
40 C 00004000
41 30 SIZE = 1 + 1 00004100
42 WRITE (7, 35) SIZE 00004200
43 35 FORMAT (' STANDARD FILE - ', 12, ' LINES') 00004300
44 C DETERMINE NUMBER OF PAGES IN FILE 00004400
45 26 DO 10026 I = 1, 100 00004500
46 N = 1 + SIZE + 1 00004600
47 READ (3, 15, ERR=999) CTLCAR 00004700
48 IF (NGR) 10026, 10026, 10027 00004800
49 10026 CONTINUE 00004900
50 10027 NGR = 0 00005000
51 WRITE (7, 10028) I 00005100
52 10028 FORMAT (12, 13, ' PAGES IN FILE') 00005200
53 IF (SIZE .NE. 25) GO TO 27 00005300
54 IF (I .EQ. 1) GO TO 27 00005400
55 WRITE (7, 40) 00005500
56 40 FORMAT (' COURSE FILE - SELECT BY "CDP" OR "PAGE" ') 00005600
57 GO TO 241 00005700
58 27 WRITE (7, 36) 00005800
59 36 FORMAT (' ENTER PAGE NUMBER') 00005900
60 241 READ (5, 51) IN, IN2 00006000
61 51 FORMAT (10A1) 00006100
62 INPLG = 0 00006200
63 C TEST IF IN IS NUMBER OR CODE 00006300
64 242 CALL CONVRT (IN, NUM, CODE, DUM) 00006400
65 IF (CODE .LE. 5) GO TO 666 00006500
66 C HAS ALPHAS- SET IF VALID CODE 00006600
67 IF (INPLG .GT. 0) GO TO 247 00006700
68 INPLG = 10 00006800
69 DO 244 I = 1, 5 00006900
70 DO 243 J = 1, 4 00007000
71 IF (IN (J) .NE. TEST(J, 1)) GO TO 244 00007100
72 243 CONTINUE 00007200
73 C HERE IF RECOGNIZED CODE 00007300
74 GO TO (999, 999, 245, 246, 800), I 00007400
75 GO TO 247 00007500
76 244 CONTINUE 00007600
77 247 WRITE (6, 61) IN 00007700
78 61 FORMAT (1X, 5A1, ' INVALID- RETRY') 00007800
79 GO TO 241 00007900
80 C HERE IF LOOK- NEXT LINE IF PAGE 00008000
81 245 LOOKPL = 10 00008100
82 C NOW TEST IF IN2 IS BLANK OR HAS NUM 00008200
83 246 DO 248 I = 1, 5 00008300
84 IF (IN2 (I) .NE. BLANK) GO TO 249 00008400
85 248 CONTINUE 00008500
86 C HERE IF BLANK- GO GET NUM 00008600
87 GO TO 27 00008700
88 C HAVE SECOND ENTRY- LOAD INTO IN & DECODE 00008800
89 249 DO 290 I = 1, 5 00008900
90 IN (I) = IN2 (I) 00009000
91 INPLG = 10 00009100
92 GO TO 242 00009200
93 666 IF (NUM .NE. 0) GO TO 1006 00009300
94 NSTART = NSTART + SIZE 00009400
95 NUM = NSTART / SIZE + 1 00009500
96 C CALC NSTART POSITION OF PAGE 00009600
97 1006 NSTART = (NUM - 1) * SIZE + 1 00009700
98 987 ENOIT = NSTART + (SIZE - NSET) 00009800
99 IF (LOOKPL .GT. 1) ENOIT = NSTART 00009900
100 C CLEAR PAGE THEN OUTPUT 00010000
101 CALL COMND (NNN, J3) 00010100
102 IF (LOOKPL .EQ. 0) WRITE (7, 103) NUM 00010200
103 103 FORMAT (' PAGE', I4) 00010300
104 LOOKPL = 0 00010400
105 DO 110 I = NSTART, ENOIT 00010500
106 READ (3, 115, ERR=300) CTLCAR, LINE 00010600
107 115 FORMAT (A1, 9A8, A7) 00010700
108 IF (NGR) 120, 120, 300 00010800
109 120 IF (CTLCAR .EQ. SLASH) GO TO 110 00010900

```

TABLE V-14

520

V-74

TAEG REPORT NO. 29

08/14/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

CARD NO	*****	CONTENTS	*****
110		110 WRITE (7,116) LINE	00011000
111		116 FORMAT (1X,9AB,A7)	00011100
112	C		00011200
113		140 WRITE (7,39) NUM	00011300
114		GO TO 241	00011400
115		39 FORMAT (' PAGE', 14, ' *PAUSING- ENTER NEXT PAGE NO.')	00011500
116	C	ALPHA ERROR	00011600
117		200 NGA = 0	00011700
118		WRITE (8,6) IN	00011800
119		GO TO 241	00011900
120	C	RANGE ERROR	00012000
121		300 NGA = 0	00012100
122		WRITE (7,310) NUM	00012200
123		310 FORMAT (1X,14,1X,'OUT OF RANGE - RETRY')	00012300
124		GO TO 241	00012400
125	C		00012500
126	C	CDP SELECT ROUTINE	00012600
127		800 WRITE (7,802)	00012700
128		802 FORMAT (' *ENTER CDP')	00012800
129		803 READ (5,42,ERR=800) SELECT, IN2	00012900
130		42 FORMAT (1A,1X,5A1)	00013000
131		IF (SELECT .EQ. QUIT) GO TO 999	00013100
132		IF (SELECT .EQ. DONE) GO TO 999	00013200
133		IF (SELECT .EQ. PAGE) GO TO 246	00013300
134	C	SEARCH IF CDP IN FILE	00013400
135		DO 816 I = 1, 100	00013500
136		N = ((I - 1) * SIZE) + 1	00013600
137		READ (3,N,806,ERR=850) CDPA	00013700
138		806 FORMAT (1X, A4)	00013800
139		IF (NCR=810, 810, 850	00013900
140		810 IF (CDPA .EQ. SELECT) GO TO 820	00014000
141		816 CONTINUE	00014100
142	C		00014200
143	C	HAVE CDP IN FILE - PRINT PAGE	00014300
144		820 CALL CORNO (NNN,J1)	00014400
145		NUM = 1	00014500
146		ENDIT = N + 25	00014600
147		DO 825 I = N, ENDIT	00014700
148		READ (3,I,115,ERR=850) CTLCAR,LINE	00014800
149		IF (NGR) 822, 822, 850	00014900
150		822 IF (CTLCAR .EQ. SLASH) GO TO 830	00015000
151		825 WRITE (7,116) LINE	00015100
152	C	END OF PAGE	00015200
153		830 WRITE (7,832) NUM	00015300
154		832 FORMAT (' PAGE', 14, ' *PAUSING- ENTER CDP, PAGE, OR QUIT')	00015400
155		GO TO 803	00015500
156	C	HERE IF BAD READ / NO SELECT / OUT OF RANGE	00015600
157		850 NGR = 0	00015700
158		WRITE (7, 852) SELECT	00015800
159		852 FORMAT (1X, A4, ' *NOT IN FILE OR INVALID - RETRY')	00015900
160		GO TO 803	00016000
161	C	WRAPUP (END)	00016100
162		999 WRITE (7,998)	00016200
163		998 FORMAT (' *DISPLAY TPF ENDED')	00016300
164		STOP	00016400
165		END	00016500
166		SUBROUTINE RANGE (KK,LL)	00016600
167		COMMON NGA,NGR	00016700
168		NGR = 10	00016800
169		KK = 0	00016900
170		LL = 232	00017000
171		RETURN	00017100
172		END	00017200
173		SUBROUTINE ALPHA (KK,LL)	00017300
174		COMMON NGA,NGR	00017400
175		NGA = 10	00017500
176		KK = 0	00017600
177		LL = 215	00017700
178		RETURN	00017800
179		END	00017900

TABLE V-14 (CONTINUED)

TAEG REPORT NO. 29

08/14/79


AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

PAGE 02

CHART TITLE - PROCEDURES

AUTOFLOW - PROGRAM DISPLAY



PAGE 03

AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

CHART TITLE - PROCEDURES




FIGURE V-14 (CONTINUED)

523

CHART TITLE - PROCEDURES




FIGURE V-14 (CONTINUED)

08/14/75

-DISPLAY- FLOWCHARTS

PAGE 05

CHART TITLE - PROCEDURES




FIGURE V-14 (CONTINUED)

CHART TITLE - PROCEDURES




FIGURE V-14 (CONTINUED)

526

V-80

08/14/73

AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

PAGE 07

CHART TITLE - PROCEDURES




FIGURE V-14 (CONTINUED)

TAEK REPORT NO. 29

08/14/75

AUTOFLOW CHART SET - FINAL -DISPLAY- FLOWCHARTS

PAGE 08

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

INTEGER*2 IN(5), IN2(5), CODE, TEST(4,5), SIZE, NSTART, MN, ENDIT
DATA TEST/'Q','U','I','T','D','O','N','E','L','O','D','R',
      'P','A','G','E','C','D','P','/'
INTEGER*2 BLANK /' '/
REAL*4 CDP, DONE, PAGE, QUIT, SELECT
REAL*8 LINE (10)
INTEGER*4 NUN
COMMON NGA, NGR
EXTERNAL RANGE
EXTERNAL ALPHA
DEFINE FILE 3 (2500,81,E,J3)
DATA SLASH/'/',CDP/'CDP '//,DONE/'DONE',//,PAGE/'PAGE',//,QUIT/'QUIT'//
15  FORMAT (A1,80X)
25  FORMAT (' NON STANDARD FILE TYPE - DEFAULT 20 LINES PER PAGE')
35  FORMAT (' STANDARD FILE - ',I2,' LINES')
10028  FORMAT (I1, I3, ' PAGES IN FILE')
40  FORMAT (' +COURSE FILE - SELECT BY ''CDP'' OR ''PAGE'' ')
36  FORMAT (' +ENTER PAGE NUMBER')
5  FORMAT (10A1)
6  FORMAT (I1,5A1,' +INVALID- RETRY')
103  FORMAT (' PAGE', I4)
115  FORMAT (A1,9A8,A7)
116  FORMAT (I1,9A8,A7)
39  FORMAT (' PAGE', I4,' +PAUSING- ENTER NEXT PAGE NO.')
310  FORMAT (I1,I4,I1,'OUT OF RANGE - RETRY')
802  FORMAT (' +ENTER CDP')
42  FORMAT (A4,I1,5A1)
806  FORMAT (I1, A4)
832  FORMAT (' PAGE',I4,' +PAUSING- ENTER CDP, PAGE, OR QUIT')
852  FORMAT (I1, A4, ' +NOT IN FILE OR INVALID - RETRY')
998  FORMAT (' +DISPLAY TPF ENDED')

```

FIGURE V-14 (CONTINUED)

TAEG REPORT NO. 29


08/14/75

AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

PAGE 09

CHART TITLE - SUBROUTINE RANGE(KK,LL)



08/14/75

AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

PAGE 10

CHART TITLE - NON-PROCEDURAL STATEMENTS

COMMON NGA,NGR


08/14/75

AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

PAGE 11

CHART TITLE - SUBROUTINE ALPHA(KK,LL)



08/14/75

AUTOFLOW CHART SET - FINAL

-DISPLAY- FLOWCHARTS

PAGE 12

CHART TITLE - NON-PROCEDURAL STATEMENTS

COMMON NGA,NGR

FIGURE V-14 (CONTINUED)

529

V-83

TPF LOGIC DESIGN

The design of the TPF model is such that it might be termed a front-end loaded model. That is, all schedule and demand conditions for a course are loaded at the beginning of the year, and the model then projects the resultant conditions for the remainder of the year. Likewise, the basic model projects, rather than predicts. The model itself is a true simulation, or mathematical representation of the mechanics of the overall scheduling function for the center. All major functions that affect student flow are modeled to a detail similar to the actual operations at the center, which include quota control, BUPERS detailing, scheduling, failures, and setbacks. The model outputs, however, can be predictive if the inputs themselves are predictive. To use the model for decision-making purposes, the user must input his predictions of demands, schedule changes, new courses, etc., and the model then projects the annual throughputs, failures, AOB's, and such, based on these predictions. Likewise, a simulation model is not an optimization model; the large number of variable input parameters precludes this. The user can manipulate the model inputs to achieve optimal results.

PROGRAM LOGIC DESIGN. The TPF model consists of a main control program and seven subroutines, all coded in the FORTRAN language. This structure was chosen for several reasons. All input data enter through the main control program, which edits the input data and builds a matrix for communication between the subroutines. Thus, if input methods should be changed, such as entering backlog as students rather than the present method of entering weeks, only one routine would be required. As another example, the entire scheduling routine is contained in subroutine CRSRLS. This subroutine represents the methods and procedures currently in use at the center. Should it be desirable to represent other centers with different methods and procedures, a new subroutine to represent that center could be written, and the appropriate subroutine could be linked to the model at execute time. In summary, the model has been written in a modular form so as to allow adaptability and ease of modification without extensive rewrite.

Certain programming conventions are followed throughout the design of the TPF model and its subroutines. All input data are read in at the beginning of the operation, with proper editing and error checking provided at that time. Parameter information is read in and various flags are set to control subsequent execution. In both cases, assumptions are made for missing or inaccurate data and processing continues with appropriate error messages. Finally, all communication throughout the model is through COMMON storage, with minimal use made of subroutine parameter passing.

TPF MODEL MAIN. The TPF model is compiled and stored for execution under the name KEND. This is to allow executives to use the name TPF. The basic control routine in this FORTRAN program is called MAIN. This module is the primary interface of the TPF model with the rest of the TPF system. All input data and parameters are entered and edited by this section, and all control of the TPF model execution is set up by MAIN. MAIN also controls all cycling for the various loops necessary for the TPF simulation.

Parameter Options. The first operation in MAIN is to read in the control parameter card. This method of control was chosen to provide for card batch

operation as well as on-line terminal execution. The format of the parameter card is shown in Figure V-3C. Four elements of the parameter card are key to execution; input, first year, last year, and AOB constant, as they set up control for execution. Input specifies whether the data are to be read from cards(05), or from an on-line data set (10), with the default value being 10. First year and last year are used to control the years of the projection (default 1 year, maximum 3 years) and the years entered are printed as titles on output reports. They do not currently control data base access. AOB constant is used to denote the method and value to be used for average-on-board calculations. A value of 300 or greater will cause weekend days to be counted in AOB calculations, while a value of less than 300 will alter the model so that only working days are counted.

The next 8 parameters on the parameter card control across-the-board modification. The first character in each field is a flag (0 for off, 1 for active) and the remaining four characters are a multiplier. If the flag is 1 or greater, the multiplier is passed to other routines for data overrides. The next two fields allow the user to select only a course CDP number or school for execution, without the need to alter the data base.

The last 10 fields on this card contain flags used to control various options of the TPF model. If the INIT flag is set, the model will perform the pre-run initialization described later in this section. If the print flag is 0, only on-line terminal output is provided, a 2 in this field providing only off-line printer output, while a 1 produces both forms of output. The output data provided is controlled by flags COURSE(\$R1), SCHOOL(\$R2), and CENTER(\$R3). A 1 in any of these fields will produce the specified reports, while all zeros in these fields will cause the model to cycle with no output data generated. The rest of the flags control trace routines used for detailed analysis of operation of each of the TPF model subroutines. Use of these trace flags is not recommended for normal operation due to the volume produced. They may be set, however, using program PARAM and their names may be displayed by the program by requesting FLAGS.

Data Entry and Editing. The next major section of program MAIN consists of the logic to read data into storage, provide reasonableness checks, and to perform data overrides. All data are read into main storage to reduce disk I/O operations as the system runs under virtual storage. Each data element is tested for reasonableness and the value is clamped if necessary, allowing the model to execute using a data base with known errors. The various overrides are performed next for those fields where the override flag is set. Logic is included to assure that the overrides produce meaningful results, i.e., course convenings clamped to integer values, rather than allowing a value such as 2.87 convenings. Following these operations, MAIN passes control to the cycling portion of the model.

Model Control and Cycling. Except for one routine, the test of the main program logic is straightforward, using standard FORTRAN coding techniques. Three major cycling paths exist in the model; the year loop, the quarter loop, and the week loop. One of these, the quarterly loop, can undergo alteration to initialize the model. The TPF model does not snapshot existing conditions, but

rather it views conditions over a period of time. It considers the schedule and classes as they are today, and projects for one year. One important factor must be recognized. Today there may be 70 courses in session that were started in a preceding period and which, because of their length, terminate in the period being projected. To represent this, the quarter loop can reconfigure and, for the first quarter loop, the model operates as though it were the quarter prior to model start. No totals are accumulated for the run; the only effect is to release courses so that they may be active at model start. Subroutine PRERUN is used to accomplish this, and this initialization will be discussed in further detail in that segment.

The lowest order cycling loop in the model is the week loop. An understanding of how this loop operates will probably lead to an understanding of the entire model. This loop first scans each course loaded in the model, one at a time, to ascertain if a course should convene that week. It does this by testing the convening frequency of the course against a matrix loaded in core, for convening frequencies of 1 to 50 convenings per year. Before this comparison is made, the matrix is rationalized for offset, change week, and multiple convenings. This routine is described immediately following this segment, but for now, all that is necessary to know is that if this matrix returns a code that the course should start, subroutine PRERUN will be called and the course started. When a course is started, it is placed in an active matrix, which is described in the subroutine PRERUN segment. Upon completion of the test for possible convening of all courses, the MAIN program then tests all active courses to see if any end in that week. As the model cycles on a weekly basis, many courses will begin and end in the same weekly loop. When a course is found to end, subroutine CRSEND is called which closes out the course, allocates the AOB, and calculates attrition. When all of the 300 possible active courses have been tested, the weekly loop recycles to run another week.

Every 13 weeks, the quarter loop cycles, calling subroutine QRTEND, to allocate AOB against quarters and accumulate totals. Finally, after 4 quarters, the year loop cycles, calling subroutine YEARND, which controls printout for the yearly report.

Scheduling Algorithm. Several scheduling algorithms were studied as candidates for this model. As part of the design effort, the actual convening dates for many of the courses were plotted. These plots were then analyzed and an allowance was made for common holidays. The data were then transferred to the matrix shown in Figure V-15. This shows the scheduled convening weeks for courses with a convening frequency of 1 to 50 per year. Many courses convened more frequently than this, and these are handled by breaking them into multiple courses, each with convening frequencies of less than 50, but whose overall convenings are the same as the original. For example, a course with 51 convenings is handled as two courses, one that convenes 25 times annually. Provision exists to break each course into 10 separate courses. The convening matrix itself is stored in core and named ISCHED. The data are loaded in hexadecimal format to accomplish this. FORTRAN allows the loading of hexadecimal data, but does not allow individual bit testing or manipulating. Therefore, a synthetic method of bit testing was developed. This technique involves extracting the proper bit pattern by division by various constants based on week and quarter, which leaves a 1 on the low order bit position if the course is to start, or 0 if it should not. This extracted bit pattern is then tested to determine whether the low order bit is a 0 or 1, which is accomplished by a division by integer 2, and then a multiplication by integer 2. If the result

is the same as the original, the low order bit was 0 and the course is not released. Two rationalizations must be made prior to lookup in this table. First, if a course convenes only once a year, the matrix will start it the first week of the model run. In reality, this course may convene on the 21st week. Offset was introduced as an input to the model to allow fine tuning of the course release date. An offset of 20, for example, will tell the model to enter the schedule matrix as week 1 when the model is in the 21st week, the second term to be rationalized. If the schedule change date has passed, the "B" convening schedule is used, otherwise the "A" convenings are used.

As this technique uses matrix lookup, the table must be protected for invalid entries while preserving flexibility. If the convening frequency is 0, the matrix will be bypassed. If the week is greater than 52, 52 is subtracted from the week until it is less than 52. If offset is positive, such as 21, no courses will be released until the 22nd week, regardless of the convening frequency. A negative offset of 31 would accomplish the same schedule shift, and courses could be released from the start of the model run.

SUBROUTINE CRSRLS. The course release subroutine contains the scheduling logic for the center. This includes keeping backlog counts, scheduling only local seats, and overbooking certain courses with high no-show rates. The logic of this subroutine schedules the BUPERS students based on the annual BUPERS plan, divided by current convening frequency. This is done even if the result exceeds the seats controlled by BUPERS. Next, local quotas are released. This is accomplished by releasing students to a backlog pool based on local demand, divided by current convenings. This pool is released to the course up to the local capacity. No-shows are then calculated using historical no-show percentages. Only local students are used for this calculation as BUPERS students generally are on TAD or PCS orders, and are not identifiable as no-shows. Finally, for courses running near capacity, up to 10 percent of the capacity is released from the backlog pool as substitute quotas. This routine then builds an entry in the course active matrix. Included is utilization, weeks till termination, and a term to allocate AOB between quarters and between classes if a student should be set back. This subroutine closely represents the scheduling methods in use at the center. If other centers, with different algorithms, should be studied, this subroutine would most likely be replaced by one representing the location under study.

SUBROUTINE PRERUN. As mentioned previously, the model can run in an initialization mode for one quarter prior to the actual model run. Subroutine PRERUN is called by CRSRLS any time the model is in the initialization mode. It is required for two functions. First, courses are tested prior to release to ascertain whether they should be running at model start or not at all. Secondly, this subroutine allocates AOB for those courses to assure that AOB applicable to the first quarter is charged to the first quarter.

SUBROUTINE CRSEND. This subroutine is called each time a course is found to end in a particular week. Several functions are performed by this subroutine. The first function consists of disposing of all references to the course in the active matrix. Secondly, failures are calculated, with fractional failures pooled, using the current failure rate. The third function is to calculate non-academic disenrollments, based on historical rates. This subroutine also

calculates setbacks. Setback logic currently allows setbacks for those courses 3 weeks or longer, and where more than 1 convening is in session at a time. This setback rate is currently based on a fixed percentage of failures per class. AOB for setback is allocated between the "entered in" and "finished in" convening. Finally, this subroutine calculates AOB based on the current calculation method in effect.

SUBROUTINE QTREND. This short subroutine is used to accurately allocate AOB between quarters. Only the active courses are tested at the end of a quarter, the accumulated AOB is charged to the current quarter, and the active course AOB is adjusted accordingly.

SUBROUTINE YEARND. The function of subroutine YEARND is to calculate annual totals for all courses, prepare the model for multiple year runs, aggregate school and center total if those reports are keyed, and call appropriate subroutines to provide output reports. This subroutine requires that courses be entered in the data matrix sorted by school code if proper school summary reports be produced.

SUBROUTINE CRTOUT. Subroutine CRTOUT produces course, school, and center reports in a 79 column format. This format is compatible with the Hazeltine 2000 terminal which only has 79 usable columns for formatted data. A sample of the reports produced by subroutine CRTOUT is shown in Figure V-16. The format used for the control character in column 1 was described in this section under display support programs. The same format routines are used for the data portion of the school and center reports, and subroutine YEARND loads center data into the school matrix prior to calling CRTOUT to provide a center report.

SUBROUTINE NPRINT. Subroutine NPRINT produces course, school, and center reports in a 130 column format compatible with line printers or the 2741 terminal. As this routine is designed to interface directly with a line printer, standard carriage control conventions are utilized. Also, three course reports are printed per page, and page numbering is provided. The data presented are identical to those produced by CRTOUT.

COURSE SCHEDULE MATRIX

TPF MODEL COURSE RELEASE SCHEDULE

ANNUAL COURSE	1ST QTR (WKS 1-13)	2ND QTR (WKS 1-13)	3RD QTR (WKS 1-13)	4TH QTR (WKS 1-13)
1	X			
2	X			
3	X			
4	X			
5	X			
6	X			
7	X			
8	X			
9	X			
10	X			
11	X			
12	X			
13	X			
14	X			
15	X			
16	X			
17	X			
18	X			
19	X			
20	X			
21	X			
22	X			
23	X			
24	X			
25	X			
26	X			
27	X			
28	X			
29	X			
30	X			
31	X			
32	X			
33	X			
34	X			
35	X			
36	X			
37	X			
38	X			
39	X			
40	X			
41	X			
42	X			
43	X			
44	X			
45	X			
46	X			
47	X			
48	X			
49	X			
50	X			

FOR EACH WEEK IN THIS SCHEDULE: AN 'X' INDICATES THE COURSE WILL BE RELEASED
 A '-' INDICATES THE COURSE WILL NOT BE RELEASED

NOTE: IF ANNUAL CONVENINGS FOR A COURSE IS GREATER THAN 50, THE COURSE WILL BE TREATED
 AS MULTIPLE COURSES, EACH HAVING 50 OR LESS CONVENINGS PER YEAR.

FIGURE V-15

TAEG REPORT NO. 29

#284	FINANCIAL MGMT				--SCHEDULE DATA--		FY	FY+1	FY+2	CRS BACKLOG
SCHL JNO	CATALOG NO	NEC			ANNUAL CONVENINGS		13	0	0	# STU 32
S/DA 6552 A-551-0056					COURSE LENGTH DYS		5.0	0.0	0.0	# WKS 5
					COURSE CAPACITY		25	0	0	
					BUPERS CAPACITY		0	0	0	FY+1 WK 0
P AOB	PFAIL	TYPE	PRTY		ANNUAL DEMAND		150	180	180	FY+2 WK 0
2.0	7.0%	F1	31		BUPERS DEMAND		0	0	0	OFFSET 0
QUARTERLY PROJECTIONS										
	1 QR FY 75	2 QR FY 75	3 QR FY 75	4 QR FY 75	ANNUAL TOTAL					
# CONVENINGS	4	3	3	3	13					
CRS CAPACITY	100	75	75	75	325					
UTILIZATION	67	67.0%	30	40.0%	29	38.7%	30	40.0%	156	48.0%
NO SHOWS	11	14.1%	5	14.3%	5	14.7%	5	14.3%	26	14.3%
BAKLOG #/WKS	0	0 WKS	0	0 WKS	0	0 WKS	0	0 WKS	0	0 WKS
STU DAYS/AOB	335	3.7	150	1.6	145	1.6	150	1.6	780	2.1
TOTAL PASS	62	92.5%	27	90.0%	25	86.2%	26	86.7%	140	89.7%
TOTAL FAIL	5	7.5%	3	10.0%	3	10.3%	3	10.0%	14	9.0%
SETBACK ACAD	0	0.0%	0	0.0%	0	0.0%	0	0.0%	0	0.0%
DISENROLL NA	0	0.0%	0	0.0%	1	3.4%	1	3.3%	2	1.3%

TPF MODEL -- FISCAL YEAR 1976 SUMMARY										
SCHOOL CODE COMM										
COMM SCHOOL SUMMARY										
	1 QR FY 76	2 QR FY 76	3 QR FY 76	4 QR FY 76	ANNUAL TOTAL					
# CONVENINGS	47	41	44	41	173					
CRS CAPACITY	683	589	645	589	2506					
UTILIZATION	602	88.1%	447	75.9%	441	68.4%	383	65.0%	1873	74.7%
NO SHOWS	77	11.3%	68	13.2%	64	12.7%	58	13.2%	267	12.5%
BAKLOG #/WKS	181	7 WKS	90	6 WKS	46	5 WKS	27	3 WKS	27	3 WKS
STU DAYS/AOB	2810	30.8	2052	22.5	2051	22.5	1661	18.2	8574	23.5
TOTAL PASS	588	97.7%	434	97.1%	430	97.5%	372	97.1%	1824	97.4%
TOTAL FAIL	14	2.3%	13	2.9%	11	2.5%	11	2.9%	49	2.6%
SETBACK ACAD	0	0.0%	0	0.0%	0	0.0%	0	0.0%	0	0.0%
DISENROLL NA	0	0.0%	0	0.0%	0	0.0%	0	0.0%	0	0.0%

TPF MODEL -- FISCAL YEAR 1976 SUMMARY										
TOTALS FOR FLEET TRAINING CENTER										
FTC - NORVA SUMMARY										
	1 QR FY 76	2 QR FY 76	3 QR FY 76	4 QR FY 76	ANNUAL TOTAL					
# CONVENINGS	759	695	678	720	2852					
CRS CAPACITY	23908	22514	21648	24265	92335					
UTILIZATION	16209	67.8%	12559	55.8%	11825	54.4%	12916	53.2%	53511	58.0%
NO SHOWS	2423	13.0%	1974	13.6%	1861	13.0%	2082	13.9%	8340	13.5%
BAKLOG #/WKS	3432	9 WKS	2676	11 WKS	2325	13 WKS	2172	15 WKS	2172	15 WKS
STU DAYS/AOB	92066	1008.9	73855	809.4	71520	787.8	73931	810.2	311372	853.1
TOTAL PASS	115686	96.8%	112069	96.1%	11348	96.0%	12393	95.9%	51496	96.2%
TOTAL FAIL	417	2.6%	375	3.0%	365	3.1%	400	3.1%	1557	2.9%
SETBACK ACAD	36	0.2%	27	0.2%	27	0.2%	30	0.2%	120	0.2%
DISENROLL NA	106	0.7%	115	0.9%	112	0.9%	125	1.0%	458	0.9%

SAMPLE TPF OUTPUTS

FIGURE V-16

530

V-90

TAEG REPORT NO. 29

08/15/75

AUTOPLOM CHART SET - FINAL

-REND- FLOWCHARTS

PAGE 03

CHART TITLE - PROCEDURES




CHART TITLE - PROCEDURES




FIGURE V-17 (CONTINUED)

33

PAGE 09

```
04.19-->
      |
    2 . 01
     .   .
    .   .   .
   .   .   .
  CASES LE. O TRUE
   .   .   .
   .   .   .
   .   .   .
  FALSE 17 . ....
        06 . ...
         | 198
```

STATISTICAL FAILURE
OVERRIDE-IF STAT FLAG
ON READ FILE 8 TO
OBTAIN
NEW FAILURE RATES
CALCULATED BY OFFLINE
PROGRAM FROM STUDENT
CHARACTER-
ISTICS, OVERRIDING
HISTORICAL RATES. J
NO USED AS KEY

```

/00023100/1  NOTE 07
* * * * *
*   LIST = WHERE,   *
*   SELCAS          *
* * * * *

```

```

/00023900/ | 11
-----
| FAIL(1) = SELCRS |
|                  |
| 12 * 12 * 1      |
|-----

```

© 2000 Blackwell Science Ltd *Journal of Internal Medicine* 247: 395–401

V-94

CHART TITLE - PROCEDURES




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29


08/15/75

AUTOFLOW CHART SET - FINAL

-REND- FLOWCHARTS

PAGE 08

CHART TITLE - PROCEDURES



TAEK REPORT NO. 29


08/15/79

AUTOFLOW CHART SET - FINAL

-REND- FLOWCHARTS

PAGE 09

CHART TITLE - PROCEDURES



TAEG REPORT NO. 29


04/15/74

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 10

CHART TITLE - PROCEDURES



545

FIGURE V-17 (CONTINUED)

08/19/79

-KEND- FLOWCHARTS

PAGE 11

CHART TITLE - PROCEDURES




FIGURE V-17 (CONTINUED)

546

V-100

CHART TITLE - PROCEDURES




CHART TITLE - PROCEDURES




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

07/15/75

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

PAGE 14

CHART TITLE - PROCEDURES

SIMULTANEOUS COURSES
SET UP FOR THOSE
COURSES THAT MEET
MORE THAN ONCE
PER WEEK (50 CONV),
OR FOR COURSES WHOSE
LENGTH IS SUCH THAT
NEW
SESSIONS CONVE
BEFORE THE PREVIOUS
SESSION GRADUATES.

SET UP COUNTER
'SIMUL' TO INDICATE
NUMBER OF SESSIONS OF
THE SAME
COURSE CONVENING
SIMULTANEOUSLY DUE TO
CONVENING FREQ GT
THAN 1 / WEEK
MULTIPLE CONVENING
SCHEDULES SET UP AS
NEEDED IN ARRAY C
(1), MAX 10.

```

12.24-->>
  51 | 01
-----
| DIVSR = (18CONV -
| 11/50) * .
|
| QUOT = 8CONV
|
| SIMUL = DIVSR
|-----
  
```

NOW BREAK UP COURSE
INTO SEPARATE
SECTIONS, WITH APPROX
SAME NUMBER
OF INDIVIDUAL
CONVENINGS, AND
EXACTLY SAME NUMBER
TOTAL CONV.

```

/00053400/ NOTE 02
* BEGIN DO LOOP *
* 100 11 = 1, SIMUL *
  
```

```

14.09-->>
  03 |
-----
| DIVSR (-/0)
|
| (-)
|
  
```

```

  99 | 04
-----
| C(11) =
| QUOT/DIVSR
|
| DIVSR = DIVSR - 1
|
| QUOT = QUOT -
| C(11)
|-----
  
```

CALC OFFSET - OFFSET
AVAILABLE AS A MODEL
INPUT TO DELAY OR
ADVANCE
A COURSE CONVENING
SCHEDULES

TEST FOR OFFSET

```

/00054600/ 06
  06 |
-----
| WROFF (-/0)
|
| (0)
|
  
```

```

  10 |
-----
| (0)
|
  
```

```

  11 |
-----
| (0)
|
  
```

```

  12 |
-----
| (0)
|
  
```

```

  13 |
-----
| (0)
|
  
```

```

  14 |
-----
| (0)
|
  
```

HAVE OFFSET,
STRAIGHTEN OUT IF
NEGATIVE (PRESTART)

```

  152 | 07
-----
| ITEM = WROFF
|-----
  
```

MODIFY QUARTERS &
WEEKS TO WEEK

```

/00055900/ 08
  08 |
-----
| ITEM1 = (1Q -
| 11) * W
|-----
  
```

SUBTRACT OFFSET

```

/00056200/ 09
  09 |
-----
| ITEM1 = ITEM1 -
| ITEM
|-----
  
```

SKIP CASALS IF 0 OR
NEG

```

/00056500/ 10
  10 |
-----
| ITEM1 (-/0)
|
| (0)
|
  
```

```

  11 |
-----
| (0)
|
  
```

```

  12 |
-----
| (0)
|
  
```

```

  13 |
-----
| (0)
|
  
```

```

  14 |
-----
| (0)
|
  
```

```

  15 |
-----
| (0)
|
  
```

NO OFFSET, SET WEEKS
& QUARTERS TO ACTUAL

```

14.08-->>
  151 | 11
-----
| Q1 = Q
|
| W1 = W
|-----
  
```

```

  152 |
-----
|
|
  
```

```

  153 |
-----
|
|
  
```

```

  154 |
-----
|
|
  
```

```

  155 |
-----
|
|
  
```

```

  156 |
-----
|
|
  
```

```

  157 |
-----
|
|
  
```

```

  158 |
-----
|
|
  
```

```

  159 |
-----
|
|
  
```

```

  160 |
-----
|
|
  
```

```

  161 |
-----
|
|
  
```

```

  162 |
-----
|
|
  
```

```

  163 |
-----
|
|
  
```

```

  164 |
-----
|
|
  
```

```

  165 |
-----
|
|
  
```

```

  166 |
-----
|
|
  
```

```

  167 |
-----
|
|
  
```

```

  168 |
-----
|
|
  
```

```

  169 |
-----
|
|
  
```

```

  170 |
-----
|
|
  
```

```

  171 |
-----
|
|
  
```

```

  172 |
-----
|
|
  
```

```

  173 |
-----
|
|
  
```

```

  174 |
-----
|
|
  
```

```

  175 |
-----
|
|
  
```

```

  176 |
-----
|
|
  
```

```

  177 |
-----
|
|
  
```

```

  178 |
-----
|
|
  
```

```

  179 |
-----
|
|
  
```

```

  180 |
-----
|
|
  
```

FIGURE V-17 (CONTINUED)

CHART TITLE - PROCEDURES




FIGURE V-17 (CONTINUED)

550

TAEF REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-KFND- FLOWCHARTS

PAGE 16

CHART TITLE - PROCEDURES

COURSE ENDS THIS WEEK
- CALL COURSE END
SUBROUTINE

```

15.20-->
502 | 01
-----
12 | M
19 | CRSEND M
1. | (1) M
10 | M
11 | M
-----

```

15.18-->

```

600 | 02
-----
END OF DO LOOP?
YES | 15
NO | 18
-----

```

15.14-->

```

601 | NOTE 03
-----
CONTINUE
-----

```

TRACE PRINT ROUTINE -
PRINT ONLY IF PROPER
TRACE FLAG IS SET

/00062700/ 04

```

-----
TRACEF
-----
(1)
-----

```

10602 05

```

WRITE TO DEV
VIA FORMAT
11134
FROM THE LIST
-----

```

```

/00652800/ NOTE 06
-----
YEAR, SUMRUN
-----

```

***** END WEEKLY
COURSE LOOP - END
CLASS START AND
COMPLET *****

NEGFLG ON; CALL
SUBROUTINE PRERUN;
CLEAR FLAG, AND
BRANCH TO BEGINNING
OF QUARTER CYCLING

```

801 | 10
-----
12 | M
11 | PRERUN M
1. | (2) M
10 | M
11 | M
-----

```

```

/00064600/ 11
-----
NEGFLG = 0
-----

```

... 12.12.
... 10800

16.04-->

```

800 | 08
-----
END OF DO LOOP?
YES | 12
NO | 17
-----

```

TEST IF NEGFLG IS ON;
INDICATING THAT
QUARTER RUN PRIOR TO
THE START
OF MODEL FISCAL YEAR
CYCLING.

/00064000/ 09

```

-----
NEGFLG
-----
(1)
-----
17
01
802
-----

```

FIGURE V-17 (CONTINUED)

551

CHART TITLE - PROCEDURES



RETURN TO SYSTEM

FIGURE V-17 (CONTINUED)

V-106 552

PAGE 19

CHART TITLE - NON-PROCEDURAL STATEMENTS

FIGURE V-17 (CONTINUED)

553

V-107

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL -KEND- FLOWCHARTS

PAGE 19

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

ZIPFE,ZPPP,ZIPFF/
DATA DIV/4096,2048,1024,512,256,128,64,32,16,8,4,2,1/
1000 FORMAT(12, 314, 1X, 7 (11, F4.3), 9X, 11, F4.3, 2(11, A4),10(1)
1001 FORMAT ('1BEGIN TRAINING PROCESS FLOW MODEL EXECUTION - CHARACTERI
STICS FOR THIS RUN ARE:')
1002 FORMAT (/ ' FIRST FISCAL YEAR OF MODEL RUN', 15, 4X, 'YEARS PROJEC
TED', 13)
1006 FORMAT (/ ' AOB CONSTANT IS', 14, ' WEEKEND DAYS USED IN STUDENT D
AYS AND AOB CALC')
1007 FORMAT (/ ' AOB CONSTANT IS', 14, ' ONLY WORKING DAYS USED IN STUD
ENT DAYS AND AOB CALC')
1008 FORMAT (/ ' COURSE DATA INPUT DEVICE - READER: STATISTICS INPUT
DEVICE - READER')
1009 FORMAT(/ ' ALL INPUTS THIS RUN FROM UNLOADED DATA BASE')
1010 FORMAT(/ ' TRACE FLAGS THIS RUN: PRERUN', 12, ' : CRS REL', 12, ' :
CRS END', 12, ' : YEAR FORMAT', 12 //)
1012 FORMAT ( ' INIT FLAG IS SET - MODEL WILL INIT COURSES IN SESSION A
T 1ST QUARTER START' //)
11013 FORMAT ( ' STAT FLAG IS SET-STATISTICAL FAIL DATA WILL OVERRIDE HI
STORICAL RA,ES' //)
1011 FORMAT ( ' -----
-----')
12014 FORMAT ( ' SELECT OPTION- SELECT KEY IS ', A4, '
10 FORMAT (A4, A8, A2, 2A8, 13, F3.1, 213, 219, 12, 4F4.3, 14, A4,2X,
/4X,
2 (13, F3.1, 213, 219, 13), 2F4.1, 2A2, 2A4)
12002 FORMAT ( ' COURSES ACTIVE THIS RUN', 15)
3002 FORMAT (A4, F4.3)
3006 FORMAT ( ' STATISTICS OVERRIDE-COURSE J NO ', A4, ' NOT IN FILE')
3007 FORMAT ('STATISTICS UPDATE ROUTINE - ', 13, ' COURSES UPDATED')
11011 FORMAT ( ' NEG BACKLOG COURSE ', A4, ' ZEROED THIS RUN')
91003 FORMAT ( ' NEGATIVE OVERRIDE - REQUEST IGNORED. VALUE =', F6.3)
91005 FORMAT ( ' FAIL OVERRIDE- RATES MULT BY', F6.3, ' THIS RUN ONLY')
91015 FORMAT ( ' NO SHOW OVERRIDE - RATES MULT BY',F6.3,' THIS RUN ONLY')
91025 FORMAT ( ' DEMAND OVERRIDE-DEMANDS MULT BY',F6.3,' THIS RUN ONLY')
91035 FORMAT ( ' CONVENINGS OVERRIDE-FREQ MULT BY',F6.3,' THIS RUN ONLY')
91055 FORMAT ( ' CAPACITY OVERRIDE-CAP MULT BY',F6.3,' THIS RUN ONLY')
91058 FORMAT ( ' TREND OPTION- DEMANDS MULT BY', F6.3, ' EACH YEAR')
91045 FORMAT ( ' LENGTH OVERRIDE-LEN MULT BY',F6.3,' THIS RUN ONLY')
10017 FORMAT ( ' OFFSET GT 1 YEAR FOR COURSE ', A4, ' ZEROED THIS RUN')
11035 FORMAT ( ' NEGATIVE CHANGE WEEK COURSE ',A4,' ZEROED THIS RUN')
10012 FORMAT ( ' NEGATIVE CONVENINGS FOR COURSE ', A4,' ZEROED THIS RUN')
33 FORMAT ( ' NEG LENGTH COURSE ', A4, ' ZEROED THIS RUN')
34 FORMAT ( ' NEGATIVE CAPACITY COURSE ', A4, ' ZEROED THIS RUN')
11018 FORMAT ( ' NEGATIVE DEMAND FOR COURSE ', A4, ' ZEROED THIS RUN')
11020 FORMAT ( ' WARNING-BUPERS DEMAND WITH NO BUPERS SEATS COURSE ', A4)
1013 FORMAT(/ ' PRERUN FLAG SET- 4TH QTR WILL BE RUN TO INIT CASES IN S
ESSION AT MODEL START',//)

```

FIGURE V-17 (CONTINUED)

554

V-108

TAEG REPORT NO. 29

08/15/75

AUTOPLOW CHART SET - FINAL

-REMO- FLOWCHARTS

PAGE 20

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

11134  FORMAT (' TRACE- END OF WEEK   WEEK =', 13, '1' QUARTER =', 12,
          '1' YEAR =', 15, 9X, 'COURSES ACTIVE THIS WEEK =', 14, //)
3000   FORMAT ('END OF TPE OUTPUT', 14, ' COURSES PROCESSED', / '//'*)
    
```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

PAGE 21

CHART TITLE - SUBROUTINE PRERUN(X)

/ PRERUN /

16.10-->0

COMMON DATA FOR CLASS
DATA MATRIX

COMMON FOR COURSE
ACTIVE MATRIX
ELEMENTS

COMMON FOR
COMMUNICATION BETWEEN
SUBROUTINES

THIS SUBROUTINE
HANDLES THE UNIQUE
SITUATION WHERE A
NEGATIVE OFFSET
HAS BEEN SPECIFIED TO
START A COURSE PRIOR
TO THE START OF A
MODEL RUN
THIS SITUATION EXISTS
FOR COURSES OF
RELATIVELY LONG
DURATION, AND
RELATIVELY PSW
CONVERGENCE. IT IS
USEFUL TO INDICATE
TRUE AND DURING
A QUARTER.

A CODE OF 0 IS IN (X)
IF CALLED BY COURSE
RELEASE, 2 IF CALLED
BY END.

00071300/0 01
X
(-/0)
(+)
...
.21.00
... 1000

CALLED BY RELEASE,
TEST IF COURSE SHOULD
BE RELEASED. CRITERIA
IS THAT
COURSE LENGTH IS SUCH
THAT COURSE WILL
STILL BE RUNNING AT
MODEL START
TEST INIT TO SEE IF
GENERAL PRERUN OR NEG
OFFSET PRERUN

100 02
TER = 14. - W
00072100/0 03
TRUE
SLEN .LE. TER
FALSE .22
.10
1999

COURSE SHOULD BE
RELEASED - SET DUMMY
TO 1 FOR RETURN.
MODIFY LENGTH TO
REFLECT WEEKS
REMAINING IN 1ST
QUARTER OF COURSE.

00072400/ 04
DUMMY = 1
SLEN = SLEN - TER

TRACE PRINT ROUTINE -
PRINT ONLY IF PROPER
TRACE FLAG IS SET

00073100/0 05
PREPLG
(-/0)
(+)
.22
.10
1999

5001 06
WRITES TO DEV
VIA FORMAT
3000
FROM THE LIST

00073200/ 07
NOTE 07
LIST
CDP(COURSE)
COURSE, WROFF,
SLEN

.22.10.
... 1999

HERE IF PRERUN
CLOSEOUT ROUTINE

21.01-->0
1000 1 NOTE 08
0000000000000000
0000000000000000
0000000000000000
0000000000000000
0000000000000000
22.08-->0
09
ACTIVE(J)
(-/0)
(+)
.22
.08
500
... 401

556

FIGURE V-17 (CONTINUED)

V-110

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-XEND- FLOWCHARTS

PAGE 22

CHART TITLE - SUBROUTINE PRERUMIKI




FIGURE V-17 (CONTINUED)

55,

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL -KEND- FLOWCHARTS

PAGE 21

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (A-Z,0)
REAL*4 LEN, NOSHON, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, CDP
REAL*4 TOMAND, SETBAK
COMMON /DATA/ CDP (176), CRSRUN (176), CONV (3,176), LEN (3,176)
COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGK (2,176)
COMMON /DATA/ OFFSET (176), DEMAND (3,176), BORAND (3,176)
COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)
COMMON /DATA/ BKLOG (176), NOSHON (176), BKLGPL (176)
COMMON /DATA/ BKLG (176), TOMAND, SETBAK
REAL*4 ACTCTR
COMMON /RUN/ ACTIVE (250), ACTCTR (25), ACTUTL (250), ACTNEG(250)
INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, IT 14, ITEMS, WHERE
REAL*4 TEN, TEN1, TEN2, TEN3, TEN4, TEN5, ALEN
COMMON DUMRY, BCONV, ALEN, BCAP, BBCAP, LAST, COURSE
COMMON BR1,BR2,BR3,BR4, TEN, TEN1, TEN2, TEN3, TEN4, TEN5
COMMON ITER, ITER1, ITEM2, ITEM3, ITEM4, ITEMS
COMMON YEAR, CRSES, Q, W, WROFF, INIT, WHERE, NEGPLG, ADBCON
COMMON TRACEF, RLSPLG, ENDPLO, PREPLG, YRPLG, YEARUN,PRINTF
3000 FORMAT (1 PRERUN CALLED - CDP = %, A4, 1 POSITION =%, 15,
1 OFFSET =%, 14, 1 LENGTH IN 1ST QTR =%, P4.1)
4356 FORMAT (1 PRESTART CLOSEOUT CDP =%, A4, 32, 1ACTCTR = %, P5.1,
1 NEGLEN = %, P5.1)

```

FIGURE V-17 (CONTINUED)

5/19

-KEND- FLOWCHARTS

/ CASALS /



.27.15.

129.61

V-113 559

CHART TITLE - SUBROUTINE CRSMLSIX




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

05/19/79

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 20

CHART TITLE - SUBROUTINE CASALSIN)





FIGURE V-17 (CONTINUED)

V-115

561

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 27

CHART TITLE - SUBROUTINE CRSRLS(X)

NO SHOWS GT 1, ADD TO
TOTALS & TAKE FROM
CLASS.
ITEM3 IS STUDENTS
FROM NO SHOW POOL

```

26.13-->
110 1 01
TNOHQ(I,X) =
TNOHQ(I,X) +
ITEM3
ITEM2 = ITEM2 -
ITEM3
NOSHPL(X) =
NOSHPL(X) - ITEM3
    
```

```

26.13-->
111 1 NOTE 02
*****
CONTINUE
*****
    
```

NOW TOTAL STUDENTS &
SEE IF FULL CAPACITY.
ITEM IS SUPERS
STUDENTS, ITEM2 IS
LOCAL STUDENTS AFTER
NO SHOW

```

/00099400/ 03
ACTUTL(Y) =
ITEM + ITEM2
    
```

```

/00099600/ 04
ITEM4 = 0
    
```

```

/00099700/ 05
    
```

```

ACTUTL(Y)
GE. SCAP
TRUE
FALSE
27
12
114
    
```

```

/00099800/ 06
ITEM4 =
(198CAP) + 3
    
```

CAPACITY NOT FULL -
CHECK IF CAN RELEASE
THESE FROM BACKLOG
POOL

```

/00100200/ 07
ITEM5 = BKLGPL(X)
    
```

```

/00100300/ 08
ITEM5
(-/0)
(+1)
    
```

BACKLOG POOL GT 1;
RELEASE SUBSTITUTE
QUOTAS
CLAMP STUDENTS TO MAX
IN POOL.

```

113 09
ITEM5 .LT.
ITEM4
FALSE
TRUE
    
```

```

/00100800/ 10
ITEM4 = ITEM5
    
```

```

BKLGPL(X) =
BKLGPL(X) - ITEM4
ACTUTL(Y) =
ACTUTL(Y) + ITEM4
    
```

```

27.05-->
114 12
TUTL(I,X) =
TUTL(I,X) +
ACTUTL(Y)
    
```

```

24.07-->
999 13
*****
CONTINUE
*****
    
```

TRACE PRINT ROUTINE -
PRINT ONLY IF PROPER
TRACE FLAG IS SET

```

/00101800/ 14
RLSFLG
(-/0)
(+1)
    
```

```

1001 15
WRITE TC DEV
VIA FORMAT
1002
FROM THE LIST
    
```

```

/00101900/ NOTE 16
*****
LIST = COPY(X),
ACTUTL(Y), BKLG,
X, LAST, ITEM,
ITEM2, ITEM4,
ITEM3
*****
    
```

```

/00102500/ 17
NEGFLG .GT. 0
FALSE
TRUE
    
```

```

/00102500/ 18
WRITE TO DEV
VIA FORMAT
1003
FROM THE LIST
    
```

```

/00102500/ NOTE 19
*****
LIST = DUMMY
*****
    
```

```

1010 NOTE 20
*****
CONTINUE
*****
    
```

```

/00103000/ 21
EXIT
    
```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/79

AUTOFLOW CHART SET - FINAL -KEND- FLOWCHARTS

PAGE 28

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (A-Z,B)
REAL*4 BDMAND, BDMAND
REAL*4 LEN, NOSHOM, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, CDP
REAL*4 TDHAND, SETBAK
COMMON /DATA/ CDP (176), CRSRUN (176), CONV (2,176), LEN (3,176)
COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWR (2,176)
COMMON /DATA/ OFFSET (176), DEMAND (3,176), BDMAND (3,176)
COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)
COMMON /DATA/ BAKLOG (176), NOSHOM (176), BKLGPL (176)
COMMON /DATA/ BKLG (176), TDHAND, SETBAK
REAL*4 TFAIL, TNADIS
INTEGER*4 TSDAYS, TCAP, TUTIL
COMMON /TOTALS/ TCAP (5,176), TUTIL (5,176), TSETBK (5,176)
COMMON /TOTALS/ TSDAYS (5,176), TFAIL (5,176), TNOSHOM (5,176)
COMMON /TOTALS/ TNADIS (5,176), TBKLOG (5,176), TCONV (5,176)
REAL*4 ACTCTR
COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG (250)
INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE
REAL*4 TEN, TEN1, TEN2, TEN3, TEN4, TEN5, BLEN
COMMON DUMMY, BCONV, BLEN, BCAP, BDCAP, LAST, COURSE
COMMON SR1,SR2,SR3,SR4, TEN, TEN1, TEN2, TEN3, TEN4, TEN5
COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5
COMMON YEAR, CRSES, O, W, WKOFF, INIT, WHERE, NEGFLG, AOBCON
COMMON TRACEF, RLFLG, ENDPLG, PREPLG, YRFLG, YEARUM,PRINTF
1000 FORMAT (1H0, 'COURSE ACTIVE TABLE PULL - COURSE NOT RELEASED',
      ' COURSE NUMBER (5, A6)
1002 FORMAT (1' RELEASE- CDP= ', A4, ' STUDENTS= ', I3, ' LENGTH= ',
      'P5.1, ' CRS SEQ= ', I4, ' RUN POSITN= ', I4, ' BUPRS= ', I3, '
      LOCAL= ', I3, ' SUBQTA= ', I2, ' NOSHOM= ', I3)
1003 FORMAT ('+', T132, 'P', I1)

```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-REND- FLOWCHARTS

PAGE 29

CHART TITLE - SUBROUTINE CRSEND(X)

/ CRSEND /

16.01--->

SUBROUTINE CRSEND
CALCULATES
PASS/FAIL/SETBACK,
NACDISENROLLMENT,
AND CALCULATES
UTILIZATION, TOTALS
FOR QUARTERLY REPORT

COMMON DATA FOR CLASS
DATA MATRIX

QUARTERLY AND ANNUAL
COURSE TOTALS
ACCUMULATION

COMMON FOR COURSE
ACTIVE MATRIX
ELEMENTS

COMMON FOR
COMMUNICATION BETWEEN
SUBROUTINES

/00107900/ 01
12 = 0
ITEM2 = 0
J = ACTIVE(X)

CALLING PARAMETER 'X'
IS SUBSCRIPT OF
COURSE IN ACTIVE
MATRIX.
ACTIVE (X) CONTAINS
RELATIVE COURSE
NUMBER IN COURSE
MATRIX, HAS '000'
ADDED IF '1' SCHED,
2000 IF '2' SCHED,
3000 IF '3' SCHED

/00108700/ 02
ITEMS = J/1000
J = J -
ITEMS*1000

/00109000/ 03
SLEN =
LEN(ITEMS,J)

CALCULATE FAILURES -
FAILURE RATE FROM
REGRESSION CONSTANTS
NOTE - J POINTS TO
COURSE MATRIX, X
POINTS TO ACTIVE
MATRIX

/00109500/ 04
FER =
FAIL(J)*ACTUTL(X)
TFAIL(Q,J) =
TFAIL(Q,J) + FER

CALCULATE
NON-ACADEMIC
DISENROLLMENT - RATE
FROM DATA BASE

/00110000/ 05
TER1 =
NADIS(J)
*ACTUTL(X)
TNADIS(Q,J) =
TNADIS(Q,J) +
TER1

TEST FOR SETBACK
POSSIBILITY
CRITERIA FOR SETBACK:
COURSE GT 2 WEEKS,
MULTIPLE CONVENINGS,
FAILURE
RATE TO PRODUCE
SETBACKS.

/00110700/ 06
SLEN .LT. 2.0
TRUE
FALSE .29
11
100

/00110800/ 07
CRSRUN(J)
LT. 2
TRUE
FALSE

/00110900/ 08
FER2 =
TER*SETBAR + .5

/00111000/ 09
FER2 .LT. 1
TRUE
FALSE

HERE IF SETBACKS MAY
OCCUR

10
30.01
200

TOTAL COURSE AND
CLOSEOUT ACTIVE
MATRIX FOR COURSE

29.06
100 11
ACTIVE(X) = 0

CALCULATE TOTAL
STUDENT DAYS FOR AOB
CALCULATION.
ACTNEG CONTAINS DAYS
CHARGED TO OTHER
QUARTER OR OTHER
CONVENINGS.

TEST WHICH METHOD OF
AOB CALCULATION TO BE
USED.

/00112400/ 12
ADBCON .GT.
300
TRUE
FALSE

HERE IF CLASS DAYS
METHOD TO BE USED

/00112700/ 13
TSDAYS(Q,J) =
TSDAYS(Q,J) +
(SLEN*.5*ACTUTL
(X) + .01) -
ACTNEG(X)

HERE IF YEARLY METHOD
TO BE USED.

430 14
ITEM1 = SLEN - 1
TER = (ITEM1*2) +
(SLEN*.5)

/00113500/ 15
TSDAYS(Q,J) =
TSDAYS(Q,J) +
(TER*ACTUTL(X) +
.01) - ACTNEG(X)

470 NOTE 16
CONTINUE

CLOSE OUT COURSE,
RESET ACTIVE & RUN
FLAGS.

/00114100/ 17
ACTIVE(X) = 0
CRSRUN(J) =
CRSRUN(J) - 1

/00114300/ 18
CRSRUN(J)
.LT. 0
FALSE
TRUE

/00114300/ 19
CRSRUN(J) = 0

20
31.08
999

FIGURE V-17 (CONTINUED)

TAEQ REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 30

CHART TITLE - SUBROUTINE CRSEND(X)

 SETBACK
 ROUTINE *****

 HAVE SETBACKS -
 SEARCH OUT PROPER
 CONVENING TO SET BACK
 TO.

INIT TEST VALUES

29.10--> 01
 200 |
 ITEMS = 1
 ITEM = ACTIVE(X)
 TEMS = 999.
 ITEM2 = 0
 ITEM3 = 0

/00115800/ NOTE 02

 BEGIN DO LOOP
 120 12 = 1, 250

 30.13--> 03
 ITEM1 =
 ACTIVE(12)

/00114000/ 04

 ITEM1
 (1) 30
 13
 120

HAVE ACTIVE COURSE -
 TEST IF OURS:
 DUMMY=SCHED,
 ITEM1=CRSHO

101 | 05
 DUMMY =
 ITEM1/1000
 ITEM1 = ITEM1 -
 DUMMY*1000

/00114400/ 06

 ITEM1 .NE. J
 TRUE
 FALSE

HAVE OUR COURSE
 NUMBER-TEST IF ONE WE
 ARE ENDING

/00114600/ 07

 12 .EQ. X
 TRUE
 FALSE

FOUND ONE OF OUR
 COURSES-TEST IF
 EARLIEST CONVENING.

/00114900/ 08

 ACTCTR(12)
 GT. TEMS
 TRUE
 FALSE 30
 11
 118

EARLIEST SO FAR, SAVE
 WEEKS & POSITION

/00117200/ 09
 TEMS = ACTCTR(12)
 ITEM3 = 12

SEE IF WE FOUND ALL
 CONVENINGS, BUMP
 COUNTER & TEST.

/30.11

30.07--> 11
 118 |
 ITEM2 = ITEM2 + 1

/00117800/ 12

 ITEM2 .EQ.
 CRSHO(J)
 TRUE
 FALSE

30.04--> 13
 120 | 13
 END OF DO
 LOOP?
 NO
 YES 30
 03

HERE IF DONE COURSE
 SEARCH OF ACTIVE
 MATRIX. ITEM3 IS 0 IF
 NO HIT.
 STATEMENT 100 IS
 BACKWARD BRANCH TO
 CLOSEOUT ROUTINE

121 | 14

 ITEM3
 (1) 30
 11
 100

31.01
 122

FIGURE V-17 (CONTINUED)

V-119 565

CHART TITLE - SUBROUTINE CRSENDIX1

FIND COURSE AND
MODIFY TABLES TO
REPRESENT SETBACKS

```

30.14--->*
122 1 01
ITEM =
ACTIVE(ITEM3)
DUMMY = ITEM/1000
ITEM = ITEM -
DUMMY*1000
TEMP =
LEN(DUMMY, ITEM)
    
```

```

/00119300/ 02
ITEM2 = ITEM2
ACTUTL(ITEM3) =
ACTUTL(ITEM3) +
ITEM2
TSETBK(Q, ITEM) =
TSETBK(Q, ITEM) +
ITEM2
    
```

NOW CALCULATE
NEGATIVE STUDENT DAYS
- TO COMPENSATE
COURSE STUD LEFT.
ITEM2 IS SETBACKS,
LEN IS FIRST COURSE
LENGTH, TEMP IS SET
BACK TO CAS
LENGTH, TEMP IS WEEKS
LEFT IN SET BACK TO
COURSE.

NOW LET TEMP EQUAL
WEEKS STUDENT HAS
BEEN IN SET BACK TO
COURSE.

```

/00120300/ 03
TEMP = TEMP -
TEMP
    
```

TEST AOB MULT FOR
METHOD OF AOB
CALCULATION.

```

/00120400/ 04
AOBCON .GT. TRUE
330
FALSE
    
```

AOBCON 330, USE
STUDENT DAYS METHOD.

YEARLY AOB METHOD
USED - CONVERT WEEKS
TO INTEGER.
STUDENT BEGINS
SETBACK TO CLASS
MONDAY, WEEKEND
CHARGED TO OLD COURSE
CALC TOTAL STUD DAYS,
INCLUDING WEEKENDS -
DUMMY IS INTEGER.

```

130--->* 06
DUMMY = TEMP
TEMP =
(DUMMY*2) +
(TEMP*5.)
ACTNEG(X) =
ACTNEG(X) +
(TEMP*TEMP2 + .01)
    
```

```

...
.29.11.
... 100
    
```

```

/00120900/ 07
ACTNEG(X) =
ACTNEG(X) +
(TEMP*TEMP2 + .01)
    
```

```

...
.29.11.
... 100
    
```

```

/ 999 /
29.20---> NOTE 08
*****
* CONTINUE *
*****
    
```

```

/00122600/ 09
    
```

```

(-/01)
ENDFLG
(+)
    
```

```

1001 10
WRITE TO DEV
VIA FORMAT
1002
FROM THE LIST
    
```

```

/00122700/ NOTE 11
*****
* LIST = CDP13, *
* ACTUTL(X) = 5LEN, *
* J, X *
*****
    
```

```

/00123100/ 12
    
```

```

FALSE
ITEM2 .GT. 0
TRUE
    
```

```

/00123100/ 13
WRITE TO DEV
VIA FORMAT
1003
FROM THE LIST
    
```

```

/00123100/ NOTE 14
*****
* LIST = ITEM2, *
* ITEM3 *
*****
    
```

```

31.099---> NOTE 15
1010
*****
* CONTINUE *
*****
    
```

```

/00123700/ 16
EXIT
    
```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/79

AUTOFLOW CHART SET - FINAL -REND- FLOWCHARTS

PAGE 32

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (A-Z,0)
REAL*4 LEN, NOSHOW, NOSHPL, BRLGPL, BPOOL, NADIS, FAIL, CDP
REAL*4 TORAND, SETBAK
COMMON /DATA/ CDP (176), CRSRUN (176), CONV (3,176), LEN (3,176)
COMMON /DATA/ CAP (3,176), BCAP (3,176), CMGWK (2,176)
COMMON /DATA/ OFFSEY (176), DERAND (3,176), BDWAND (3,176)
COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)
COMMON /DATA/ BAKLOG (176), NOSHOW (176), BRLGPL (176)
COMMON /DATA/ BRLG (176), TORAND, SETBAK
REAL*4 TFAIL, TNADIS
INTEGER*4 TSDAYS, TCAP, TUTIL
COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176)
COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHO (5, 176)
COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)
REAL*4 ACTCTR
COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG(250)
INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE
REAL*4 TEM, TEM1, TEM2, TEM3, TEM4, TEM5, BLEN
COMMON DUMMY, SCONV, BLEN, SCAP, BBCAP, LAST, COURSE
COMMON BR1, BR2, BR3, BR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5
COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5
COMMON YEAR, CASES, Q, W, WKOFF, INIT, WHERE, NEGFLG, AOSCOM
COMMON TRACEF, RLSFLG, ENDFLG, PREFLG, YRFLG, YEARUN, PRINTF
1002 FORMAT (1' CRS END- CDP= ', A4, '3' STUDENT#= ', I3, '3' LENGTH=
      ,F5.1, '3' CRS SEQ= ', I4, '3' RUN POSITN= ', I4, '3'
1005 FORMAT (1'*, ' T105, I2, ' STONTS SET TO CRS ', I4)

```

FIGURE V-17 (CONTINUED)

TAEQ REPORT NO. 29

08/15/79

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 33

CHART TITLE - SUBROUTINE QRTENDIX

/ QRTEND /

17.02--->

QUARTER END ROUTINE
TOTALS STUDENT DAYS
OF ALL COURSES IN
SESSION.
AND ADDS THEM TO
COURSE TOTALS. THESE
DAYS ARE ALSO ENTERED
AS
"NEGATIVE" DAYS IN
ACTIVE MATRIX TO
PREVENT THEM FROM
BEING COUNTED IN
NEXT QUARTERS TOTALS.
ROUTINE CHECKS AOBCON
FOR WHICH METHOD OF
TALLING AOB IS
USED.

COMMON DATA FOR CLASS
DATA MATRIX

QUARTERLY AND ANNUAL
COURSE TOTALS
ACCUMULATION

COMMON FOR COURSE
ACTIVE MATRIX
ELEMENTS

COMMON FOR
COMMUNICATION BETWEEN
SUBROUTINES

TEST ACTIVE MATRIX
FOR ACTIVE COURSES.

/00129900/ NOTE 01
* * * * *
* BEGIN DO LOOP *
* 500 J = 1, 250 *
* * * * *

33.09--->

02
* * * * *
* ACTIVE(J) *
* * * * *
* (1) *
* 33 *
* 09 *
* 500 *
* * * * *

ACTIVE FILE HAS A
COURSE ACTIVE AT 'J'.
GET POINTER INTO
COURSE MATRIX.

401 03
* * * * *
* ITEM = ACTIVE(J) *
* DUMMY = ITEM/1000 *
* * * * *
* ITEM = ITEM - *
* DUMMY*1000 *
* * * * *
* SLEN = *
* LEN(DUMMY,ITEM) *
* * * * *

TEST WHICH METHOD OF
AOB CALCULATION TO BE
USED.

/00130700/ 04
* * * * *
* AOBCON .GT. *
* 300 *
* * * * *
* TRUE *
* * * * *

FALSE

C HERE IF CLASS DAYS
METHOD TO BE USED.

/00131000/ 05
* * * * *
* TEM = (SLEN - *
* ACTCTR(J)) *
* *ACTUTL(J)*9. *
* * * * *

HERE IF YEARLY AOB
METHOD TO BE USED
CHARGE THIS WEEKEND
TO THE COURSE BEING
CLOSED OUT

430 04
* * * * *
* TEM1 = SLEN - *
* ACTCTR(J) *
* * * * *
* ITEM1 = TEM1 *
* * * * *
* TEM = (ITEM1*2) + *
* (ITEM1*9) *
* * * * *
* TEM = *
* TEM*ACTUTL(J) *
* * * * *

440 NOTE 07
* * * * *
* CONTINUE *
* * * * *

ADD TOTAL STUDENT
DAYS TO COURSE &
ACTIVE MATRICES

/00132400/ 08
* * * * *
* TEM = TEM + .01 *
* * * * *
* ACTNEG(J) = *
* ACTNEG(J) + TEM *
* * * * *
* TSDAYS(Q,ITEM) = *
* TSDAYS(Q,ITEM) + *
* TEM *
* * * * *

33.02--->

500 09
* * * * *
* END OF DO *
* LOOP? *
* * * * *
* YES *
* 33 *
* 02 *
* * * * *

COPY CURRENT BACKLOG
POOL FIGURES INTO
COURSE TOTALS

/00133200/ NOTE 10
* * * * *
* BEGIN DO LOOP *
* 8111 I = 1, CRSES *
* * * * *
* * * * *
* 34.01---> *
* 8111 *
* * * * *
* TSKLOG(Q,I) = *
* BKLGPL(I) *
* * * * *

/34.01

FIGURE V-17 (CONTINUED)

CHART TITLE - SUBROUTINE QRTEND1X1




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/79

AUTOFLOW CHART SET - FINAL -XEND- FLOWCHARTS

PAGE 35

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (A-Z,8)
REAL*4 LEN, NOSHON, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, CDP
REAL*4 TDHAND, SETBAR
COMMON /DATA/ CDP (176), CRSRUM (176), CONV (3,176), LEN (3,176)
COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWR (2,176)
COMMON /DATA/ OFFSET (176), DEMAND (3,176), BDHAND (3,176)
COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)
COMMON /DATA/ BAKLOG (176), NOSHON (176), BKLGPL (176)
COMMON /DATA/ BKLG (176), TDHAND, SETBAR
REAL*4 TFAIL, TNADIS
INTEGER*4 TSDAYS, TCAP, TUTIL
COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBR (5, 176)
COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHO (5, 176)
COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)
REAL*4 ACTCTR
COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG(250)
INTEGER*4 ITEC, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE
REAL*4 TEM, TEM1, TEM2, TEM3, TEM4, TEM5, SLEN
COMMON DUMMY, SCONV, SLEN, SCAP, SBCAP, LAST, COURSE
COMMON BR1, BR2, BR3, BR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5
COMMON ITEM, ITEM1, ITEA2, ITEM3, ITEM4, ITEM5
COMMON YEAR, CRSES, Q, W, WKOFF, INIT, WHERE, NEGFLG, AOBCON
COMMON TRACEF, ALSFLG, ENOFLG, PREFLG, YRFLG, YEARUN, PRINTF
1000 FORMAT (4 QUARTER END ROUTINE FOR QUARTER ', I1)

```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

AUTOPLON CHART SET - FINAL -REND- FLOWCHARTS

PAGE 34

CHART TITLE - SUBROUTINE YEARND(Y)




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/13/75

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

PAGE 37

CHART TITLE - SUBROUTINE YEARNO(2)




FIGURE V-17 (CONTINUED)

V-126 572

TAEG REPORT NO. 29


08/15/75

AUTOFLOW CHART SET - FINAL

-REND- FLOWCHARTS

PAGE 28

CHART TITLE - SUBROUTINE YEARNDIV



TAEG REPORT NO. 29

08/19/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 39

CHART TITLE - SUBROUTINE YEARND(Y)




FIGURE V-17 (CONTINUED)

V-128 574

CHART TITLE - SUBROUTINE YEARND(Y)




FIGURE V-17 (CONTINUED)

575

V-129

TAEG REPORT NO. 29

08/19/79

AUTOFLOW CHART SET - FINAL -END- FLOWCHARTS

PAGE 42

CHART TITLE - SUBROUTINE YEARNO(V)




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 43

CHART TITLE - SUBROUTINE YEARND(Y)




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL -END- FLOWCHARTS

PAGE 44

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (A-Z,0)
REAL*4 LEN, NOSHOW, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, CDP
REAL*4 TDHAND, SETBAK
COMMON /DATA/ CDP (176), CRSRUN (176), COMV (3,176), LEN (3,176)
COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWK (2,176)
COMMON /DATA/ OFFSET (176), DEMAND (3,176), BDHAND (3,176)
COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)
COMMON /DATA/ BKLOG (176), NOSHOW (176), BKLGPL (176)
COMMON /DATA/ BKLG (3,176), TDHAND, SETBAK
INTEGER*4 JNO, PNEC, SCHOOL
REAL*4 PAOB, PFAIL
REAL*8 NAME1, NAME2, CATNO1
COMMON /TEXT/ JNO (176), NAME1 (176), NAME2 (176), CATNO1 (176)
COMMON /TEXT/ CATNO2 (176), PNEC (176), TYPE (176), PAOB (176)
COMMON /TEXT/ PFAIL (176), PRY (176), SCHOOL (176)
REAL*4 TFAIL, TNADIS
INTEGER*4 TSDAYS, TCAP, TUTIL
COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176)
COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHO (5, 176)
COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)
INTEGER*4 SUTIL, CUTIL, SCAP, CCAP, SSDAYS, CSDAYS, IFAIL, INADIS
INTEGER*4 PASS, SBKLOG, CBKLOG, SBKL, CBKL
REAL*4 AOB, PCTUTL, PCTNSH, PCTPAS, PCTPL, PCTSB, PCTNDS, PLEN
COMMON /T/ SUTIL (5), SCAP (5), SSDAYS (5), SSETBK (5), SNOSHO (5)
COMMON /T/ CUTIL (5), CCAP (5), CSDAYS (5), CSETBK (5), CNOSHO (5)
COMMON /T/ SBKL(5), SBKLOG(5), SCONV (5), SFAIL (5), SNADIS (5)
COMMON /T/ CCONV(5), CBKL(5), CBKLOG(5), CFAIL (5), CNADIS (5)
COMMON /T/ PCTUTL (5), PCTNSH (5), PCTNDS (5), INADIS (5)
COMMON /T/ AOB (5), PASS (5), PCTPAS (5), PCTPL (5), PCTSB (5)
COMMON /T/ IFAIL (5), PLEN (5), BKL (5), SPLAT (4), YEAR2D
INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE
REAL*4 TEN, TEM1, TEM2, TEM3, TEM4, TEM5, ALEN
COMMON DUNNY, BCONV, ALEN, BCAP, BSCAP, LAST, COURSE
COMMON BR1, BR2, BR3, BR4, TEN, TEM1, TEM2, TEM3, TEM4, TEM5
COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5
COMMON YEAR, CRSES, Q, W, WKOFF, INIT, WHERE, NEGFLG, AOBCON
COMMON TRACEF, ALSFLG, ENDFLG, PREFLG, YRFLG, YEARUN, PRINTF
    
```

FIGURE V-17 (CONTINUED)

TAEK REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 45

CHART TITLE - SUBROUTINE NPRINT(X)




FIGURE V-17 (CONTINUED)

V-134

580

PAGE 46

V-135 581

TAEG REPORT NO. 29

08/19/79

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 47

CHART TITLE - SUBROUTINE NPRINT1




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL -REND- FLOWCHARTS

PAGE 48

CHART TITLE - NON-PROCEDURAL STATE, TS

```

IMPLICIT INTEGER*2 (A-Z,8)
REAL*4 LEN, NOSHOM, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, CDP
REAL*4 TDHAND, SETBAK
COMMON /DATA/ CDP (176), CDSRUN (176), CONV (3,176), LEN (3,176)
COMMON /DATA/ CAP (3,176), BCAP (3,176), CMGWR (2,176)
COMMON /DATA/ OFFSET (176), DERAND (3,176), BDHAND (3,176)
COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)
COMMON /DATA/ BAKLOG (176), NOSHOM (176), BKLGPL (176)
COMMON /DATA/ BRLG (176), TDHAND, SETBAK
INTEGER*4 JNO, PNEC, SCHOOL
REAL*4 PAOB, PFAIL
REAL*8 NAME1, NAME2, CATNO1
COMMON /TEXT/ JNO (176), NAME1 (176), NAME2 (176), CATNO1 (176)
COMMON /TEXT/ CATNO2 (176), PNEC (176), TYPE (176), PAOB (176)
COMMON /TEXT/ PFAIL (176), PRY (176), SCHOOL (176)
REAL*4 TFAIL, TNADIS
INTEGER*4 TSDAYS, TCAP, TUTIL
COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176)
COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHO (5, 176)
COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)
INTEGER*4 SUTIL, CUTIL, SCAP, CCAP, SSDAYS, CSDAYS, IFAIL, INADIS
INTEGER*4 PASS, SBKLOG, CBKLOG, SBKL,CBKL
REAL*4 AOB, PCTUTL, PCTNSH, PCTPAS, PCTPL, PCTSB, PCTNDS, PLEN
COMMON /T/ SUTIL (5), SCAP (5), SSDAYS (5), SSETBK (5), SMOSHO (5)
COMMON /T/ CUTIL (5), CCAP (5), CSDAYS (5), CSETBK (5), CMOSHO (5)
COMMON /T/SBKL(5),SBKLOG(5),SCONV (5), SFAIL (5), SNADIS (5)
COMMON /T/ CCONV(5),CBKL(5),CBKLOG(5), CFAIL (5), CNADIS (5)
COMMON /T/ PCTUTL (5), PCTNSH (5), PCTNDS (5), INADIS (5)
COMMON /T/ AOB (5), PASS (5), PCTPAS (5), PCTPL (5), PCTSB (5)
COMMON /T/ IFAIL (5), PLEN (3), BKL (5), SPLAT (4), YEAN2D
INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE
REAL*4 TEN, TEN1, TEN2, TEN3, TEN4, TEN5, BLEN
COMMON DUMMY, BCONV, BLEN, BCAP, BBCAP, LAST, COURSE
COMMON BR1,BR2,BR3,BR4, TEN, TEN1, TEN2, TEN3, TEN4, TEN5
COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5
COMMON YEAR, CRSES, Q, W, WKOFF, INIT, WHERE, NEGFLG, AOBCON
COMMON TRACEF, RLSFLG, ENDFLG, PREFLG, YRPLG, YEARUN,PRINTF
DATA PAGE /1/, PAGER /4/
8001 FORMAT (1H0,T42,'***** TOTALS FOR FLEET TRAINING CENTER *****
    ' , //)
1000 FORMAT (1H1,T49,'TPF MODEL -- FISCAL YEAR ',I4,' SUMMARY',T123,
    'PAGE ',I3)
1001 FORMAT (1' ', T58, 'SCHOOL CODE ', A4)
2000 FORMAT (1' ', A4, 5X, Z48)
2001 FORMAT (1' ', T78, 'QUARTERLY PROJECTIONS')
2002 FORMAT (1' JNO CATALOG NO NEC TYPE PRY', T60,' | 1 QTR FY ',
    I2,' | 2 QTR FY ',I2,' | 3 QTR FY ',I2,' | 4 QTR FY ',I2,
    ' | ANNUAL TOTAL |')

```

FIGURE V-17 (CONTINUED)

583

V-137

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 49

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

2003  FORMAT (1X, A4, 2X, A8, A2, 2X, A4, 4X, A2, 4X, A2,
          T42, '-----|-----|-----|')
--|-----|-----|-----|-----|
2004  FORMAT (1X, T42, 'NUMBER CONVENINGS ', 4 (15, ' ', 1X, 6X, ' '),
          16, ' ', 1X, 6X, ' ')
2005  FORMAT (' P AOB PFAIL BACKLOG STU LENGTH',
          T42, 'COURSE CAPACITY ', 4 (15, ' ', 1X, 6X, ' '),
          16, ' ', 1X, 6X, ' ')
2006  FORMAT (1X, F5.1, F6.1, 'E INIT', 2X, 15, 14, ' WKS',
          T42, 'UTILIZATION ', 4 (15, ' ', 1X, F5.1, 'E'),
          16, ' ', 1X, F5.1, 'E')
2007  FORMAT (1X, T19, 3 (4X, A2),
          T42, 'NO SHOWS ', 4 (15, ' ', 1X, F5.1, 'E'),
          16, ' ', 1X, F5.1, 'E')
2008  FORMAT ('--SCHEDULE DATA-- PY PY+1 PY+2',
          T42, 'BKLOG-STUDENTS/WKS', 4 (15, ' ', 1X, 12, ' WKS'),
          16, ' ', 1X, 12, ' WKS')
2009  FORMAT (' ANNUAL CONVENINGS', 316,
          T42, 'STUDENT DAYS / AOB', 4 (15, ' ', 1X, F5.1, ' '),
          16, ' ', 1X, F5.1, ' ')
2010  FORMAT (' COURSE LENGTH DYS', 3P6.1,
          T60, ' ', T67, ' ', T74, ' ', T81, ' ', T88, ' ', T95, ' ', T102, ' ',
          T109, ' ', T116, ' ', T124, ' ', T131, ' ')
2011  FORMAT (' COURSE CAPACITY ', 316,
          T42, 'TOTAL PASS ', 4 (15, ' ', 1X, F5.1, 'E'),
          16, ' ', 1X, F5.1, 'E')
2012  FORMAT (' SUPERS SEATS ', 316,
          T42, 'TOTAL FAIL ', 4 (15, ' ', 1X, F5.1, 'E'),
          16, ' ', 1X, F5.1, 'E')
2013  FORMAT (' ANNUAL DEMAND ', 316,
          T42, 'ACADEMIC SETBACK ', 4 (15, ' ', 1X, F5.1, 'E'),
          16, ' ', 1X, F5.1, 'E')
2014  FORMAT (' SUPERS DEMAND ', 316,
          T42, 'NON-ACAD DISENROLL', 4 (15, ' ', 1X, F5.1, 'E'),
          16, ' ', 1X, F5.1, 'E')
2015  FORMAT (' OFFSET / CHG WEEK', 316,
          T42, '-----|-----|-----|')
--|-----|-----|-----|
2001  FORMAT (/////1X, T17, 'SCHOOL CODE ', A4, ' SUMMARY')
2002  FORMAT (//1X, T59, 'QUARTERLY PROJECTIONS')
2003  FORMAT (1X, T37, ' 1 QTR FY ', 12, ' | 2 QTR FY ', 12, ' | 3 QTR
          FY ', 12, ' | 4 QTR FY ', 12, ' | ANNUAL TOTAL |')
2004  FORMAT (1X, T17, '-----|-----|-----|')
--|-----|-----|-----|
2005  FORMAT (1X, T17, 'NUMBER OF CONVENINGS', 16, ' ', 1X, 7X, ' ', 16, ' ', 1X,
          ' ', 16, ' ', 1X, 7X, ' ', 16, ' ', 1X, 7X, ' ', 17, ' ', 1X, 7X, ' ')
2006  FORMAT (1X, T17, 'COURSE CAPACITY', 9X, ' ', 16, ' ', 1X, 7X, ' ', 16, ' ',
          7X, ' ', 16, ' ', 1X, 7X, ' ', 16, ' ', 1X, 7X, ' ', 17, ' ', 1X, 7X, ' ')

```

FIGURE V-17 (CONTINUED)

584

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL -KEND- FLOWCHARTS

PAGE 50

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

7007  FORMAT (IX,T17,'UTILIZATION',T37,'|',I6,' |',F6.1,'%',I6,' |',
        F6.1,'%',I6,' |',F6.1,'%',I6,' |',F6.1,'%',I7,' |',F6.1,
        '%|')
7008  FORMAT (IX,T17,'NO SHOWS',T37,'|',I6,' |',F5.1,'%',I6,' |',
        F5.1,'%',I6,' |',F5.1,'%',I6,' |',F5.1,'%',I7,' |',F5.1,
        '%|')
7009  FORMAT (IX,T17,'STUDENT DAYS / AOB |',I6,' |',F6.1,' |',I6,' |',
        F6.1,' |',I6,' |',F6.1,' |',I6,' |',I7,' |',
        F6.1,' |')
7010  FORMAT (IX,T37,'|',7X,'|',7X,'|',7X,'|',7X,'|',7X,'|',7X,'|',7X,
        '|',7X,'|',8X,'|',7X,'|')
7011  FORMAT (IX,T17,'TOTAL PASS',T37,'|',I6,' |',F5.1,'%',I6,' |',
        F5.1,'%',I6,' |',F5.1,'%',I6,' |',F5.1,'%',I7,' |',F5.1,
        '%|')
7012  FORMAT (IX,T17,'TOTAL FAIL',T37,'|',I6,' |',F5.1,'%',I6,' |',
        F5.1,'%',I6,' |',F5.1,'%',I6,' |',F5.1,'%',I7,' |',F5.1,
        '%|')
7013  FORMAT(IX,T17,'ACADEMIC SETBACK |',I6,' |',F5.1,'%',I6,
        ' |',F5.1,'%',I6,' |',F5.1,'%',I6,' |',F5.1,'%',I7,' |',
        F5.1,'%|')
7014  FORMAT (IX,T17,'NON-ACADEM DISENROLL|',I6,' |',F5.1,'%',I6,
        ' |',F5.1,'%',I6,' |',F5.1,'%',I6,' |',F5.1,'%',I7,' |',
        F5.1,'%|')
7015  FORMAT (IX,T17,'-----
        -----')

```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 51

CHART TITLE - SUBROUTINE CRTOUT(X)




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

04/15/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 52

CHAR: TITLE - SUBROUTINE CRTOUT(X)




FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29


08/15/75

AUTOFLOW CHART SET - FINAL

-REND- FLOWCHARTS

PAGE 55

CHART TITLE - SUBROUTINE CRTOUT(X)



FORMATS FOR 80 COLUMN
CRT OUTPUT

SCHOOL AND CENTER CRT
FORMATS

/00232500/ 22

* EXIT *

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/19/79

AUTOFLOW CHART SET - FINAL -REND- FLOWCHARTS

PAGE 54

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (A-Z,8)
REAL*4 LEN, NOSHOM, NOSHPL, BKLGPL, BPOOL, MADIS, FAIL, COP
REAL*4 TDMAND, SETBAK
COMMON /DATA/ COP (176), CRSRUN (176), CONV (3,176), LEN (3,176)
COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWK (2,176)
COMMON /DATA/ OFFSET (176), DEMAND (3,176), BDMAND (3,176)
COMMON /DATA/ BPOOL (176), FAIL (176), MADIS (176), NOSHPL (176)
COMMON /DATA/ BAKLOG (176), NOSHOM (176), BKLGPL (176)
COMMON /DATA/ BKLG (176), TDMAND, SETBAK
INTEGER*4 JMO, PNEC, SCHOOL
REAL*4 PAOB, PFAIL
REAL*8 NAME1, NAME2, CATNO1
COMMON /TEXT/ JMO (176), NAME1 (176), NAME2 (176), CATNO1 (176)
COMMON /TEXT/ CATNO2 (176), PNEC (176), TYPE (176), PAOB (176)
COMMON /TEXT/ PFAIL (176), PRY (176), SCHOOL (176)
REAL*4 TFAIL, TNADIS
INTEGER*4 TSDAYS, TCAP, TUTIL
COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176)
COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHOM (5, 176)
COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)
INTEGER*4 SUTIL, CUTIL, SCAP, CCAP, SSDAYS, CSDAYS, TFAIL, INADIS
INTEGER*4 PASS, SBKLOG, CBKLOG, SBKL, CBKL
REAL*4 AOB, PCTUTL, PCTNSH, PCTPAS, PCTFL, PCTSR, PCTNDS, PLEN
COMMON /T/ SUTIL (5), SCAP (5), SSDAYS (5), SSETBK (5), SNOSHOM (5)
COMMON /T/ CUTIL (5), CCAP (5), CSDAYS (5), CSETBK (5), CNOSHOM (5)
COMMON /T/ SBKL (5), SBKLOG (5), SCONV (5), SFAIL (5), SNADIS (5)
COMMON /T/ CCONV (5), CBKL (5), CBKLOG (5), CFAIL (5), CNADIS (5)
COMMON /T/ PCTUTL (5), PCTNSH (5), PCTNDS (5), INADIS (5)
COMMON /T/ AOB (5), PASS (5), PCTAS (5), PCTFL (5), PCTSR (5)
COMMON /T/ IFAIL (5), PLEN (5), BKL (5), SPLAT (4), YEAR2D
INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE
REAL*4 TEN, TEN1, TEN2, TEN3, TEN4, TEN5, BLEN
COMMON DUMMY, BCONV, BLEN, SCAP, SBKAP, LAST, COURSE
COMMON BR1, BR2, BR3, BR4, TEN, TEN1, TEN2, TEN3, TEN4, TEN5
COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5
COMMON YEAR, CRSES, Q, W, WKOFF, INIT, WHERE, NPGFLG, AOBCON
COMMON TRACEF, RLSFLG, ENDFLG, PREFLG, YRFLG, YEARUN, PRINTF
9001 FORMAT ('1', T23, 'TYPE MODEL -- FISCAL YEAR ', I4, ' SUMMARY')
4001 FORMAT ('1', T22, '*** TOTALS FOR FLEET TRAINING CENTER *** /')
4002 FORMAT ('1' FTC - HORVA SUMMARY' /)
9002 FORMAT (1X, T33, 'SCHOOL CODE ', A4 /)
9003 FORMAT ('1', A4, 2X, 'SCHOOL SUMMARY' /)
4001 FORMAT ('1', A4, 5X, 2A8, 4X, '---SCHEDULE DATA--- PY PY+1 PY+
2 CR5 BACKLOG')
4002 FORMAT ('1', T31, 'ANNUAL CONVENINGS', IS, 217, A4, 'S STD', IS)
4003 FORMAT ('1' SCHL JNO CATALOG NO NEC COURSE LENGTH OYS', P5.1,
2P7.1, 4X, 'S WKS', IS)
4004 FORMAT ('1', 2 (A4, 1X), A8, A2, 1X, A4, 4X, 'COURSE CAPACITY',

```

FIGURE V-17 (CONTINUED)

589

V-143

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 55

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

317)
4005 FORMAT (' ', T31, 'BUPERS CAPACITY', 317, 3X, 'PY+1 WK', 14)
4006 FORMAT (' P AOB PAIL TYPE PRTY ANNUAL DEMAND', 2X, 317,
3X, 'PY+2 WK', 14)
4007 FORMAT (' ', P5.1, P6.1, 'E', 3X, 2 (A2, 3X), 'BUPERS DEMAND',
2X, 317, 3X, 'OFFSET', 15)
4008 FORMAT (1X, T46, 3 (5X, A2), / 1X, T33, 'QUARTERLY PROJECTIONS')
4009 FORMAT (' ', 12X, ' | 1 'R PY', 13, ' | 2 QR PY', 13,
' | 3 QR PY', 13, ' | 4 QR PY', 13, ' | ANNUAL TOTAL | ')
4010 FORMAT (' ', '-----|-----|-----|',
'-----|-----|-----|')
4011 FORMAT (' ', 'O CONVENINGS', 14, ' |', 5X, ' ', 14, ' |',
5X, ' ', 14, ' |', 5X, ' ', 14, ' |', 5X, ' ', 14,
14, ' |', 5X, ' ')
4012 FORMAT (' ', 'CAS CAPACITY', 14, ' |', 5X, ' ', 14, ' |',
5X, ' ', 14, ' |', 5X, ' ', 14, ' |', 5X, ' ', 14,
14, ' |', 5X, ' ')
4013 FORMAT (' ', 'UTILIZATION ', 14, ' |', P5.1, 'E', 14, ' |',
P5.1, 'E', 14, ' |', P5.1, 'E', 14, ' |', P5.1, 'E',
14, ' |', P5.1, 'E')
4014 FORMAT (' ', 'NO SHOWS ', 14, ' |', P5.1, 'E', 14, ' |',
P5.1, 'E', 14, ' |', P5.1, 'E', 14, ' |', P5.1, 'E',
14, ' |', P5.1, 'E')
4015 FORMAT (' ', 'BACKLOG S/WKS', 14, ' |', 12, ' WKS', 14, ' |',
12, ' WKS', 14, ' |', 12, ' WKS', 14, ' |', 12, ' WKS',
14, ' |', 12, ' WKS')
4016 FORMAT (' ', 'STU DAYS/AOB', 14, ' |', P5.1, ' ', 14, ' |',
P5.1, ' ', 14, ' |', P5.1, ' ', 14, ' |', P5.1, ' ',
14, ' |', P5.1, ' ')
4017 FORMAT (' ', 12X, ' |', 5X, ' |', 6X, ' |', 5X, ' |', 6X, ' |', 5X,
' |', 6X, ' |', 5X, ' |', 6X, ' |', 7X, ' |', 6X, ' |')
4018 FORMAT (' ', 'TOTAL PASS ', 14, ' |', P5.1, 'E', 14, ' |',
P5.1, 'E', 14, ' |', P5.1, 'E', 14, ' |', P5.1, 'E',
14, ' |', P5.1, 'E')
4019 FORMAT (' ', 'TOTAL FAIL ', 14, ' |', P5.1, 'E', 14, ' |',
P5.1, 'E', 14, ' |', P5.1, 'E', 14, ' |', P5.1, 'E',
14, ' |', P5.1, 'E')
4020 FORMAT (' ', 'SETBACK ACAD', 14, ' |', P5.1, 'E', 14, ' |',
P5.1, 'E', 14, ' |', P5.1, 'E', 14, ' |', P5.1, 'E',
14, ' |', P5.1, 'E')
4021 FORMAT (' ', 'DISMISSED NA', 14, ' |', P5.1, 'E', 14, ' |',
P5.1, 'E', 14, ' |', P5.1, 'E', 14, ' |', P5.1, 'E',
14, ' |', P5.1, 'E')
4022 FORMAT (' ', '-----',
'-----',
'//')
5004 FORMAT (' ', 'O CONVENINGS', 19, ' |', 5X, ' ', 19, ' |',
5X, ' ', 19, ' |', 5X, ' ', 19, ' |', 5X, ' ', 19,

```

FIGURE V-17 (CONTINUED)

590

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL -KEND- FLOWCHARTS

PAGE 56

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

16, ' |', SX, ' |')
5009 FORMAT (' ', 'CRS CAPACITY|', 15, '|', SX, ' |', 15, '|',
SX, ' |', 15, '|', SX, ' |', 15, '|', SX, ' |',
16, ' |', SX, ' |')
5006 FORMAT (' ', 'UTILIZATION |', 15, '|', P5.1, 'E|', 15, '|',
P5.1, 'E|', 15, '|', P5.1, 'E|', 15, '|', P5.1, 'E|',
16, ' |', P5.1, 'E|')
5007 FORMAT (' ', 'NO SHOWS |', 15, '|', P5.1, 'E|', 15, '|',
P5.1, 'E|', 15, '|', P5.1, 'E|', 15, '|', P5.1, 'E|',
16, ' |', P5.1, 'E|')
14015 FORMAT (' ', 'BACKLOG #/WKS|', 15, '|', 12, ' WKS|', 15, '|',
12, ' WKS|', 15, '|', 12, ' WKS|', 15, '|', 12, ' WKS|',
16, ' |', 12, ' WKS|')
5008 FORMAT (' ', 'STU DAYS/ADB|', 15, '|', P6.1, ' |', 15, '|',
P6.1, ' |', 15, '|', P6.1, ' |', 15, '|', P6.1, ' |',
16, ' |', P6.1, ' |')
5009 FORMAT (' ', 'TOTAL PASS |', 15, '|', P5.1, 'E|', 15, '|',
P5.1, 'E|', 15, '|', P5.1, 'E|', 15, '|', P5.1, 'E|',
16, ' |', P5.1, 'E|')
5010 FORMAT (' ', 'TOTAL FAIL |', 15, '|', P5.1, 'E|', 15, '|',
P5.1, 'E|', 15, '|', P5.1, 'E|', 15, '|', P5.1, 'E|',
16, ' |', P5.1, 'E|')
5011 FORMAT (' ', 'SETBACK ACAD|', 15, '|', P5.1, 'E|', 15, '|',
P5.1, 'E|', 15, '|', P5.1, 'E|', 15, '|', P5.1, 'E|',
16, ' |', P5.1, 'E|')
5012 FORMAT (' ', 'DISENROLL NA|', 15, '|', P5.1, 'E|', 15, '|',
P5.1, 'E|', 15, '|', P5.1, 'E|', 15, '|', P5.1, 'E|',
16, ' |', P5.1, 'E|')

```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/19/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 57

CHART TITLE - BLOCK DATA

INITIAL VALUES FOR PARAMETERS IN COMMON STORAGE

QUARTERLY AND ANNUAL COURSE TOTALS ACCUMULATION

COMMON FOR COURSE ACTIVE MATRIX ELEMENTS

COMMON FOR SCHOOL AND CENTER TOTALS

08/19/75

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

PAGE 58

CHART TITLE - PROCEDURES

```
-----  
//00238000//  
-----  
  |  
  | 01  
-----  
• EXIT •  
-----  
  RETURN
```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

AUTOFLOW CHART SET - FINAL -REND- FLOWCHARTS

PAGE 59

CHART TITLE - NON-PROCEDURAL STATEMENTS

```

IMPLICIT INTEGER*2 (A-Z,0)
REAL*4 LEN, NOSHMO, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, COP
REAL*4 TDAND, SETBK
COMMON /DATA/ COP (176), CRSRUN (176), CONV (3,176), LEN (3,176)
COMMON /DATA/ CAP (3,176), BCAP (3,176), CCRWK (2,176)
COMMON /DATA/ OFFSET (176), DEMAND (3,176), BONAND (3,176)
COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)
COMMON /DATA/ BAKLOG (176), NOSHMO (176), BKLGPL (176)
COMMON /DATA/ BKLG (176), TDAND, SETBK
DATA BKLG/176*0/, CRSRUN /176*0/, BKLGPL, NOSHPL, BPOOL /528*0./
REAL*4 TFAIL, TNADIS
INTEGER*4 TSDAYS, TCAP, TUTIL
COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176)
COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHMO (5, 176)
COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)
DATA TCAP /880*0/, TUTIL /880*0/, TSETBK /880*0/
DATA TNADIS /880*0./, TBKLOG /880*0/, TCONV /880*0/
DATA TSDAYS /880*0/, TFAIL /880*0./, TNOSHMO /880*0/
REAL*4 ACTCTR
COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG(250)
DATA ACTIVE /250*0/, ACTCTR /250*0./, ACTUTL, ACTNEG /500*0/
INTEGER*4 SUTIL, CUTIL, SCAP, CCAP, SSDAYS, CSDAYS, IFAIL, INADIS
INTEGER*4 PASS, SBKLOG, CBKLOG, SBKL,CBKL
REAL*4 AOB, PCTUTL, PCTNSH, PCTPAS, PCTPL, PCTSB, PCTNDS, PLEN
COMMON /T/ SUTIL (5), SCAP (5), SSDAYS (5), SSETBK (5), SNOSHMO (5)
COMMON /T/ CUTIL (5), CCAP (5), CSDAYS (5), CSETBK (5), CNOSHMO (5)
COMMON /T/ SBKL(5),SBKLOG(5),SCONV (5), SFAIL (5), SNADIS (5)
COMMON /T/ CCONV(5),CBKL(5),CBKLOG(5), CFAIL (5), CNADIS (5)
COMMON /T/ PCTUTL (5), PCTNSH (5), PCTNDS (5), INADIS (5)
COMMON /T/ AOB (5), PASS (5), PCTPAS (5), PCTPL (5), PCTSB (5)
COMMON /T/ IFAIL (5), PLEN (5), BKLG (5), SPLAT (4), YEAR2D
DATA SPLAT /' 0',30' 0/

```

FIGURE V-17 (CONTINUED)

TAEG REPORT NO. 29

08/19/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

FORTRAN MODULE

(LIST,NAMSQ,SOURCEQ)

LISTING - PROGRAM KEND

CARD NO	****	CONTENTS	****
1	C	***** TPF MODEL - AS OF THURSDAY JUNE 12, 1975 *****	00000100
2	C		00000200
3		IMPLICIT INTEGER*2 (A-Z,*)	00000300
4		REAL*4 SELCRS	00000400
5		INTEGER*4 SELSCH	00000500
6	C	COMMON DATA FOR CLASS DATA MATRIX	00000600
7	C		00000700
8		REAL*4 LEN, NOSHML, NOSHPL, BRGLPL, BPOL, NADIS, FAIL, CDP	00000800
9		REAL*4 TDAND, SETBAK	00000900
10	C		00001000
11		COMMON /DATA/ CDP (176), CSRUN (176), CONV (3,176), LEN (3,176)	00001100
12		COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGW (2,176)	00001200
13		COMMON /DATA/ OFFSET (176), DEMAND (3,176), ROMAND (3,176)	00001300
14		COMMON /DATA/ BPOL (176), FAIL (176), NADIS (176), NOSHPL (176)	00001400
15		COMMON /DATA/ BRLOG (176), NOSHML (176), BRGLPL (176)	00001500
16		COMMON /DATA/ BRGL (176), TDAND, SETBAK	00001600
17	C		00001700
18		INTEGER*4 JNO, PNEC, SCHOOL	00001800
19		REAL*4 PAOB, PFAIL	00001900
20		REAL*8 NAME1, NAME2, CATNO1	00002000
21	C		00002100
22		COMMON /TEXT/ JNO (176), NAME1 (176), NAME2 (176), CATNO1 (176)	00002200
23		COMMON /TEXT/ CATNO2 (176), PNEC (176), TYPE (176), PAOB (176)	00002300
24		COMMON /TEXT/ PFAIL (176), PRTY (176), SCHOOL (176)	00002400
25	C		00002500
26		QUARTERLY AND ANNUAL COURSE TOTALS ACCUMULATION	00002600
27	C		00002700
28		REAL*4 TFAIL, TNADIS	00002800
29		INTEGER*4 TSDAYS, TCAP, TUTIL	00002900
30	C		00003000
31		COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176)	00003100
32		COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHML (5, 176)	00003200
33		COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)	00003300
34	C		00003400
35		COMMON FOR COURSE ACTIVE MATRIX ELEMENTS	00003500
36	C		00003600
37		REAL*4 ACTCTR	00003700
38		COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTTUT (250), ACTNEG (250)	00003800
39	C		00003900
40		COMMON FOR COMMUNICATION BETWEEN SUBROUTINES	00004000
41	C		00004100
42		INTEGER*4 ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE	00004200
43		REAL*4 TEM1, TEM2, TEM3, TEM4, TEM5, SLEN	00004300
44	C		00004400
45		COMMON DUMMY, SCONV, SLEN, SCAP, SSCAP, LAST, COURSE	00004500
46		COMMON BR1, BR2, BR3, BR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5	00004600
47		COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5	00004700
48		COMMON YEAR, CRSES, Q, W, WKOFF, INIT, WHERE, NEFLG, AOBCON	00004800
49		COMMON TRACEF, ALSPLG, ENOPLG, PREPLG, YRPLG, YEARUN, PRINTF	00004900
50	C		00005000
51		DIMENSION AND DATA FOR SPECIAL SCHEDULER ROUTINE	00005100
52	C		00005200
53		DIMENSION C (107), ISCHD (4, 50), DIV (13)	00005300
54	C		00005400
55		DATA ISCHD/1000, 3*20, 1000, 20, 2800, 20, 1000, 1000, 24, 20, 2*1000,	00005500
56		2800, 21000, 21004, 220, 240, 2200, 21008, 2100, 2804, 280, 2810, 2408, 281,	00005600
57		240, 21020, 21040, 2810, 2820, 2841, 2*2104, 2410, 21084, 2420, 2442, 2210,	00005700
58		21084, 2444, 2108, 2*2888, 21110, 2844, 2888, 2889, 2222, 2112, 2444, 21112,	00005800
59		2488, 2489, 2244, 21224, 2248, 21244, 21224, 21248, 2892, 2924, 2925,	00005900
60		2492, 2249, 2492, 21249, 2444, 2492, 2444, 2484, 2452, 2253, 2449, 21294,	00006000
61		21444, 2444, 2452, 2495, 2445, 2495, 2495, 2495, 2495, 2495, 2495, 2495,	00006100
62		21444, 2495, 21554, 21554, 2444, 21555, 2444, 2555, 2444, 21444, 21554, 2444,	00006200
63		21555, 21444, 21554, 2485, 2444, 21554, 2444, 2444, 21554, 21444,	00006300
64		21555, 21444, 21554, 2485, 2444, 21554, 2444, 2444, 21554, 21444,	00006400
65		2854, 21444, 2485, 2485, 2485, 21540, 21540, 21540, 21540, 21540, 21540,	00006500
66		2860, 21540, 21444, 21444, 21444, 21444, 21444, 21444, 21444, 21444, 21444,	00006600
67		2087, 2088, 2088, 21876, 2088, 21876, 21876, 21876, 21876, 21876, 21876,	00006700
68		21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876,	00006800
69		21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876,	00006900
70		21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876,	00007000
71		21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876,	00007100
72		21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876, 21876,	00007200
73	C		00007300
74		DATA DIV/4096, 2048, 1024, 512, 256, 128, 64, 32, 16, 8, 4, 2, 1/	00007400
75	C		00007500
76			00007600
77	C		00007700
78		READ RUN PARAMETERS: 'WHERE' IS INPUT DEVICE: 'PRSTYR' & 'LASTYR' ARE	00007800
79	C		00007900
80		C OVERIDES - ITEM1(FAIL), ITEM2(NOSHML), ITEM3(DEMAND), ITEM4(CONV),	00008000
81		C ITEM5(LEN), ITEM6(CAP), TDAND IS DEMAND TREND OVERRIDE - USED TREND	00008100
82	C		00008200
83		C Q PLG FOR COURSE SEL, W PLG FOR SCHOOL SEL, 12 PLG FOR LENGTH IN WEEKS	00008300
84		READ (5, 1000, END=998) WHERE, PRSTYR, LASTYR, AOBCON,	00008400
85		1 ITEM, TEM, ITEM1, TEM1, ITEM2, TEM2, 1, TDAND, ITEM3, TEM3,	00008500
86		2 ITEM4, TEM4, ITEM5, TEM5, 11, SETBAK, Q, SELCRS, W, SELSCH, YRPLG,	00008600
87		3 WPLG, TRACEF, PREPLG, ALSPLG, ENOPLG, STAT, BR1, BR2, BR3	00008700
88	C		00008800
89		1000 FORMAT(12, 314, 1X, 7 (11, P4.3), 5X, 11, P4.3, 2(11, A4), 1011)	00008900
90	C		00009000
91		C CLAMP SETBACK RATE (AS PCT OF FAILURES), CLAMP AOB CONST IF MISSING	00009100
92		IF (11 .LE. 0) SETBAK = 0.5	00009200
93		IF (AOBCON .LE. 0) AOBCON = 365	00009300
94		IF (11 .LE. 0) TDAND = 0	00009400
95	C		00009500
96		SET INIT FLAG - USED TO KEY MODEL PRERUN	00009600
97	C		00009700
98		CLAMP INIT AS USED TO SET NEGRUN FLAG WHOSE ACTUAL VALUE IS SIGNIFICANT	00009800
99		INIT = 1	00009900
100		PRINTF = 0	00010000
101		NEGRUN = INIT	00010100
102	C		00010200
103		SET TRACE FLAG - USED FOR DETAILED COURSE RUN PRINTOUT	00010300
104		TRACEF = TRACEF + PREPLG + ALSPLG + ENOPLG	00010400
105	C		00010500
106		CLAMP DEVICE TO READER OR DISK FOR DATA INPUT	00010600
107	C		00010700
108		IF (WHERE .NE. 10) WHERE = 5	00010800
109	C		00010900

TAEG REPORT NO. 29

09/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

CARD NO	*****	CONTENTS	*****
110	C	FIND NUMBER OF YEARS FOR MODEL RUN - MAX 3 YEARS, PROTECT FOR NEGATIVE	00011000
111	C	PRSTYR IS FIRST PY OF RUN, LASTYR IS LAST YR, YEAR IS CURRENT YEAR OF	00011100
112	C	RUN, ASSUME 1975 IF MISSING, INVERT IF YRS OUT OF ORDER	00011200
113	C	TEST FOR MISSING DATA	00011300
114	C	YEARUN = 1	00011400
115	C	IF (PRSTYR) 26, 26, 27	00011500
116	C	DATA MISSING-ASSUME 1975 & RUN 1 YEAR	00011600
117	C	26 YEAR = 1975	00011700
118	C	GO TO 32	00011800
119	C	HAVE FIRST YEAR, TEST FOR LAST RUN 1 YEAR IF NONE	00011900
120	C	27 IF (LASTYR) 31, 31, 28	00012000
121	C	HERE IF HAVE 1ST & LAST YR, FIND DELTA FOR YEARS RUN	00012100
122	C	28 YEARUN = LASTYR - PRSTYR	00012200
123	C	IF (YEARUN) 29, 30, 30	00012300
124	C	NEG DELTA, YEARS OUT OF ORDER - STRAIGHTEN OUT	00012400
125	C	29 YEARUN = -YEARUN	00012500
126	C	PRSTYR = LASTYR	00012600
127	C	30 YEARUN = YEARUN + 1	00012700
128	C	31 YEAR = PRSTYR	00012800
129	C	IF (YEARUN .GT. 3) YEARUN = 3	00012900
130	C	32 CONTINUE	00013000
131	C	PRINT CHARACTERISTICS UNIQUE TO THIS MODEL RUN	00013100
132	C	WRITE (6, 1001)	00013200
133	C	1001 FORMAT ('BEGIN TRAINING PROCESS FLOW MODEL EXECUTION - CHARACTERISTICS FOR THIS RUN ARE:')	00013300
134	C	WRITE YEARS OF RUN	00013400
135	C	WRITE (6, 1002) YEAR, YEARUN	00013500
136	C	1002 FORMAT (' FIRST FISCAL YEAR OF MODEL RUN', 15, 4X, ' YEARS PROJECTED', 13)	00013600
137	C	IF (AORCON .GT. 300) WRITE (6, 1004) AORCON	00013700
138	C	1004 FORMAT (' AOR CONSTANT IS', 14, ' WEEKEND DAYS USED IN STUDENT DAYS AND AOR CALC')	00013800
139	C	IF (AORCON .LP. 300) WRITE (6, 1007) AORCON	00013900
140	C	1007 FORMAT (' AOR CONSTANT IS', 14, ' ONLY WORKING DAYS USED IN STUDENT DAYS AND AOR CALC')	00014000
141	C	IF (WHERE .EQ. 5) WRITE (6, 1008)	00014100
142	C	1008 FORMAT (' COURSE DATA INPUT DEVICE - READER: STATISTICS INPUT DEVICE - READER')	00014200
143	C	IF (WHERE .GE. 10) WRITE (6, 1009)	00014300
144	C	1009 FORMAT (' ALL INPUTS THIS RUN FROM UNLOADED DATA BASE')	00014400
145	C	WRITE (6, 1010) PRFLG, ALSFLG, ENDFLG, YRFLG	00014500
146	C	1010 FORMAT (' TRACE FLAGS THIS RUN: PRERUN', 12, ' CRS REL', 12, ' CRS END', 12, ' YEAR FORMAT', 12 /)	00014600
147	C	IF (INIT .GT. 0) WRITE (6, 1012)	00014700
148	C	1012 FORMAT (' INIT FLAG IS SET - MODEL WILL INIT COURSES IN SESSION AT 1ST QUARTER START')	00014800
149	C	IF (STAT .GT. 0) WRITE (6, 11013)	00014900
150	C	11013 FORMAT (' STAT FLAG IS SET-STATISTICAL FAIL DATA WILL OVERRIDE HISTORICAL RATES')	00015000
151	C	END OF MODEL RUN DATA MESSAGES - OUTLINE ERROR MESSAGES	00015100
152	C	WRITE (6, 1011)	00015200
153	C	1011 FORMAT (' -----')	00015300
154	C	IF (Q .GT. 0) WRITE (6, 12014) SELCRS	00015400
155	C	IF (W .GT. 0) WRITE (6, 12014) SELSCH	00015500
156	C	12014 FORMAT (' SELECT OPTION- SELECT KEY IS ', 4)	00015600
157	C	READ COURSE DATA FROM DATA BASE INTERFACE INTO MATRIX	00015700
158	C	COURSE MATRIX SET UP FOR MAXIMUM OF 176 INDIVIDUAL COURSES	00015800
159	C	CASES EQUALS NUMBER OF UNIQUE COURSES FOR THIS RUN	00015900
160	C	CASES = 0	00016000
161	C	1 = CASES + 1	00016100
162	C	READ (WHERE, 10, END=2) COP (1), CATN01 (1), CATN02 (1),	00016200
163	C	1 NAME1 (1), NAME2 (1), CONV (1,1), LEN (1,1), CAP (1,1),	00016300
164	C	2 BCAP (1,1), DEMAND (1,1), BOMAND (1,1), OFFSET (1), FAIL (1),	00016400
165	C	3 NADIS (1), NOSHOW (1), DUNNY (1), BARLOG (1), JND (1),	00016500
166	C	4 CONV (2,1), LEN (2,1), CAP (2,1), BCAP (2,1), DEMAND (2,1),	00016600
167	C	5 BOMAND (2,1), CHGWRK (1,1), CONV (3,1), LEN (3,1), CAP (3,1),	00016700
168	C	6 BCAP (3,1), DEMAND (3,1), BOMAND (3,1), CHGWRK (2,1), PADR (1),	00016800
169	C	7 PPAIL (1), PPTY (1), TYPE (1), PNEC (1), SCHOOL (1)	00016900
170	C	10 FORMAT (A4, A8, A2, 2A8, 13, F3.1, 213, 215, 12, 4F4.3, 14, 4A.2X,	00020000
171	C	1 2 (13, F3.1, 213, 215, 13), 2F4.1, 2A2, 2A4)	00020100
172	C	COURSE / SCHOOL SELECT ROUTINE (Q IS COURSE FLAG, W IS SCHOOL FLAG)	00020200
173	C	IF (Q) 4, 4, 3	00020300
174	C	3 IF (SELCRS .NE. COP (1)) GO TO 1	00020400
175	C	4 IF (W) 6, 6, 5	00020500
176	C	5 IF (SELSCH .NE. SCHOOL (1)) GO TO 1	00020600
177	C	6 CASES = CASES + 1	00020700
178	C	IF (CRSES .LT. 176) GO TO 1	00020800
179	C	EXIT MODEL IF NO ACTIVE COURSES	00020900
180	C	2 IF (CRSES .LE. 0) GO TO 1998	00021000
181	C		00021100

TABLE V-15 (CONTINUED)

V-149 595

TAEQ REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

CARD NO	****	CONTENTS	****
222		WRITE (A, 12002) CRSES	00022200
223		12002 FORMAT (1' COURSES ACTIVE THIS RUN', 151	00022300
224		C	00022400
225		C STATISTICAL FAILURE OVERRIDE-IF STAT FLAG ON READ FILE # TO OBTAIN	00022500
226		C NEW FAILURE RATES CALCULATED BY OFFLINE PROGRAM FROM STUDENT CHARACTE	00022600
227		C RISTICS, OVERRIDING HISTORICAL RATES. J NO USED AS KEY	00022700
228		C	00022800
229		IF (STAT) 3010, 3010, 3000	00022900
230		3000 12 = 0	00023000
231		3001 READ (A, 3002, END = 3005) WHERE, SELCRS	00023100
232		3002 FORMAT (A4, P4.3)	00023200
233		C	00023300
234		C SEE IF COURSE IN OUR FILE	00023400
235		DO 3004 I = 1, CRSES	00023500
236		IF (WHERE .NE. JND (I)) GO TO 3004	00023600
237		C	00023700
238		C FOUND OUR COURSE - WRITE IN NEW FAIL RATE & BUMP COUNTER	00023800
239		FAIL (I) = SELCRS	00023900
240		12 = 12 + 1	00024000
241		GO TO 3001	00024100
242		3004 CONTINUE	00024200
243		C	00024300
244		C HERE IF COURSE NOT IN FILE - PRINT ERROR MESSAGE	00024400
245		WRITE (A, 3006) WHERE	00024500
246		3006 FORMAT (1' STATISTICS OVERRIDE-COURSE J NO ', A4, ' NOT IN FILE')	00024600
247		GO TO 3001	00024700
248		C	00024800
249		C END STATISTICS UPDATE - PRINT TOTAL COURSES FOUND	00024900
250		3005 WRITE (A, 3007) 12	00025000
251		3007 FORMAT (1' STATISTICS UPDATE ROUTINE - ', 13, ' COURSES UPDATED')	00025100
252		3010 CONTINUE	00025200
253		C	00025300
254		C	00025400
255		CC INITIALIZE BACKLOG POOL - BACKLOG IS COURSE BACKLOG IN WEEKS. CONVERT	00025500
256		C TO STUDENT DEMAND & INIT TO BRLGPL, ZERO BACKLOG IF NEGATIVE INPUT ERR	00025600
257		C INIT BACKLOG POOL TO B-CONVENINGS-IF NO 'A' CONVENINGS.	00025700
258		C	00025800
259		DO 720 I = 1, CRSES	00025900
260		IF (BACKLOG (I)) 711, 720, 712	00026000
261		711 BACKLOG (I) = 0	00026100
262		WRITE (A, 11011) CDP (I)	00026200
263		11011 FORMAT (1' NEG BACKLOG COURSE ', A4, ' ZEROED THIS RUN')	00026300
264		GO TO 720	00026400
265		C	00026500
266		712 I = 1	00026600
267		IF (CONV (I), 11) 713, 713, 714	00026700
268		C NO 'A' CONVENINGS, TEST B CONVENINGS	00026800
269		713 I = 2	00026900
270		IF (CONV (I), 11) 720, 720, 714	00027000
271		C HAVE CONVENINGS, 11 POINTS AT WHICH ONE	00027100
272		714 12 = CAP (I, 1) - BCAP (I, 1)	00027200
273		IF (12) 720, 720, 715	00027300
274		715 SELCRS = 50. / CONV (I, 1)	00027400
275		BRLGPL (I) = (BACKLOG (I) / SELCRS) * 12	00027500
276		BRLG (I) = BRLGPL (I)	00027600
277		720 CONTINUE	00027700
278		C	00027800
279		C OVERRIDE ROUTINES - FROM PARAMETER CARD	00027900
280		C	00028000
281		C FAIL OVERRIDE - ITEM IS FLAG, TEM IS MULTIPLIER	00028100
282		C	00028200
283		IF (ITEM) 91007, 91007, 91001	00028300
284		91001 IF (TEM) 91002, 91004, 91004	00028400
285		91002 WRITE (A, 91003) TEM	00028500
286		91003 FORMAT (1' NEGATIVE OVERRIDE - REQUEST IGNORED. VALUE =', P4.3)	00028600
287		GO TO 91007	00028700
288		91004 WRITE (A, 91005) TEM	00028800
289		91005 FORMAT (1' FAIL OVERRIDE- RATES MULT BY', P4.3, ' THIS RUN ONLY')	00028900
290		DO 91006 I = 1, CRSES	00029000
291		91006 FAIL (I) = FAIL (I) * TEM	00029100
292		C	00029200
293		C NO SHOW OVERRIDE - FLAG IS ITEM1, MULT IS TEM1	00029300
294		C	00029400
295		91007 IF (ITEM1) 91017, 91017, 91011	00029500
296		91011 IF (TEM1) 91012, 91014, 91014	00029600
297		91012 WRITE (A, 91003) TEM1	00029700
298		GO TO 91017	00029800
299		91014 WRITE (A, 91019) TEM1	00029900
300		91019 FORMAT (1' NO SHOW OVERRIDE - RATES MULT BY', P4.3, ' THIS RUN ONLY')	00030000
301		DO 91016 I = 1, CRSES	00030100
302		91016 NOSHOW (I) = NOSHOW (I) * TEM1	00030200
303		C	00030300
304		C DEMAND OVERRIDE - FLAG IS ITEM2, MULT IS TEM2	00030400
305		C	00030500
306		91017 IF (ITEM2) 91027, 91027, 91021	00030600
307		91021 IF (TEM2) 91022, 91024, 91024	00030700
308		91022 WRITE (A, 91003) TEM2	00030800
309		GO TO 91027	00030900
310		91024 WRITE (A, 91029) TEM2	00031000
311		91029 FORMAT (1' DEMAND OVERRIDE-DEMANDS MULT BY', P4.3, ' THIS RUN ONLY')	00031100
312		DO 91026 I = 1, CRSES	00031200
313		DO 91026 I = 1, 3	00031300
314		DEMAND (I, 1) = DEMAND (I, 1) * TEM2 + .5	00031400
315		91026 DEMAND (I, 1) = DEMAND (I, 1) * TEM2 + .5	00031500
316		C	00031600
317		C OVERRIDE ANNUAL CONVENINGS - FLAG IS ITEM3, MULT IS TEM3	00031700
318		C	00031800
319		91027 IF (ITEM3) 91037, 91037, 91031	00031900
320		91031 IF (TEM3) 91032, 91032, 91034	00032000
321		91032 WRITE (A, 91003) TEM3	00032100
322		GO TO 91037	00032200
323		91034 WRITE (A, 91035) TEM3	00032300
324		91035 FORMAT (1' CONVENINGS OVERRIDE-FREQ MULT BY', P4.3, ' THIS RUN ONLY')	00032400
325		DO 91036 I = 1, CRSES	00032500
326		DO 91036 I = 1, 3	00032600
327		91036 CONV (I, 1) = CONV (I, 1) * TEM3 + 0.5	00032700
328		C	00032800
329		C CAPACITY OVERRIDE - FLAG IS ITEM5, MULT IS TEM5	00032900
330		C	00033000
331		91037 IF (ITEM5) 91057, 91057, 91051	00033100
332		91051 IF (TEM5) 91052, 91052, 91054	00033200
333		91052 WRITE (A, 91003) TEM5	00033300

TABLE V-15 (CONTINUED)

V-150

596

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

CARD NO	****	CONTENTS	****
334		GO TO 91057	00033400
335		91054 WRITE (6, 91059) TEM5	00033500
336		91055 FORMAT (1) CAPACITY OVERRIDE-CAP MULT BY',P6.3,' THIS RUN ONLY')	00033600
337		DO 91056 I = 1, CRSES	00033700
338		DO 91058 I1 = 1, 3	00033800
339		CAP (I1, I) = CAP (I1, I) + TEM5 + .5	00033900
340		91056 BCAP (I1, I) = BCAP (I1, I) + TEM5 + .5	00034000
341		C	00034100
342		91057 IF (TOWAND .GT. 0.) WRITE (6,91058) TOWAND	00034200
343		91058 FORMAT (1) TREND OPTION- DEMANDS MULT BY', P6.3, ' EACH YEAR')	00034300
344		C	00034400
345		C TEST IF LENGTH INPUT IN DAYS, CONVERT TO WEEKS IF IN DAYS FOR EXECUTE	00034500
346		C	00034600
347		IF (MNF LG) 91061, 91061, 91069	00034700
348		91061 DO 91062 J = 1, 3	00034800
349		DO 91068 I = 1, CRSES	00034900
350		IF (LEN (J,I)) 91068, 91068, 91062	00035000
351		91062 ITEM = LEN (J,I) / 7	00035100
352		TEM = LEN (J,I) - ITEM * 7	00035200
353		IF (ITEM .GT. 5) TEM = 5	00035300
354		LEN (J,I) = ITEM + TEM / 5.	00035400
355		91068 CONTINUE	00035500
356		C	00035600
357		C LENGTH OVERRIDE - MIN CHANGE - HALF DAYS ONLY	00035700
358		C SET TEM TO 1 IF LENGTH INPUT IN DAYS, 10 IF IN WEEKS	00035800
359		C	00035900
360		91069 IF (ITEM4) 91047, 91047, 91041	00036000
361		91041 IF (ITEM4) 91042, 91042, 91044	00036100
362		91042 WRITE (6, 91003) TEM4	00036200
363		GO TO 91047	00036300
364		91044 WRITE (6, 91049) TEM4	00036400
365		91045 FORMAT (1) LENGTH OVERRIDE-LEN MULT BY',P6.3,' THIS RUN ONLY')	00036500
366		DO 91046 I = 1, CRSES	00036600
367		DO 91046 I1 = 1, 3	00036700
368		IF (LEN (I1,I)) .LE. 0) GO TO 91046	00036800
369		ITEM = LEN (I1,I) - TEM4 * 10. + 1	00036900
370		LEN (I1,I) = ITEM / 10.	00037000
371		91046 CONTINUE	00037100
372		C	00037200
373		C TEST COURSE DATA MATRIX FOR INVALID OR NEGATIVE DATA	00037300
374		C	00037400
375		91047 DO 25 I = 1, CRSES	00037500
376		C	00037600
377		PFAIL (I) = FAIL (I) * 100.	00037700
378		C	00037800
379		C CLAMP OFFSET AT 1 YEAR	00037900
380		C	00038000
381		ITEM = OFFSET (I)	00038100
382		IF (IABS (ITEM) .LE. 51) GO TO 12	00038200
383		OFFSET (I) = 0	00038300
384		WRITE (6, 10017) CDP (I)	00038400
385		10017 FORMAT (1) OFFSET GT 1 YEAR FOR COURSE ', A4, ' ZEROED THIS RUN')	00038500
386		12 CONTINUE	00038600
387		C	00038700
388		C TEST MULTI DIMENSIONED DATA, TEST ALL FOR I1 = 1, REST ONLY IF CHG WK	00038800
389		C	00038900
390		DO 25 I1 = 1, 3	00039000
391		I2 = I1 - 1	00039100
392		IF (I2) 19, 19, 13	00039200
393		C	00039300
394		C TEST CHANGE WEEK FOR NEG, SKIP FURTHER TESTS IF NO CHANGE WEEK	00039400
395		13 IF (CHG WK (I2, I)) 14, 25, 15	00039500
396		14 CHG WK (I2, I) = 0	00039600
397		WRITE (6, 11035) CDP (I)	00039700
398		11035 FORMAT (1) NEGATIVE CHANGE WEEK COURSE ', A4, ' ZEROED THIS RUN')	00039800
399		GO TO 25	00039900
400		C	00040000
401		C TEST CONVENINGS - BYPASS FURTHER TESTS IF 0 CONVENINGS	00040100
402		15 IF (CONV (I1, I)) 16, 25, 17	00040200
403		16 CONV (I1, I) = 0	00040300
404		WRITE (6, 10012) CDP	00040400
405		10012 FORMAT (1) NEGATIVE CONVENINGS FOR COURSE ', A4, ' ZEROED THIS RUN')	00040500
406		GO TO 25	00040600
407		C	00040700
408		17 IF (LEN (I1, I)) 18, 19, 19	00040800
409		18 LEN (I1, I) = 0	00040900
410		WRITE (6, 33) CDP	00041000
411		33 FORMAT (1) NEG LENGTH COURSE ', A4, ' ZEROED THIS RUN')	00041100
412		C	00041200
413		19 IF (CAP (I1, I)) 20, 21, 21	00041300
414		20 CAP (I1, I) = 0	00041400
415		WRITE (6, 34) CDP (I)	00041500
416		34 FORMAT (1) NEGATIVE CAPACITY COURSE ', A4, ' ZEROED THIS RUN')	00041600
417		C	00041700
418		21 IF (BCAP (I1, I)) 22, 23, 23	00041800
419		22 BCAP (I1, I) = 0	00041900
420		WRITE (6, 34) CDP (I)	00042000
421		C	00042100
422		23 IF (DEMAND (I1, I)) 24, 701, 701	00042200
423		24 DEMAND (I1, I) = 0	00042300
424		WRITE (6, 11018) CDP (I)	00042400
425		11018 FORMAT (1) NEGATIVE DEMAND FOR COURSE ', A4, ' ZEROED THIS RUN')	00042500
426		C	00042600
427		701 IF (DEMAND (I1, I)) 702, 25, 703	00042700
428		702 DEMAND (I1, I) = 0	00042800
429		WRITE (6, 11018) CDP (I)	00042900
430		GO TO 25	00043000
431		C	00043100
432		703 IF (BCAP (I1, I) 11019, 11019, 25	00043200
433		11019 WRITE (6, 11020) CDP (I)	00043300
434		11020 FORMAT (1) WARNING-BUPERS DEMAND WITH NO BUPERS SEATS COURSE ', A4)	00043400
435		C	00043500
436		25 CONTINUE	00043600
437		C	00043700
438		C OUTLINE ERROR MESSAGES	00043800
439		WRITE (6, 1011)	00043900
440		C	00044000
441		IF (NEG PLG .GT. 0) WRITE (6, 1013)	00044100
442		1013 FORMAT (1) 'PRELIM PLG SET- 4TH QTR WILL BE RUN TO INIT CRSES IN 50004300	00044200
443		'SESSION AT MODEL START',//)	00044300
444		C	00044400
445			00044500

TABLE V-15 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

END- FLOWCHARTS

CARD NO

CONTENTS

```

446 C ***** END MODEL INITIALIZATION - BEGIN ACTIVE MODEL LOOP ***** 00044600
447 C 00044700
448 C ----- 00044800
449 C YEAR LOOP - ALLOWS MODEL TO RUN MULTIPLE YEARS, YEAR INPUT ON PARM C0000044900
450 C YEARUN HANDLED OFF TO OTHER SUBROUTINES TO TEST CHANGE DATE 00045000
451 C ----- 00045100
452 C 00045200
453 Y = YEARUN 00045300
454 DO 999 YEARUN = 1, Y 00045400
455 C 00045500
456 C 00045600
457 C QUARTER LOOP - MODEL RUNS ON 4 QUARTERS OF 13 WEEKS 00045700
458 C 00045800
459 C 00045900
460 DO 900 TEMQ = 1, 4 00046000
461 C 00046100
462 C 10800 IS ENTRY FOR PRERUN END 00046200
463 10800 CONTINUE 00046300
464 Q = TEMQ 00046400
465 C 00046500
466 C TEST FOR NEGFLAG, OVERRIDE Q IF PRERUN 00046600
467 IF (NEGFLG .GT. Q) Q = 4 00046700
468 C 00046800
469 C ***** BEGIN LOWEST ORDER (WEEKLY) CYCLING FOR TPF MODEL ***** 00046900
470 C LOOP THROUGH ENTIRE COURSE MATRIX ON A WEEKLY BASIS 00047000
471 C 00047100
472 DO 800 W = 1, 13 00047200
473 C 00047300
474 C 00047400
475 C INITIALIZE 'LAST' TO 1, USED TO FIND LAST USED POSITION IN CRS ACTIVE 00047500
476 C MATRIX BY CRSLS SUBROUTINE 00047600
477 C 00047700
478 LAST = 1 00047800
479 NOW = (1Q - 1) * 13 + W + 192 * (YEARUN - 1) 00047900
480 C 00048000
481 C LOOP THROUGH COURSE MATRIX 00048100
482 C 00048200
483 DO 500 I = 1, CRSES 00048300
484 C 00048400
485 C SET UP PROPER COURSE CONVENING, LENGTH, & CAPACITY DATA, DEPENDING ON 00048500
486 C WHETHER OR NOT A COURSE CHANGE DATE HAS PASSED 00048600
487 C USE A CONVENING IF NEGFLG (PRERUN) FLAG IS ON 00048700
488 C 00048800
489 ITEM = 1 00048900
490 IF (NEGFLG) 11034, 11034, 37 00049000
491 11034 IF (CHGWR (1, 1)) 37, 37, 35 00049100
492 C 00049200
493 C HAVE A CHANGE WEEK - CHECK IF EITHER HAS PASSED (1 DOMINANT) 00049300
494 35 IF INOW .LT. CHGWR (1, 1) GO TO 37 00049400
495 ITEM = 2 00049500
496 IF (CHGWR (2, 1)) 36, 36, 39 00049600
497 39 IF INOW .LT. CHGWR (2, 1) GO TO 36 00049700
498 C 00049800
499 C CHANGE WEEK 2 HAS PASSED - USE '1' DATA 00049900
500 ITEM = 1 00050000
501 C IF CONV FREQ LT 8 SET OFFSET TO CHANGE WEEK (TO ASSURE CRS START) 00050100
502 36 WKOFF = 0 00050200
503 IF (CONV (ITEM, 1) .LT. 8) WKOFF = CHGWR (ITEM-1, 1) - 1 00050300
504 GO TO 38 00050400
505 C 00050500
506 37 WKOFF = OFFSET (1) 00050600
507 38 CONVP = CONV (ITEM, 1) 00050700
508 BLEN = LEN (ITEM, 1) 00050800
509 SCAP = CAP (ITEM, 1) 00050900
510 BOCAP = BCAP (ITEM, 1) 00051000
511 COURSE = 1 + (ITEM * 1000) 00051100
512 C 00051200
513 C TEST FOR CONVENINGS, SKIP IF CONVENINGS LE 0 00051300
514 C 00051400
515 IF (BCONVP) 500, 500, 51 00051500
516 C 00051600
517 C 00051700
518 C SIMULTANEOUS COURSES SET UP FOR THOSE COURSES THAT MEET MORE THAN ONCE 00051800
519 C PER WEEK (SO CONV), OR FOR COURSES WHOSE LENGTH IS SUCH THAT NEW 00051900
520 C SESSIONS CONVEINE BEFORE THE PREVIOUS SESSION GRADUATES. 00052000
521 C 00052100
522 C 00052200
523 C SET UP COUNTER 'SIMUL' TO INDICATE NUMBER OF SESSIONS OF THE SAME 00052300
524 C COURSE CONVENING SIMULTANEOUSLY DUE TO CONVENING FREQ GT THAN 1 / WEEK 00052400
525 C MULTIPLE CONVENING SCHEDULES SET UP AS NEEDED IN ARRAY C (1), MAX 10. 00052500
526 C 00052600
527 51 DIVSR = (1BCONVP - 1) / 50 + 1 00052700
528 QUOT = BCONVP 00052800
529 SIMUL = DIVSR 00052900
530 C 00053000
531 C NOW BREAK UP COURSE INTO SEPARATE SECTIONS, WITH APPROX SAME NUMBER 00053100
532 C OF INDIVIDUAL CONVENINGS, AND EXACTLY SAME NUMBER TOTAL CONV. 00053200
533 C 00053300
534 DO 100 II = 1, SIMUL 00053400
535 IF (DIVSR) 100, 100, 99 00053500
536 99 C (II) = QUOT / DIVSR 00053600
537 DIVSR = DIVSR - 1 00053700
538 QUOT = QUOT - C (II) 00053800
539 100 CONTINUE 00053900
540 C 00054000
541 C 00054100
542 C CALC OFFSET - OFFSET AVAILABLE AS A MODEL INPUT TO DELAY OR ADVANCE 00054200
543 C A COURSE CONVENING SCHEDULE 00054300
544 C 00054400
545 C TEST FOR OFFSET 00054500
546 IF (WKOFF) 192, 191, 192 00054600
547 C 00054700
548 C NO OFFSET, SET WEEKS & QUARTERS TO ACTUAL 00054800
549 C 00054900
550 191 Q1 = Q 00055000
551 W1 = W 00055100
552 GO TO 160 00055200
553 C 00055300
554 C HAVE OFFSET, STRAIGHTEN OUT IF NEGATIVE (PRESTART) 00055400
555 C 00055500
556 192 ITEM = WKOFF 00055600
557 C 00055700

```

TABLE V-15 (CONTINUED)

TAEG REPORT NO. 29

08/19/79

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

CARD NO

CONTENT

558	C MODIFY QUARTERS & WEEKS TO WEEKS	00055800
559	ITEM1 = (IQ - 1) * 13) * W	00055900
560	C	00056000
561	C SUBTRACT OFFSET	00056100
562	ITEM1 = ITEM1 - ITEM	00056200
563	C	00056300
564	C SKIP CRSRLS IF 0 OR NEG	00056400
565	IF (ITEM1) 500, 500, 153	00056500
566	C	00056600
567	C WEEKS POSITIVE, CLAMP TO 52	00056700
568	153 IF (ITEM1 .GT. 52) ITEM1 = ITEM1 - 52	00056800
569	C	00056900
570	C CONVERT BACK INTO WORKING WEEK FOR SCHEDULE MATRIX	00057000
571	C	00057100
572	Q1 = (ITEM1 / 13) * 1	00057200
573	W1 = ITEM1 - (Q1 * 13)	00057300
574	C	00057400
575	180 DO 200 12 = 1, SIMUL	00057500
576	ITEM = C (12)	00057600
577	IF (ITEM) 200, 200, 199	00057700
578	199 ITEM1 = 1 + DO (Q1, ITEM) / DIV (W1)	00057800
579	C	00057900
580	IF ((ITEM1 / 2) * 2) .EQ. ITEM1 GO TO 200	00058000
581	C	00058100
582	C COURSE SECTION CONVENES THIS WEEK, CALL COURSE RELEASE -TO ACTIVE MTRX	00058200
583	C	00058300
584	CALL CRSRLS (1)	00058400
585	C	00058500
586	200 CONTINUE	00058600
587	500 CONTINUE	00058700
588	C	00058800
589	C SAVE NUMBER OF COURSES RELEASED (OR ACTIVE) THIS WEEK	00058900
590	MUMRUN = LAST	00059000
591	C	00059100
592	C	00059200
593	C	00059300
594	C **** END COURSE RELEASE - NOW CHECK ACTIVE MATRIX FOR COMPLETIONS ****	00059400
595	C	00059500
596	C	00059600
597	C SEARCH COURSE ACTIVE MATRIX FOR COURSES THAT END THIS WEEK	00059700
598	C ACTIVE (1) CONTAINS RELATIVE COURSE NUMBER, CRS ACTIVE IF GT ZERO	00059800
599	C	00059900
600	C DON'T TERMINATE OR COUNT DOWN COURSES DURING CHRISTMAS RECESS.	00060000
601	C	00060100
602	IF (Q .EQ. 2 .AND. W .EQ. 13) GO TO 601	00060200
603	IF (Q .EQ. 3 .AND. W .EQ. 1) GO TO 601	00060300
604	C	00060400
605	C SKIP COURSE END IF NEGFLAG (PRESTART) IS ON	00060500
606	IF (NEGFLAG .GT. 0) GO TO 601	00060600
607	C	00060700
608	DO 600 1 = 1, 250	00060800
609	IF (ACTIVE (1)) 600, 600, 501	00060900
610	C	00061000
611	C COURSE ACTIVE - SUBTRACT 1 FROM WEEKS TO END & TEST IF COMPLETE	00061100
612	C ACTIVE (1) CONTAINS WEEKS TILL CRS END, COURSE ENDS IF 0 OR NEGATIVE	00061200
613	C	00061300
614	501 MUMRUN = 1	00061400
615	ACTCTR (1) = ACTCTR (1) - 1.	00061500
616	IF (ACTCTR (1)) 502, 502, 600	00061600
617	C	00061700
618	C COURSE ENDS THIS WEEK - CALL COURSE END SUBROUTINE	00061800
619	C	00061900
620	502 CALL CRSEND (1)	00062000
621	C	00062100
622	600 CONTINUE	00062200
623	601 CONTINUE	00062300
624	C	00062400
625	C	00062500
626	C TRACE PRINT ROUTINE - PRINT ONLY IF PROPER TRACE FLAG IS SET	00062600
627	IF (TRACEP) 800, 800, 10602	00062700
628	10602 WRITE (6, 11134) W, Q, YEAR, MUMRUN	00062800
629	11134 FORMAT (' TRACE- END OF WEEK WEEK =', 13, ' QUARTER =', 12,	00062900
630	' YEAR =', 15, 54, 'COURSES ACTIVE THIS WEEK =', 14, /)	00063000
631	C	00063100
632	C	00063200
633	C ***** END WEEKLY COURSE LOOP - END COURSE START AND COMPLETE *****	00063300
634	C	00063400
635	800 CONTINUE	00063500
636	C	00063600
637	C TEST IF NEGFLAG IS ON, INDICATING THAT QUARTER RUN PRIOR TO THE START	00063700
638	C OF MODEL FISCAL YEAR CYCLING.	00063800
639	C	00063900
640	IF (NEGFLAG) 802, 802, 801	00064000
641	C	00064100
642	C NEGFLAG ON, CALL SUBROUTINE PRERUN, CLEAR FLAG, AND BRANCH TO BEGINNING	00064200
643	C OF QUARTER CYCLING	00064300
644	C	00064400
645	801 CALL PRERUN (2)	00064500
646	NEGFLAG = 0	00064600
647	GO TO 10800	00064700
648	C	00064800
649	802 CONTINUE	00064900
650	C	00065000
651	C END QUARTER LOOP - CALL QRTEND SUBROUTINE TO COLLECT QUARTERLY DATA.	00065100
652	C	00065200
653	CALL QRTEND (Q)	00065300
654	C	00065400
655	900 CONTINUE	00065500
656	C	00065600
657	C	00065700
658	C END ANNUAL (4 QUARTERS) LOOP - CALL YEAR END SUBROUTINE TO AGGREGATE	00065800
659	C AND PRINT ANNUAL TOTALS.	00065900
660	C	00066000
661	CALL YEAREND (Y)	00066100
662	C	00066200
663	999 CONTINUE	00066300
664	C	00066400
665	1998 WRITE (6, 5000) CRS	00066500
666	IF (YRFLAG .LE. 1) WRITE (11, 5000) CRS	00066600
667	5000 FORMAT ('END OF YR OUTPUT', 14, ' COURSES PROCESSED', /, ' / ')	00066700
668	C	00066800
669	STOP	00066900

TABLE V-15 (CONTINUED)

590 V-153

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

CARD NO	****	CONTENTS	****
670		END	00067000
671			00067100
672		SUBROUTINE PRERUN (X)	00067200
673	C		00067300
674		IMPLICIT INTEGER*2 (A-Z,*)	00067400
675	C		00067500
676		COMMON DATA FOR CLASS DATA MATRIX	00067600
677	C		00067700
678		REAL*4 LEN, NOSHON, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, CDP	00067800
679		REAL*4 TONAND, SETBAK	00067900
680	C		00068000
681		COMMON /DATA/ CDP (176), CRSRUN (176), CONV (3,176), LEN (3,176)	00068100
682		COMMON /DATA/ CAP (3,176), BCAP (3,176), CMGWA (2,176)	00068200
683		COMMON /DATA/ OFFSET (176), DEMAND (3,176), RDMAND (3,176)	00068300
684		COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)	00068400
685		COMMON /DATA/ BKLOG (176), NOSHON (176), BKLGPL (176)	00068500
686		COMMON /DATA/ BKLG (176), TONAND, SETBAK	00068600
687	C		00068700
688		COMMON FOR COURSE ACTIVE MATRIX ELEMENTS	00068800
689	C		00068900
690		REAL*4 ACTCTR	00069000
691		COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG(250)	00069100
692	C		00069200
693		COMMON FOR COMMUNICATION BETWEEN SUBROUTINES	00069300
694	C		00069400
695		INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE	00069500
696		REAL*4 TEM, TEM1, TEM2, TEM3, TEM4, TEM5, BLEN	00069600
697	C		00069700
698		COMMON DUMMY, BCONV, BLEN, BCAP, SBCAP, LAST, COURSE	00069800
699		COMMON BR1, BR2, BR3, BR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5	00069900
700		COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5	00070000
701		COMMON YEAR, CASES, Q, W, WKOFF, INIT, WHERE, NEGLG, AOBCON	00070100
702		COMMON TRACEP, RLSPLG, ENDFLG, PREFLG, YRFLG, YEARN, PRINTF	00070200
703	C		00070300
704			00070400
705	C	THIS SUBROUTINE HANDLES THE UNIQUE SITUATION WHERE A NEGATIVE OFFSET	00070500
706		C HAS BEEN SPECIFIED TO START A COURSE PRIOR TO THE START OF A MODEL RUN	00070600
707	C	THIS SITUATION EXISTS FOR COURSES OF RELATIVELY LONG DURATION, AND	00070700
708	C	RELATIVELY FEW CONVENINGS. IT IS USEFUL TO INDICATE TRUE AOB DURING	00070800
709	C	A QUARTER.	00070900
710			00071000
711	C	A CODE OF 0 IS IN (X) IF CALLED BY COURSE RELEASE, 2 IF CALLED BY END	00071100
712	C		00071200
713		IF (X) 100, 100, 1000	00071300
714	C		00071400
715		C CALLED BY RELEASE, TEST IF COURSE SHOULD BE RELEASED. CRITERIA IS THAT	00071500
716	C	COURSE LENGTH IS SUCH THAT COURSE WILL STILL BE RUNNING AT MODEL START	00071600
717	C	TEST INIT TO SEE IF GENERAL PRERUN OR NEG OFFSET PRERUN	00071700
718	C		00071800
719			00071900
720		100 TEM = 14. - W	00072000
721		IF (BLEN .LE. TEM) GO TO 1999	00072100
722	C		00072200
723		C COURSE SHOULD BE RELEASED - SET DUMMY TO 1 FOR RETURN.	00072300
724	C	MODIFY LENGTH TO REFLECT WEEKS REMAINING IN 1ST QUARTER OF COURSE.	00072400
725	C		00072500
726		DUMMY = 1	00072600
727		BLEN = BLEN - TEM	00072700
728	E		00072800
729	C	TRACE PRINT ROUTINE - PRINT ONLY IF PROPER TRACE FLAG IS SET	00072900
730	C		00073000
731		IF (PREFLG) 1999, 1999, 3001	00073100
732		3001 WRITE (6, 30001) CDP (COURSE), COURSE, WKOFF, BLEN	00073200
733		3000 FORMAT (1' PRERUN CALLED - CDP = ', A4, ' POSITION = ', I5,	00073300
734		1' OFFSET = ', I4, ' LENGTH IN 1ST QTR = ', F4.1)	00073400
735		GO TO 1999	00073500
736	C		00073600
737			00073700
738	C	HERE IF PRERUN CLOSEOUT ROUTINE	00073800
739	E		00073900
740		1000 DO 500 J = 1, 250	00074000
741		IF (ACTIVE (J)) 500, 500, 401	00074100
742	C		00074200
743		C ACTIVE COURSE AT 'J', CALC POSITION IN CLASS DATA MATRIX	00074300
744	C		00074400
745		401 ITEM = ACTIVE (J) / 1000	00074500
746		ITEM = ACTIVE (J) - ITEM * 1000	00074600
747	C		00074700
748		C FIND LENGTH FOR NEG DAYS CALCULATION.	00074800
749	C	ACTCTR CONTAINS NUMBER OF WEEKS REMAINING TILL CLOSEOUT OF COURSE.	00074900
750	C		00075000
751		BLEN = LEN (1, ITEM) - ACTCTR (J)	00075100
752	C		00075200
753			00075300
754	C	TRACE PRINT ROUTINE - PRINT ONLY IF PROPER TRACE FLAG IS SET	00075400
755	C		00075500
756		IF (PREFLG) 403, 403, 402	00075600
757		402 WRITE (6, 4396) CDP (ITEM), ACTCTR (J), BLEN	00075700
758		4396 FORMAT (1' PRESTANT CLOSEOUT CDP = ', A4, 3X, 'ACTCTR = ', F5.1,	00075800
759		1' NEGLN = ', F5.1)	00075900
760	C		00076000
761			00076100
762	C	TEST AOB CONSTANT FOR WHICH METHOD OF CALC STUDENT DAYS	00076200
763		403 IF (AOBCON .GT. 3001) GO TO 450	00076300
764	C		00076400
765		C HERE IF CLASS DAYS METHOD USED TO CALCULATE AOB.	00076500
766	C		00076600
767		ACTNEG (J) = BLEN * ACTUTL (J) * .5. + .01	00076700
768		GO TO 500	00076800
769	E		00076900
770		C HERE IF CALANDER DAYS METHOD USED FOR AOB CALCULATION.	00077000
771	C		00077100
772		450 ITEM1 = BLEN - 1	00077200
773		TEM = (ITEM1 * 2) + (BLEN * 5)	00077300
774		ACTNEG (J) = TEM * ACTUTL (J) * .01	00077400
775	C		00077500
776		500 CONTINUE	00077600
777	C	HERE IF NO MORE ACTIVE COURSES - EXIT SUBROUTINE	00077700
778	C		00077800
779		NEGLG = 0	00077900
780	C		00078000
781		1999 CONTINUE	00078100

TABLE V-15 (CONTINUED)

V-154 600

TAEG REPORT NO. 29

08/19/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KFND- FLOWCHARTS

CARD NO	****	CONTENTS	****
787	C	RETURN	00078200
788		END	00078300
789			00078400
790			00078500
791		SUBROUTINE CRSRLS (X)	00078600
792	C		00078700
793	C	COURSE RELEASE (START) SUBROUTINE - RELEASES COURSE; CALCULATES SUPERS	00078800
794	C	SEATS & ATTENDANCE, LOCAL QUOTA CONTROL SCHEDULING, BACKLOG, NOSHOWS,	00078900
795	C	SUBSTITUTE QUOTAS, AND ULTIMATE CLASS UTILIZATION, INCLUDING SETBACKS.	00079000
796	C		00079100
797	C	COURSE TOTALS - ADDED TO QUARTER TOTALS AS COURSE RELEASES;	00079200
798	C	CAPACITY, UTILIZATION, NOSHOWS, BACKLOG, SUBSTITUTE QUOTAS.	00079300
799	C		00079400
800		IMPLICIT INTEGER*2 (A-Z,0)	00079500
801		REAL*4 BDMAND, BDMND	00079600
802	C		00079700
803	C	COMMON DATA FOR CLASS DATA MATRIX	00079800
804	C		00079900
805		REAL*4 LEN, NOSHOW, NOSMPL, BKLGPL, BPOOL, NADIS, FAIL, COP	00080000
806		REAL*4 TOMAND, SETBAK	00080100
807	C		00080200
808		COMMON /DATA/ COP (176), CRSRUN (176), CONV (3,176), LEN (3,176)	00080300
809		COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWR (2,176)	00080400
810		COMMON /DATA/ OPFSET (176), DEMAND (3,176), BDMAND (3,176)	00080500
811		COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSMPL (176)	00080600
812		COMMON /DATA/ BKLOG (176), NOSHOW (176), BKLGPL (176)	00080700
813		COMMON /DATA/ BRLG (176), TOMAND, SETBAK	00080800
814	C		00080900
815	C	QUARTERLY AND ANNUAL COURSE TOTALS ACCUMULATION	00081000
816	C		00081100
817		REAL*4 TFAIL, TNADIS	00081200
818		INTEGER*4 TSDAYS, TCAP, TUTIL	00081300
819	C		00081400
820		COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176)	00081500
821		COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHO (5, 176)	00081600
822		COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)	00081700
823	C		00081800
824	C	COMMON FOR COURSE ACTIVE MATRIX ELEMENTS	00081900
825	C		00082000
826		REAL*4 ACTCTR	00082100
827		COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG (250)	00082200
828	C		00082300
829	C	COMMON FOR COMMUNICATION BETWEEN SUBROUTINES	00082400
830	C		00082500
831		INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE	00082600
832		REAL*4 TEM, TEM1, TEM2, TEM3, TEM4, TEM5, BLEN	00082700
833	C		00082800
834		COMMON DUMMY, BCONV, BLEN, BCAP, BDCAP, LAST, COURSE	00082900
835		COMMON BRL, BR2, BR3, BR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5	00083000
836		COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5	00083100
837		COMMON YEAR, CRSES, G, W, WKOFF, INIT, WHERE, NEGLG, AORCOM	00083200
838		COMMON TRACEF, RLSPGL, ENDPGL, PREPLG, YRPLG, YEARIN, PRINTF	00083300
839	C		00083400
840	C		00083500
841	C	SEARCH ACTIVE MATRIX FOR FIRST AVAILABLE SLOT FOR NEW ACTIVE CONVENING.	00083600
842	C	ACTIVE (Y) IS ZERO IF NOT IN USE, HAS POINTER TO CRSE MATRIX IF IN USE	00083700
843	C	LAST IS POSITION LAST USED TO INSERT A COURSE, START SEARCH FROM THERE	00083800
844	C	LAST IS 1 IF THIS IS FIRST COURSE RELEASE FOR THE WEEK.	00083900
845	C		00084000
846	C		00084100
847	C		00084200
848	C	TEST IF LOCATION UNUSED IN ACTIVE MATRIX, EXIT IF FREE.	00084300
849	C		00084400
850		DO 10 Y = LAST, 250	00084500
851		IF (ACTIVE (Y)) 90, 90, 10	00084600
852		10 CONTINUE	00084700
853	C		00084800
854	C	HERE IF TABLE FULL - CANNOT RELEASE COURSE-WRITE ERROR MESSAGE.	00084900
855	C		00085000
856		WRITE (6, 1000) (COP (X))	00085100
857		1000 FORMAT (0H 'COURSE ACTIVE TABLE FULL - COURSE NOT RELEASED',	00085200
858		1 ' COURSE NUMBER IS', A6)	00085300
859	C		00085400
860	C	EXIT SUBROUTINE	00085500
861	C		00085600
862	C	GO TO 999	00085700
863	C		00085800
864	C		00085900
865	C		00086000
866	C	HAVE FOUND OPENING IN TABLE, OPENING IS 'Y', COURSE POINTER IS 'X'.	00086100
867	C		00086200
868	C	TEST IF NEGLG IS ON 1 INDICATES MODEL PRESTART CONVENING).	00086300
869	C		00086400
870		50 IF (NEGLG) 60, 60, 51	00086500
871	C		00086600
872	C	HERE IF FLAG IS ON - CALL PRESTART SUBROUTINE TO TEST IF COURSE SHOULD	00086700
873	C	BE STARTED. INIT RETURN CODE (DUMMY) TO 0	00086800
874	C		00086900
875		51 DUMMY = 0	00087000
876		CALL PRERUN (0)	00087100
877	C		00087200
878	C	RETURN CODE 1 IF COURSE TO BE STARTED, 0 IF TO SKIP (DUMMY)	00087300
879	C	IF COURSE TO BE STARTED, SKIP OVER QUARTERLY TOTAL ACCUMULATE.	00087400
880	C		00087500
881		IF (DUMMY) 999, 999, 63	00087600
882	C		00087700
883	C		00087800
884	C	COURSE SHOULD BE RELEASED NORMALLY - ACCUMULATE TOTALS IN QUARTER	00087900
885	C	FOR CONVENINGS AND CAPACITY.	00088000
886	C		00088100
887		60 TCONV (Q, X) = TCONV (Q, X) + 1	00088200
888		TCAP (Q, X) = TCAP (Q, X) + BCAP	00088300
889	C		00088400
890	C	LOAD ACTIVE MATRIX & BUMP CRSRUN COUNTER IN COURSE MATRIX, PRESTART	00088500
891	C	COURSES ENTER ROUTINE HERE. SAVE LAST AS NEXT POINTER TO ACTIVE	00088600
892	C		00088700
893		63 CRSRUN (X) = CRSRUN (X) + 1	00088800
		ACTIVE (Y) = COURSE	00088900
		ACTCTR (Y) = BLEN	00089000
		ACTNEG (Y) = 0	00089100
		LAST = Y	00089200
	C		00089300

TABLE V-15 (CONTINUED)

V-155 601

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

CARD NO

CONTENTS

```

894 C ROUTINE TO ALLOW MULTI YEAR RUN WITH ONLY 1 YEAR SCHEDULE DATA 00089400
895 C CRITERIA: USE REVISED DEMAND IF AVAILABLE. USE CHANGE DATA IF CHG FLG 00089500
896 C 00089600
897     ITEM = COURSE / 1000 00089700
898     IF (YEARUM .LT. 2) GO TO 70 00089800
899     IF (ITEM .GT. 1) GO TO 70 00089900
900     IF (DEMAND (YEARUM, X)) 70, 70, 65 00090000
901     65 ITEM = YEARUM 00090100
902     70 BDMAND = DEMAND (ITEM, X) - BDMAND (ITEM, X) 00090200
903     IF (BDMAND) 71, 72, 72 00090300
904     71 BDMAND = 0 00090400
905     72 BDMAND = BDMAND (ITEM, X) 00090500
906 00090600
907 C CHECK IF BUPERS HAS ANY CONTROLLED DEMAND FOR THIS COURSE-ITEM IS NUMB 00090700
908 C CURRENTLY MODEL ALLOWS BUPERS TO OVERBOOK THERE COURSE 00090800
909 C 00090900
910     ITEM = 0 00091000
911     IF (BDMAND) .05, 105, 101 00091100
912 C 00091200
913 C BUPERS HAS DEMAND - CALC DEMAND PER CONVENING. 00091300
914 C TEN EQUALS BUPERS STUDENTS (REAL). 00091400
915 C 00091500
916     101 TEN = 0 00091600
917     TEN1 = BCONV 00091700
918     IF (BCONV) 103, 103, 102 00091800
919     102 TEN = BDMAND / TEN1 00091900
920 C 00092000
921 C NOW PUT ANY FRACTIONAL DEMAND INTO SAVE POOL, ITEM NOW EQ TO BUPERS 00092100
922 C STUDENTS (INTEGER). 00092200
923 C 00092300
924     103 ITEM = TEN 00092400
925     BPOOL (X) = BPOOL (X) + (TEN - ITEM) 00092500
926 C 00092600
927     IF (BPOOL (X) .LT. 1) GO TO 105 00092700
928 C 00092800
929 C POOL HAS MORE THAN 1 STUDENT, RELEASE & CLEAR POOL OF WHOLE STUDENTS. 00092900
930 C 00093000
931     ITEM1 = BPOOL (X) 00093100
932     BPOOL (X) = BPOOL (X) - ITEM1 00093200
933     ITEM = ITEM + ITEM1 00093300
934 C 00093400
935 C END BUPERS DEMAND, ITEM = NUMBER OF STUDENTS, 0 IF NO BUREAU DEMAND. 00093500
936 C ENTRY IF NO BP DEMAND. 00093600
937 C 00093700
938 C NOW RELEASE LOCAL QUOTA CONTROL DEMAND - SEATS AVAILABLE = CAPACITY 00093800
939 C MINUS BUREAU CONTROLLED SEATS. 00093900
940 C 00094000
941     105 ITEM1 = BCAP - BSCAP 00094100
942     IF (ITEM1) 1105, 1105, 1106 00094200
943     1105 ITEM1 = 0 00094300
944 C 00094400
945 C FIND LOCAL DEMAND FOR COURSE - DEMAND = ANNUAL DEMAND / CONVENINGS. 00094500
946 C ADD THIS DEMAND (ITEM) TO BKLGPL OR USE AS DEMAND IF IN PRERUM 00094600
947 C IF IN INIT (PRERUM) MODE-SET UP CLASSES BUT DONT ADJUST POOLS 00094700
948 C 00094800
949     1106 TEN = BDMAND / BCONV 00094900
950     IF (INEGFLG) 107, 107, 106 00095000
951 C 00095100
952 C HERE IF NEG FLG ON- HAVE BUPERS (ITEM), NOW ADD LOCAL - NO SHOW (ITEM) 00095200
953     106 ITEM2 = TEN - (ITEM + NOSHOW (X)) 00095300
954     IF (ITEM2 .GT. ITEM1) ITEM2 = ITEM1 00095400
955     ACTUTL (V) = ITEM + ITEM2 00095500
956     GO TO 999 00095600
957 C 00095700
958 C HERE IF NORMAL RELEASE - ADJUST POOLS ETC 00095800
959 C 00095900
960     107 BKLGPL (X) = BKLGPL (X) + TEN 00096000
961 C 00096100
962 C RELEASE LOCAL STUDENTS - MAKE INIT ASSUMPTION ENTIRE POOL CAN FIT. 00096200
963 C ITEM2 EQUALS LOCAL QUOTA CONTROL STUDENTS. 00096300
964 C 00096400
965     ITEM2 = BKLGPL (X) 00096500
966 C 00096600
967 C TEST IF POOL GT CAPACITY. 00096700
968 C CLAMP TO CAPACITY IF GREATER. 00096800
969 C ITEM1 IS NOW LOCAL QUOTA CONTROL CAPACITY 00096900
970 C 00097000
971     IF (ITEM2 .GT. ITEM1) ITEM2 = ITEM1 00097100
972 C 00097200
973 C RELEASE THESE STUDENTS TO COURSE, CLEAR FROM POOL. 00097300
974     BKLGPL (X) = BKLGPL (X) - ITEM2 00097400
975 C 00097500
976 C NOW TEST FOR LOCAL NO SHOWS 00097600
977     NOSHPL (X) = NOSHPL (X) + ITEM2 + NOSHOW (X) 00097700
978 C 00097800
979 C SEE IF GT 1 IN POOL. 00097900
980     ITEM3 = NOSHPL (X) 00098000
981     IF (ITEM3) 111, 111, 110 00098100
982 C 00098200
983 C NO SHOWS GT 1, ADD TO TOTALS & TAKE FROM CLASS. 00098300
984 C ITEM3 IS STUDENTS FROM NO SHOW POOL 00098400
985 C 00098500
986     110 TNOSHO (Q, X) = TNOSHO (Q, X) + ITEM3 00098600
987     ITEM2 = ITEM2 - ITEM3 00098700
988     NOSHPL (X) = NOSHPL (X) - ITEM3 00098800
989     111 CONTINUE 00098900
990 C 00099000
991 C NOW TOTAL STUDENTS & SEE IF FULL CAPACITY. 00099100
992 C ITEM IS BUPERS STUDENTS, ITEM2 IS LOCAL STUDENTS AFTER NO SHOW 00099200
993 C 00099300
994     ACTUTL (V) = ITEM + ITEM2 00099400
995 C 00099500
996     ITEM4 = 0 00099600
997     IF (ACTUTL (V) .GE. BCAP) GO TO 114 00099700
998     ITEM4 = .1 * BCAP + .3 00099800
999 C 00099900
1000 C CAPACITY NOT FULL - CHECK IF CAN RELEASE THESE FROM BACKLOG POOL 00100000
1001 C 00100100
1002     ITEM5 = BKLGPL (X) 00100200
1003     IF (ITEM5) 114, 114, 113 00100300
1004 C 00100400
1005 C BACKLOG POOL GT 1, RELEASE SUBSTITUTE QUOTAS 00100500

```

TABLE V-15 (CONTINUED)

602 V-156

TAEG REPORT NO. 29

08/15/79

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

CARD NO

CONTENTS

```

1004 C CLAMP STUDENTS TO MAX IN POOL. 00100600
1007 C 00100700
1008 113 IF (ITEM5 .LT. ITEM4) ITEM4 = ITEM5 00100800
1009 BRLGPL (X) = BRLGPL (X) - ITEM4 00100900
1010 ACTUTL (Y) = ACTUTL (Y) + ITEM4 00101000
1011 C 00101100
1012 C 00101200
1013 114 TUTIL (Q,X) = TUTIL (Q,X) + ACTUTL (Y) 00101300
1014 999 CONTINUE 00101400
1015 C 00101500
1016 C /////////////////////////////////////////////////// 00101600
1017 C TRACE PRINT ROUTINE - PRINT ONLY IF PROPER TRACE FLAG IS SET 00101700
1018 IF (IRLSFLG) 1010, 1010, 1001 00101800
1019 1001 WRITE (6, 1002) CDP (X), ACTUTL (Y), BLEN, X, LAST 00101900
1020 I, ITEM, ITEM2, ITEM4, ITEM5 00102000
1021 1002 FORMAT (' RELEASE- CDP= ', A4, ' STUDENTS= ', I3, ' LENGTH= ', 00102100
1022 I, F9.1, ' CRS SEQ= ', I4, ' RUN POS(TH)= ', I4, ' BUPRS= ', I3, ' 00102200
1023 ZLOCAL= ', I3, ' SUBQTA= ', I2, ' NOSH0= ', I3) 00102300
1024 C 00102400
1025 IF (NEGFLG .GT. 0) WRITE (6, 1003) DUMMY 00102500
1026 1003 FORMAT (' ', T132, 'P', I1) 00102600
1027 1010 CONTINUE 00102700
1028 C /////////////////////////////////////////////////// 00102800
1029 C 00102900
1030 RETURN 00103000
1031 END 00103100
1032 C 00103200
1033 SUBROUTINE CRSEMD (X) 00103300
1034 C 00103400
1035 C SUBROUTINE CRSEMD CALCULATES PASS/FAIL/SETBACK, NACDISENROLLMENT, 00103500
1036 C AND CALCULATES UTILIZATION, TOTALS FOR QUARTERLY REPORT 00103600
1037 C 00103700
1038 IMPLICIT INTEGER*2 (A-Z,B) 00103800
1039 C 00103900
1040 C COMMON DATA FOR CLASS DATA MATRIX 00104000
1041 C 00104100
1042 REAL*4 LEN, NOSH0, NOSHPL, BRLGPL, BPOOL, NADIS, FAIL, CDP 00104200
1043 REAL*4 T0MAND, SETBAK 00104300
1044 C 00104400
1045 COMMON /DATA/ CDP (176), CRSRUN (176), CONV (3,176), LEN (3,176) 00104500
1046 COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWR (2,176) 00104600
1047 COMMON /DATA/ OFFSET (176), DEMAND (3,176), ROMAND (3,176) 00104700
1048 COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176) 00104800
1049 COMMON /DATA/ BRLGLOG (176), NOSH0 (176), BRLGPL (176) 00104900
1050 COMMON /DATA/ BREG (176), T0MAND, SETBAK 00105000
1051 C 00105100
1052 C QUARTERLY AND ANNUAL COURSE TOTALS ACCUMULATION 00105200
1053 C 00105300
1054 REAL*4 TFAIL, TNADIS 00105400
1055 INTEGER*4 TSDAYS, TCAP, TUTIL 00105500
1056 C 00105600
1057 COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176) 00105700
1058 COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSH0 (5, 176) 00105800
1059 COMMON /TOTALS/ TNADIS (5, 176), TBRLOG (5, 176), TCONV (5, 176) 00105900
1060 C 00106000
1061 C COMMON FOR COURSE ACTIVE MATRIX ELEMENTS 00106100
1062 C 00106200
1063 REAL*4 ACTCTR 00106300
1064 COMMON /RUM/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG (250) 00106400
1065 C 00106500
1066 C COMMON FOR COMMUNICATION BETWEEN SUBROUTINES 00106600
1067 C 00106700
1068 INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE 00106800
1069 REAL*4 TEN, TEM1, TEM2, TEM3, TEM4, TEM5, BLEN 00106900
1070 C 00107000
1071 COMMON DUMMY, BCONV, BLEN, BCAP, BRCAP, BAST, COURSE 00107100
1072 COMMON B1, BR2, BR3, BR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5 00107200
1073 COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5 00107300
1074 COMMON YEAR, CRSES, Q, W, XOFF, INIT, WHERE, NEGFLG, AORCON 00107400
1075 COMMON TRACEF, IRLSFLG, ENDFLG, PREFLG, YRFLG, YEARIN, PRINTF 00107500
1076 C 00107600
1077 C 00107700
1078 C 00107800
1079 12 = 0 00107900
1080 ITEM2 = 0 00108000
1081 J = ACTIVE (X) 00108100
1082 C 00108200
1083 C CALLING PARAMETER 'X' IS SUBSCRIPT OF COURSE IN ACTIVE MATRIX. 00108300
1084 C ACTIVE (X) CONTAINS RELATIVE COURSE NUMBER IN COURSE MATRIX, HAS 1000 00108400
1085 C ADDED IF '1' SCHED, 2000 IF '2' SCHED, 3000 IF '3' SCHED 00108500
1086 C 00108600
1087 ITEMS = J / 1000 00108700
1088 J = J - ITEMS * 1000 00108800
1089 C 00108900
1090 BLEN = LEN (ITEMS, J) 00109000
1091 C 00109100
1092 C CALCULATE FAILURES - FAILURE RATE FROM REGRESSION CONSTANTS 00109200
1093 C NOTE - J POINTS TO COURSE MATRIX, X POINTS TO ACTIVE MATRIX 00109300
1094 C 00109400
1095 TEN = FAIL (J) + ACTUTL (X) 00109500
1096 TFAIL (Q, J) = TFAIL (Q, J) + TEN 00109600
1097 C 00109700
1098 C CALCULATE NON-ACADEMIC DISENROLLMENT - RATE FROM DATA BASE 00109800
1099 C 00109900
1100 TEM1 = NADIS (J) + ACTUTL (X) 00110000
1101 TNADIS (Q, J) = TNADIS (Q, J) + TEM1 00110100
1102 C 00110200
1103 C TEST FOR SETBACK POSSIBILITY 00110300
1104 C CRITERIA FOR SETBACK: COURSE GT 2 WEEKS, MULTIPLE CONVERINGS, FAILURE 00110400
1105 C RATE TO PRODUCE SETBACKS. 00110500
1106 C 00110600
1107 IF (BLEN .LT. 2.0) GO TO 100 00110700
1108 IF (ICRSRUN (J) .LT. 2) GO TO 100 00110800
1109 TEM2 = TEN + SETBAK * .5 00110900
1110 IF (ITEM2 .LT. 1.5) GO TO 100 00111000
1111 C 00111100
1112 C HERE IF SETBACKS MAY OCCUR 00111200
1113 C 00111300
1114 GO TO 200 00111400
1115 C 00111500
1116 C TOTAL COURSE AND CLOSEOUT ACTIVE MATRIX FOR COURSE 00111600
1117 C 00111700

```

TABLE V-15 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KENO- FLOWCHARTS

CARD NO

CONTENTS

1118	100 ACTIVE (X) = 0	00111800
1119	C	00111900
1120	C CALCULATE TOTAL STUDENT DAYS FOR AOB CALCULATION.	00112000
1121	C ACTNEG CONTAINS DAYS CHARGED TO OTHER QUARTER OR OTHER CONVENINGS.	00112100
1122	C	00112200
1123	C TEST WHICH METHOD OF AOB CALCULATION TO BE USED.	00112300
1124	IF (AOBCON .GT. 300) GO TO 430	00112400
1125	C	00112500
1126	C HERE IF CLASS DAYS METHOD TO BE USED	00112600
1127	TSDAYS (Q, J) = TSDAYS (Q, J) + (ISLEN * 5. * ACTUTL (X))	00112700
1128	1 + .01) * ACTNEG (X)	00112800
1129	GO TO 440	00112900
1130	C	00113000
1131	C HERE IF YEARLY METHOD TO BE USED.	00113100
1132	C	00113200
1133	430 ITEM1 = ISLEN - 1	00113300
1134	TEM = (ITEM1 * 2) + (ISLEN * 5.)	00113400
1135	TSDAYS (Q, J) = TSDAYS (Q, J) + TEM * A.TUTL (X) * .01)	00113500
1136	1 - ACTNEG (X)	00113600
1137	440 CONTINUE	00113700
1138	C	00113800
1139	C CLOSE OUT COURSE. RESET ACTIVE & RUN FLAG.	00113900
1140	C	00114000
1141	ACTIVE (X) = 0	00114100
1142	CRSRUN (J) = CRSRUN (J) - 1	00114200
1143	IF (CRSRUN (J) .LT. 0) CRSRUN (J) = 0	00114300
1144	GO TO 999	00114400
1145	C	00114500
1146	C	00114600
1147	C ***** BACK ROUTINE *****	00114700
1148	C HAVE SETBACKS - SEARCH OUT PROPER CONVENING TO SET BACK TO.	00114800
1149	C	00114900
1150	C INIT TEST VALU25	00115000
1151	200 ITEMS = 1	00115100
1152	ITEM = ACTIVE (X)	00115200
1153	TEMS = 999.	00115300
1154	ITEM2 = 0	00115400
1155	ITEM3 = 0	00115500
1156	C	00115600
1157	C	00115700
1158	GO 120 12 = 1, 290	00115800
1159	ITEM1 = ACTIVE (12)	00115900
1160	IF (ITEM1) 120, 120, 101	00116000
1161	C HAVE ACTIVE COURSE - TEST IF OURS; DUMMY=SCHED, ITEM1=CRSNO	00116100
1162	101 DUMMY = ITEM1 / 1000	00116200
1163	ITEM1 = ITEM1 - DUMMY * 1000	00116300
1164	IF (ITEM1 .NE. J) GO TO 120	00116400
1165	C HAVE OUR COURSE NUMBER-TEST IF ONE WE ARE ENDING	00116500
1166	IF (12 .EQ. X) GO TO 118	00116600
1167	C	00116700
1168	C FOUND ONE OF OUR COURSES-TEST IF EARLIEST CONVENING.	00116800
1169	IF (ACTCTR (12) .GT. TEMS) GO TO 118	00116900
1170	C	00117000
1171	C EARLIEST SO FAR, SAVE WEEKS & POSITION	00117100
1172	TEMS = ACTCTR (12)	00117200
1173	ITEM3 = 12	00117300
1174	C	00117400
1175	C SEE IF WE FOUND ALL CONVENINGS. BUMP COUNTER & TEST.	00117500
1176	C	00117600
1177	118 ITEM2 = ITEM2 + 1	00117700
1178	IF (ITEM2 .EQ. CRSRUN (J)) GO TO 121	00117800
1179	120 CONTINUE	00117900
1180	C	00118000
1181	C HERE IF DONE COURSE SEARCH OF ACTIVE MATRIX. ITEM3 IS 0 IF NO HIT.	00118100
1182	C STATEMENT 100 IS BACKWARD BRANCH TO CLOSEOUT ROUTINE	00118200
1183	C	00118300
1184	121 IF (ITEM3) 100, 100, 122	00118400
1185	C	00118500
1186	C FIND COURSE AND MODIFY TABLES TO REPRESENT SETBACKS	00118600
1187	C	00118700
1188	122 ITEM = ACTIVE (ITEM3)	00118800
1189	DUMMY = ITEM / 1000	00118900
1190	ITEM = ITEM - DUMMY * 1000	00119000
1191	TEM4 = LEN (DUMMY, ITEM)	00119100
1192	C	00119200
1193	ITEM2 = TEM2	00119300
1194	ACTUTL (ITEM3) = ACTUTL (ITEM3) + ITEM2	00119400
1195	TSETBK (Q, ITEM) = TSETBK (Q, ITEM) + ITEM2	00119500
1196	C	00119600
1197	C	00119700
1198	C NOW CALCULATE NEGATIVE STUDENT DAYS - TO COMPENSATE COURSE STUD LEFT.	00119800
1199	C ITEM2 IS SETBACKS, LEN IS FIRST COURSE LENGTH, TEM4 IS SET BACK TO CRSNO	00119900
1200	C LENGTH, TEM5 IS WKS LEFT IN SET BACK TO COURSE.	00120000
1201	C	00120100
1202	C NOW LET TEM5 EQUAL WEEKS STUDENT HAS BEEN IN SET BACK TO COURSE.	00120200
1203	TEM5 = TEM4 - TEMS	00120300
1204	C	00120400
1205	C TEST AOB MULT FOR METHOD OF AOB CALCULATION.	00120500
1206	IF (AOBCON .GT. 300) GO TO 130	00120600
1207	C	00120700
1208	C AOBCON LT 300, USE STUDENT DAYS METHOD.	00120800
1209	ACTNEG (X) = ACTNEG (X) + (ITEMS * 5. * TEM2) * .01)	00120900
1210	GO TO 100	00121000
1211	C	00121100
1212	C YEARLY AOB METHOD USED - CONVERT WEEKS TO INTEGER.	00121200
1213	C STUDENT BEGINS SETBACK TO CLASS MONDAY, WEEKEND CHARGED TO OLD COURSE	00121300
1214	C CALC TOTAL STUD DAYS, INCLUDING WEEKENDS - DUMMY IS INTEGER.	00121400
1215	C	00121500
1216	130 DUMMY = TEMS	00121600
1217	TEMS = (DUMMY * 2) + (ITEMS * 5.)	00121700
1218	ACTNEG (X) = ACTNEG (X) + (ITEMS * TEM2 * .01)	00121800
1219	GO TO 100	00121900
1220	C	00122000
1221	C	00122100
1222	C 999 CONTINUE	00122200
1223	C	00122300
1224	C	00122400
1225	C	00122500
1226	IF (ENDPLC) 1010, 1010, 1001	00122600
1227	1001 WRITE (6, 1002) CDP (J), ACTUTL (X), ISLEN, J, X	00122700
1228	1002 FORMAT (' CRS END- CDP= ', A4, ' STUDENTS= ', I3, ' LENGTH= ',	00122800
1229	I5, '1') CRS SEQ= ', I4, '1) RUN POSITN= ', I4)	00122900

TABLE V-15 (CONTINUED)

604 V-158

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

CARD NO

CONTENTS

```

1230 C
1231 IF (ITEM2.GT. 0) WRITE (4, 1005) ITEM2, ITEM3
1232 1005 FORMAT ('+', T105, 12, ' STONTS SET TO CRS ', 14)
1233 1010 CONTINUE
1234 C
1235 C//////////
1236 C
1237 RETURN
1238 END
1239
1240 SUBROUTINE QRTEND (X)
1241 C
1242 C QUARTER END ROUTINE TOTALS STUDENT DAYS OF ALL CONVENINGS IN SESSION.
1243 C AND ADDS THEM TO COURSE TOTALS. THESE DAYS ARE ALSO ENTERED AS
1244 C 'NEGATIVE' DAYS IN ACTIVE MATRIX TO PREVENT THEM FROM BEING COUNTED IN
1245 C NEXT QUARTERS TOTALS.
1246 C ROUTINE CHECKS ADBCON FOR WHICH METHOD OF TOTALLING ADB IS USED.
1247 C
1248 C
1249 IMPLICIT INTEGER*2 (A-Z,0)
1250 C
1251 C COMMON DATA FOR CLASS DATA MATRIX
1252 C
1253 REAL*4 LEN, NOSHOW, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, COP
1254 REAL*4 TDAND, SETBX
1255 C
1256 COMMON /DATA/ COP (176), CRSRUM (176), CONV (3,176), LEN (3,176)
1257 COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWR (2,176)
1258 COMMON /DATA/ OFFSET (176), DEMAND (3,176), BDAND (3,176)
1259 COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)
1260 COMMON /DATA/ BAKLOG (176), NOSHOW (176), BKLGPL (176)
1261 COMMON /DATA/ BKL (176), TDAND, SETBX
1262 C
1263 C QUARTERLY AND ANNUAL COURSE TOTALS ACCUMULATION
1264 C
1265 REAL*4 TFAIL, TNADIS
1266 INTEGER*4 TSDAYS, TCAP, TUTIL
1267 C
1268 COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBX (5, 176)
1269 COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHO (5, 176)
1270 COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)
1271 C
1272 C COMMON FOR COURSE ACTIVE MATRIX ELEMENTS
1273 C
1274 REAL*4 ACTCTR
1275 C
1276 COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG(250)
1277 C
1278 C COMMON FOR COMMUNICATION BETWEEN SUBROUTINES
1279 C
1280 INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEMS, WHERE
1281 REAL*4 TEM, TEM1, TEM2, TEM3, TEM4, TEM5, SLEN
1282 C
1283 COMMON DUMMY, BCONV, SLEN, BCAP, BRCAP, LAST, COURSE
1284 COMMON SRI,SR2,SR3,SR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5
1285 COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEMS
1286 COMMON YEAR, CRSES, Q, W, WROFF, INIT, WHERE, NEGFLG, ADBCON
1287 COMMON TRACEP, RLSPLG, ENDFLG, PREPLG, YRFLG, YEARUN,PRINTP
1288 C
1289 C
1290 C
1291 C
1292 C
1293 C TEST ACTIVE MATRIX FOR ACTIVE COURSES.
1294 C
1295 DO 900 J = 1, 250
1296 IF (ACTIVE (J)) 900, 500, 401
1297 C
1298 C ACTIVE FILE HAS A COURSE ACTIVE AT 'J'.
1299 C GET POINTER INTO COURSE MATRIX.
1300 C
1301 401 ITEM = ACTIVE (J)
1302 DUMMY = ITEM / 1000
1303 ITEM = ITEM - DUMMY * 1000
1304 SLEN = LEN (DUMMY, ITEM)
1305 C
1306 C TEST WHICH METHOD OF ADB CALCULATION TO BE USED.
1307 IF (ADBCON.GT. 300) GO TO 430
1308 C
1309 C HERE IF CLASS DAYS METHOD TO BE USED.
1310 TEM = (SLEN - ACTCTR (J)) * ACTUTL (J) * 5.
1311 GO TO 440
1312 C
1313 C HERE IF YEARLY ADB METHOD TO BE USED
1314 C CHANGE THIS WEEKEND TO THE COURSE BEING CLOSED OUT
1315 C
1316 430 TEM1 = SLEN - ACTCTR (J)
1317 ITEM1 = TEM1
1318 TEM = (ITEM1 * 2) * (ITEM1 * 5)
1319 TEM = TEM * ACTUTL (J)
1320 440 CONTINUE
1321 C
1322 C ADD TOTAL STUDENT DAYS TO COURSE & ACTIVE MATRICES
1323 C
1324 TEM = TEM * .01
1325 ACTNEG (J) = ACTNEG (J) + TEM
1326 TSDAYS (0, ITEM) = TSDAYS (0, ITEM) + TEM
1327 900 CONTINUE
1328 C
1329 C
1330 C COPY CURRENT BACKLOG POOL FIGURES INTO COURSE TOTALS
1331 C
1332 DO 811 I = 1, CRSES
1333 811 TBKLOG (0,I) = BKLGPL (I)
1334 C
1335 C COPY FRACTIONAL FAIL & NADIS INTO NEXT QUARTER TOTALS. SKIP IF 4TH QTR
1336 IF (Q.GE. 4) GO TO 813
1337 J = Q + 1
1338 DO 812 I = 1, CRSES
1339 ITEM = TFAIL (0,I)
1340 TFAIL (J,I) = TFAIL (0,I) - ITEM
1341 ITEM = TNADIS (0,I)

```

TABLE V-15 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

CARD NO

CONTENTS

```

1342      S112 TNADIS (J,1) = TNADIS (Q,1) - ITEM          00134200
1343      S113 CONTINUE                                     00134300
1344      C                                                  00134400
1345      C /////////////////////////////////////////////////// 00134500
1346      IF (TRACEP .GT. 0) WRITE (6,1000) X                00134600
1347      1000 FORMAT (10 QUARTER END ROUTINE FOR QUARTER ', I1) 00134700
1348      C /////////////////////////////////////////////////// 00134800
1349      C                                                  00134900
1350      RETURN                                              00135000
1351      END                                                00135100
1352      C                                                  00135200
1353      SUBROUTINE YEARND (Y)                               00135300
1354      C                                                  00135400
1355      C THIS SUBROUTINE CALCULATES ANNUAL TOTALS AND CALLS THE PROPER SUBROUT-00135500
1356      C LINE FOR PRINTOUT OR CRT OUTPUT. IF A TRACE FLAG IS ON THIS SUBR IS 00135600
1357      C BYPASSED AND A TRACE ONLY SUBROUTINE IS CALLED.    00135700
1358      C                                                  00135800
1359      C TOTALS ARE AGGREGATED BY COURSE, SCHOOL, AND CENTER ON AN ANNUAL BASIS00135900
1360      C WITH NO CARRY OVER TOTALS FROM YEAR TO YEAR.     00136000
1361      C                                                  00136100
1362      C                                                  00136200
1363      IMPLICIT INTEGER*2 (A-Z,B)                          00136300
1364      C                                                  00136400
1365      C COMMON FOR CLASS DATA MATRIX                     00136500
1366      C                                                  00136600
1367      REAL*4 LEN, NOSHOW, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, CDP 00136700
1368      REAL*4 TDHAND, SETBKX                               00136800
1369      C                                                  00136900
1370      COMMON /DATA/ CDP (176), CRSRUN (176), CONV (3,176), LEN (3,176) 00137000
1371      COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWR (2,176) 00137100
1372      COMMON /DATA/ OPSET (176), DEMAND (3,176), BDHAND (3,176) 00137200
1373      COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176) 00137300
1374      COMMON /DATA/ BKLOG (176), NOSHOW (176), BKLGPL (176) 00137400
1375      COMMON /DATA/ BKLG (176), TDHAND, SETBKX            00137500
1376      C                                                  00137600
1377      INTEGER*4 JND, PNEC, SCHOOL                          00137700
1378      REAL*4 PAOB, PFAIL                                    00137800
1379      REAL*8 NAME1, NAME2, CATNO1                          00137900
1380      C                                                  00138000
1381      COMMON /TEXT/ JND (176), NAME1 (176), NAME2 (176), CATNO1 (176) 00138100
1382      COMMON /TEXT/ CATNO2 (176), PNEC (176), TYPE (176), PAOB (176) 00138200
1383      COMMON /TEXT/ PFAIL (176), PRY (176), SCHOOL (176) 00138300
1384      C                                                  00138400
1385      REAL*4 TFAIL, TNADIS                                 00138500
1386      INTEGER*4 TSDAYS, TCAP, TUTIL                        00138600
1387      C                                                  00138700
1388      COMMON /TOTALS/ TCAP (5,176), TUTIL (5,176), TSETBK (5,176) 00138800
1389      COMMON /TOTALS/ TSDAYS (5,176), TFAIL (5,176), TNOSHD (5,176) 00138900
1390      COMMON /TOTALS/ TNADIS (5,176), TBKLOG (5,176), TCONV (5,176) 00139000
1391      C                                                  00139100
1392      C COMMON FOR SCHOOL AND CENTER TOTALS               00139200
1393      C                                                  00139300
1394      INTEGER*4 SUTIL, CUTIL, SCAP, CCAP, SSDAYS, CSDAYS, IFAIL, INADIS 00139400
1395      INTEGER*4 PASS, SBKLOG, CBKLOG, SBKL, CBKL          00139500
1396      REAL*4 AOB, PCTUTL, PCTNSH, PCTPAS, PCTPL, PCTSB, PCTNDS, PLEN 00139600
1397      C                                                  00139700
1398      COMMON // SUTIL (5), SCAP (5), SSDAYS (5), SSETBK (5), SNOSHD (5) 00139800
1399      COMMON // CUTIL (5), CCAP (5), CSDAYS (5), CSETBK (5), CNOSHD (5) 00139900
1400      COMMON // SBKL (5), SBKLOG (5), SCONV (5), SFAIL (5), SNADIS (5) 00140000
1401      COMMON // CCONV (5), CBKL (5), CBKLOG (5), CFAIL (5), CNADIS (5) 00140100
1402      COMMON // PCTUTL (5), PCTNSH (5), PCTNDS (5), INADIS (5) 00140200
1403      COMMON // AOB (5), PASS (5), PCTPAS (5), PCTPL (5), PCTSB (5) 00140300
1404      COMMON // IFAIL (5), PLEN (5), BKL (5), SPLAT (4), YEAR20 00140400
1405      C                                                  00140500
1406      C COMMON FOR COMMUNICATION BETWEEN SUBROUTINES     00140600
1407      C                                                  00140700
1408      INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE 00140800
1409      REAL*4 TEN, TEN1, TEN2, TEN3, TEN4, TEN5, BLEN       00140900
1410      C                                                  00141000
1411      COMMON DUMMY, SCONV, BLEN, SCAP, BSCAP, LAST, COURSE 00141100
1412      COMMON SRI,SR2,SR3,SR4, TEN, TEN1, TEN2, TEN3, TEN4, TEN5 00141200
1413      COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5       00141300
1414      COMMON YEAR, CRSES, Q, H, WKOFF, INIT, WHERE, NECPLG, AOBCON 00141400
1415      COMMON TRACEP, ALSPLG, ENOPLG, PREPLG, YRPLG, YEARUN,PRINTF 00141500
1416      C                                                  00141600
1417      C                                                  00141700
1418      C YRPLG 0 FOR CRT OUTPUT, 1 FOR BOTH, 2 FOR PRINT ONLY, 3 FOR TRACE ONLY00141800
1419      IF (YRPLG .GE. 3) GO TO 29999                      00141900
1420      C                                                  00142000
1421      C SET SPLAT TO KEY YEAR OF RUN                       00142100
1422      IF (YEARUN .LE. 1) GO TO 81001                     00142200
1423      ITEM = YEARUN - 1                                    00142300
1424      SPLAT (YEARUN) = SPLAT (ITEM)                       00142400
1425      SPLAT (ITEM) = SPLAT (4)                             00142500
1426      81001 CONTINUE                                      00142600
1427      C                                                  00142700
1428      C INIT & CLAMP RUN CONSTANTS                        00142800
1429      ITEMS = 0                                           00142900
1430      IF (AOBCON .LE. 0) AOBCON = 250                     00143000
1431      YEAR20 = YEAR - 1900                                00143100
1432      C                                                  00143200
1433      C INITIALIZE CENTER TOTALS                          00143300
1434      C                                                  00143400
1435      DO 1 Q = 1, 5                                        00143500
1436      CUTIL (Q) = 0                                       00143600
1437      CCAP (Q) = 0                                         00143700
1438      CSETBK (Q) = 0                                       00143800
1439      CSDAYS (Q) = 0                                       00143900
1440      CNOSHD (Q) = 0                                       00144000
1441      CCONV (Q) = 0                                        00144100
1442      CFAIL (Q) = 0                                        00144200
1443      CNADIS (Q) = 0                                       00144300
1444      CBKL (Q) = 0                                         00144400
1445      CBKLOG (Q) = 0                                       00144500
1446      C                                                  00144600
1447      SUTIL (Q) = 0                                       00144700
1448      SCAP (Q) = 0                                         00144800
1449      SSETBK (Q) = 0                                       00144900
1450      SSDAYS (Q) = 0                                       00145000
1451      SNOSHD (Q) = 0                                       00145100
1452      SCONV (Q) = 0                                       00145200
1453      SFAIL (Q) = 0                                       00145300

```

TABLE V-15 (CONTINUED)

TAEQ REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-XEND- FLOWCHARTS

CARD NO	*****	CONTENTS	*****
1454		SNADIS(I) = 0	00145400
1455		SBRL(I) = 0	00145500
1456		1 SBKLOG(I) = 0	00145600
1457	C		00145700
1458			00145800
1459	C	CALCULATE TOTALS & PRINT FOR EACH COURSE	00145900
1460		DO 4444 I = 1, CRSES	00146000
1461	C		00146100
1462	C	TEST FOR SCHOOL CODE CHANGE	00146200
1463	C	DONT PRINT SCHOOL SUMMARY IF THIS IS FIRST PASS	00146300
1464	C		00146400
1465		IF I1 .EQ. 1) GO TO 4	00146500
1466		IF (SCHOOL(I) .EQ. SCHOOL(I-1)) GO TO 4	00146600
1467	C		00146700
1468	C	NEW SCHOOL CODE, CALC OLD SCHOOL TOTALS & PRINT.	00146800
1469		GO TO 500	00146900
1470	C		00147000
1471	C	RETURN FROM PRINT SCHOOL TOTALS - NOW CALC TOTALS FOR CLASS	00147100
1472	C	ITEMS IS COUNTER FOR COURSE ACTUALLY CALCULATING	00147200
1473	C		00147300
1474		4 ITEMS = ITEMS + 1	00147400
1475	C		00147500
1476	C	USE 5TH POSITION IN TOTALS MATRIX TO AGGREGATE TOTALS - INIT TO ZERO	00147600
1477		TUTIL(5, I) = 0	00147700
1478		TCAP(5, I) = 0	00147800
1479		TSETBK(5, I) = 0	00147900
1480		TSDAYS(5, I) = 0	00148000
1481		TNOSHO(5, I) = 0	00148100
1482		TCONV(5, I) = 0	00148200
1483	C		00148300
1484	C	INIT INTEGER FAIL & NON-ACADEMIC DROPOUT TOTALS TO ZERO	00148400
1485	C		00148500
1486		IFAIL(5) = 0	00148600
1487		INADIS(5) = 0	00148700
1488	C		00148800
1489	C		00148900
1490	C	NOW TOTAL ANNUAL FIGURES	00149000
1491	C		00149100
1492		DO 5 Q = 1, 4	00149200
1493	C		00149300
1494		TUTIL(5, I) = TUTIL(5, I) + TUTIL(IQ, I)	00149400
1495		TCAP(5, I) = TCAP(5, I) + TCAP(IQ, I)	00149500
1496		TSETBK(5, I) = TSETBK(5, I) + TSETBK(IQ, I)	00149600
1497		TSDAYS(5, I) = TSDAYS(5, I) + TSDAYS(IQ, I)	00149700
1498		TNOSHO(5, I) = TNOSHO(5, I) + TNOSHO(IQ, I)	00149800
1499		TCONV(5, I) = TCONV(5, I) + TCONV(IQ, I)	00149900
1500	C		00150000
1501	C	CONVERT TO INTEGER, ROUND, & TOTAL FAILURES & NON-ACADEMIC DISENROLLS	00150100
1502	C		00150200
1503		IFAIL(IQ) = 0	00150300
1504		IFAIL(IQ) = IFAIL(IQ, I) + .5	00150400
1505		IFAIL(5) = IFAIL(5) + IFAIL(IQ)	00150500
1506	C		00150600
1507		INADIS(IQ) = 0	00150700
1508		INADIS(IQ) = INADIS(IQ, I) + .5	00150800
1509		INADIS(5) = INADIS(5) + INADIS(IQ)	00150900
1510	C		00151000
1511	C	TOTAL DATA FROM INDIVIDUAL SCHOOL TOTALS	00151100
1512	C		00151200
1513		SUTIL(IQ) = SUTIL(IQ) + TUTIL(IQ, I)	00151300
1514		SCAP(IQ) = SCAP(IQ) + TCAP(IQ, I)	00151400
1515		SSETBK(IQ) = SSETBK(IQ) + TSETBK(IQ, I)	00151500
1516		SSDAYS(IQ) = SSDAYS(IQ) + TSDAYS(IQ, I)	00151600
1517		SNOSHO(IQ) = SNOSHO(IQ) + TNOSHO(IQ, I)	00151700
1518		SCONV(IQ) = SCONV(IQ) + TCONV(IQ, I)	00151800
1519		SFAIL(IQ) = SFAIL(IQ) + IFAIL(IQ)	00151900
1520		SNADIS(IQ) = SNADIS(IQ) + INADIS(IQ, I)	00152000
1521	C		00152100
1522	C	TOTAL DATA FOR FLEET TRAINING CENTER TOTALS	00152200
1523	C		00152300
1524		CUTIL(IQ) = CUTIL(IQ) + TUTIL(IQ, I)	00152400
1525		CCAP(IQ) = CCAP(IQ) + TCAP(IQ, I)	00152500
1526		CSETBK(IQ) = CSETBK(IQ) + TSETBK(IQ, I)	00152600
1527		CSDAYS(IQ) = CSDAYS(IQ) + TSDAYS(IQ, I)	00152700
1528		CNOSHO(IQ) = CNOSHO(IQ) + TNOSHO(IQ, I)	00152800
1529		CCONV(IQ) = CCONV(IQ) + TCONV(IQ, I)	00152900
1530		CPAIL(IQ) = CPAIL(IQ) + IFAIL(IQ)	00153000
1531		CNADIS(IQ) = CNADIS(IQ) + INADIS(IQ, I)	00153100
1532		5 CONTINUE	00153200
1533	C		00153300
1534	C	NOW CALCULATE TOTALS & PERCENTAGES	00153400
1535	C	ASSUME CHANGE WEEK HAS NOT PASSED THIS QUARTER, INIT CAP & CONV TO 'A'	00153500
1536		BCONV = CONV(1, I)	00153600
1537		BCAP = CAP(1, I) - BCAP(1, I)	00153700
1538		TBKLOG(5, I) = TBKLOG(4, I)	00153800
1539	C		00153900
1540	C	NOW CALCULATE UTILIZATIONS & PERCENTAGES	00154000
1541		DO 12 Q = 1, 5	00154100
1542		BRL(IQ) = 0	00154200
1543		IF (TBKLOG(IQ, I) .EQ. 0) GO TO 12	00154300
1544	C		00154400
1545	C	TEST IF THERE IS A CHANGE WEEK	00154500
1546		IF (CHGWK(1, I)) 7, 7, 6	00154600
1547	C		00154700
1548	C	HERE IF THERE IS A CHANGE WEEK, CHECK IF IT HAS PASSED	00154800
1549		8 ITEM = 0	00154900
1550		IF (ITEM .GT. 4) ITEM = 4	00155000
1551		ITEM = (13 * ITEM) + (52 * (YEARUN - 1))	00155100
1552		IF (CHGWK(1, I) .LT. ITEM) GO TO 7	00155200
1553	C		00155300
1554	C	CHANGWK HAS PASSED - USE 'B' CONVEN & CAPACITY	00155400
1555		BCONV = CONV(12, I)	00155500
1556		BCAP = CAP(12, I) - BCAP(12, I)	00155600
1557	C		00155700
1558	C		00155800
1559		7 IF (BCONV) B1112, B1112, 10	00155900
1560		B1112 TBKLOG(0, I) = 0	00156000
1561		IF (IQ .EQ. 4) TBKLOG(5, I) = 0	00156100
1562		GO TO 12	00156200
1563		10 IF (BCAP) 12, 12, 11	00156300
1564		11 TEM = BCAP	00156400
1565		BRL(IQ) = (50. / BCONV) * (TBKLOG(IQ, I) / TEM)	00156500

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

CARD NO

CONTENTS

1566	IF (BRL (Q) .GT. 30) BRL (Q) = 30	00156600
1567	SBKLOG (Q) = SBKLOG (Q) + TBKLOG (Q,1)	00156700
1568	CBKLOG (Q) = CBKLOG (Q) + TBKLOG (Q,1)	00156800
1569	SBRL (Q) = SBRL (Q) + BRL (Q) + TBKLOG (Q,1)	00156900
1570	CBRL (Q) = CBRL (Q) + BRL (Q) + TBKLOG (Q,1)	00157000
1571	12 CONTINUE	00157100
1572	IF (BRL .EQ. 0) GO TO 44444	00157200
1573	C	00157300
1574	DO 20 Q = 1, 5	00157400
1575	TEM = AOBCON	00157500
1576	AOB (Q) = TSDAYS (Q,1) / TEM	00157600
1577	C MULT BY 4 IF QUARTERLY TOTAL	00157700
1578	IF (Q .LE. 4) AOB (Q) = AOB (Q) * 4.	00157800
1579	PASS (Q) = TUTIL (Q,1) - IPAIL (Q) - INADIS (Q)	00157900
1580	IF (PASS (Q) .LT. 0) PASS (Q) = 0	00158000
1581	PCTUTL (Q) = 0.	00158100
1582	TEM = TCAP (Q,1)	00158200
1583	IF (TCAP (Q,1) .GT. 0)	00158300
1584	1 PCTUTL (Q) = (TUTIL (Q,1) / TEM) * 100.	00158400
1585	C	00158500
1586	C TEST UTILIZATION TO SEE IF WE CAN CALCULATE PERCENTAGES	00158600
1587	IF (TUTIL (Q,1) 13, 13, 14	00158700
1588	C	00158800
1589	C NO UTILIZATION - ZERO PERCENTAGES & EXIT	00158900
1590	13 CONTINUE	00159000
1591	PCTNSH (Q) = 0.	00159100
1592	PCTPAS (Q) = 0.	00159200
1593	PCTPL (Q) = 0.	00159300
1594	PCTSB (Q) = 0.	00159400
1595	PCTNDS (Q) = 0.	00159500
1596	GO TO 20	00159600
1597	C	00159700
1598	C HAVE UTILIZATION - CALC 8	00159800
1599	14 TEM = TUTIL (Q,1)	00159900
1600	TEM1 = TNSH (Q,1) + TUTIL (Q,1)	00160000
1601	PCTNSH (Q) = (TNSH (Q,1) / TEM1) * 100.	00160100
1602	PCTPAS (Q) = (PASS (Q) / TEM) * 100.	00160200
1603	PCTPL (Q) = (IPAIL (Q) / TEM) * 100.	00160300
1604	PCTSB (Q) = (TSETBK (Q,1) / TEM) * 100.	00160400
1605	PCTNDS (Q) = (INADIS (Q) / TEM) * 100.	00160500
1606	20 CONTINUE	00160600
1607	C	00160700
1608	C	00160800
1609	C CONVERT LENGTH TO DAYS FOR PRINTOUT	00160900
1610	DO 27 Q = 1, 3	00161000
1611	IF (LEN (Q,1) 28, 28, 28	00161100
1612	28 PLEN (Q) = 0.	00161200
1613	GO TO 27	00161300
1614	28 ITEM = LEN (Q,1) - 1	00161400
1615	PLEN (Q) = (LEN (Q,1) * 5.) + (ITEM * 2) * .01	00161500
1616	27 CONTINUE	00161600
1617	C	00161700
1618	C CALL OUTPUT ROUTINES, CRT IF FLAG 0 OR 1, PRINT IF 1 OR 2	00161800
1619	C SET X TO 1 FOR COURSE OUTPUT	00161900
1620	C	00162000
1621	X = 1	00162100
1622	IF (BRL .EQ. 0) GO TO 12341	00162200
1623	IF (YRPLG .LE. 1) CALL CRTOUT (X)	00162300
1624	IF (YRPLG .GE. 1) CALL NPRINT (X)	00162400
1625	12341 CONTINUE	00162500
1626	C	00162600
1627	C	00162700
1628	C IF I IS EQ CASES THIS IS LAST COURSE, SO FALL THROUGH & PRINT SCHOOL	00162800
1629	C SUMMARY. OTHERWISE GO TO END OF DO LOOP & CONTINUE.	00162900
1630	44444 IF (I .NE. CASES) GO TO 44444	00163000
1631	C	00163100
1632	C ENTRY SCHOOL TOTALS CALC ROUTINE, SET X TO 2 FOR SCHOOL OUTPUT	00163200
1633	C CALCULATE SCHOOL TOTALS (SAME ROUTINE USED FOR CENTER)	00163300
1634	C	00163400
1635	500 X = 2	00163500
1636	C	00163600
1637	C 500 IS ENTRY FOR CENTER TOTALS CALCULATIONS	00163700
1638	500 CONTINUE	00163800
1639	IF (X .EQ. 2 .AND. BR2 .EQ. 0) GO TO 12342	00163900
1640	IF (X .EQ. 3 .AND. BR3 .EQ. 0) GO TO 12342	00164000
1641	C	00164100
1642	C CALCULATE YEARLY TOTALS	00164200
1643	DO 540 Q = 1, 4	00164300
1644	SCONV (S) = SCONV (S) + SCONV (Q)	00164400
1645	SCAP (S) = SCAP (S) + SCAP (Q)	00164500
1646	SUTIL (S) = SUTIL (S) + SUTIL (Q)	00164600
1647	SNOSHO (S) = SNOSHO (S) + SNOSHO (Q)	00164700
1648	SSDAYS (S) = SSDAYS (S) + SSDAYS (Q)	00164800
1649	SFAIL (S) = SFAIL (S) + SFAIL (Q)	00164900
1650	SSETBK (S) = SSETBK (S) + SSETBK (Q)	00165000
1651	540 SNADIS (S) = SNADIS (S) + SNADIS (Q)	00165100
1652	C	00165200
1653	C	00165300
1654	C NOW CALC PERCENTAGES	00165400
1655	DO 550 Q = 1, 5	00165500
1656	C	00165600
1657	TEM = AOBCON	00165700
1658	AOB (Q) = SSDAYS (Q) / TEM	00165800
1659	IF (Q .LE. 4) AOB (Q) = AOB (Q) * 4.	00165900
1660	C	00166000
1661	PASS (Q) = SUTIL (Q) - SFAIL (Q) - SNADIS (Q)	00166100
1662	IF (PASS (Q) .LT. 0) PASS (Q) = 0	00166200
1663	C	00166300
1664	PCTUTL (Q) = 0.	00166400
1665	TEM = SCAP (Q)	00166500
1666	IF (TEM .GT. 0) PCTUTL (Q) = (SUTIL (Q) / TEM) * 100.	00166600
1667	C	00166700
1668	IF (SUTIL (Q) 913, 913, 914	00166800
1669	513 CONTINUE	00166900
1670	PCTNSH (Q) = 0.	00167000
1671	PCTPAS (Q) = 0.	00167100
1672	PCTPL (Q) = 0.	00167200
1673	PCTSB (Q) = 0.	00167300
1674	PCTNDS (Q) = 0.	00167400
1675	GO TO 520	00167500
1676	C	00167600
1677	514 TEM = SUTIL (Q)	00167700

TABLE V-15 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

CARD NO

CONTENTS

1678	TEM1 = SNOSMO (Q) + SUTIL (Q)	00167800
1679	PCTNM (Q) = (SNOSMO (Q) / TEM1) * 100.	00167900
1680	PCTPAS (Q) = (IPASS (Q) / TEM1) * 100.	00168000
1681	PCTFPL (Q) = (SFALL (Q) / TEM1) * 100.	00168100
1682	PCTSB (Q) = (SSETBK (Q) / TEM1) * 100.	00168200
1683	PCTMOS (Q) = (SNADIS (Q) / TEM1) * 100.	00168300
1684	920 CONTINUE	00168400
1685	SBRL (Q) = SBRL (Q) / SBKLOG (Q)	00168500
1686	550 CONTINUE	00168600
1687	C	00168700
1688	C CALL OUTPUT SUBROUTINE, X IS 2 FOR SCHOOL OUT, 3 FOR CENTER OUT	00168800
1689	C	00168900
1690	IF (YRFLG .LE. 1) CALL CRTOUT (X)	00169000
1691	IF (YRFLG .GE. 1) CALL NPRINT (X)	00169100
1692	12342 CONTINUE	00169200
1693	C	00169300
1694	C TEST IF END OF FILE - CALC YEAR CENTER TOTALS	00169400
1695	C TEST IF END OF FILE - GO PRINT CENTER TOTALS	00169500
1696	IF (ITEMS .EQ. CRSES) GO TO 580	00169600
1697	IF (ITEMS .GT. 900) GO TO 4444	00169700
1698	C	00169800
1699	C	00169900
1700	C KEEP RUNNING - ZERO SCHOOL TOTALS & RETURN	00170000
1701	DO 563 Q = 1, 5	00170100
1702	SUTIL (Q) = 0	00170200
1703	SCAP (Q) = 0	00170300
1704	SSETBK (Q) = 0	00170400
1705	SSDAYS (Q) = 0	00170500
1706	SNOSMO (Q) = 0	00170600
1707	SCONV (Q) = 0	00170700
1708	SFALL (Q) = 0	00170800
1709	SBRL (Q) = 0	00170900
1710	SBKLOG (Q) = 0	00171000
1711	563 SNADIS (Q) = 0	00171100
1712	C	00171200
1713	GO TO 4	00171300
1714	C	00171400
1715	C LOAD CENTER TOTALS INTO SCHOOL STORAGE - USE SCHOOL ROUTINE TO CALC	00171500
1716	C CENTER TOTALS.	00171600
1717	C	00171700
1718	580 DO 581 Q = 1, 5	00171800
1719	SUTIL (Q) = CUTIL (Q)	00171900
1720	SCAP (Q) = CCAP (Q)	00172000
1721	SSETBK (Q) = CSETBK (Q)	00172100
1722	SSDAYS (Q) = CSSDAYS (Q)	00172200
1723	SNOSMO (Q) = CNSOSMO (Q)	00172300
1724	SCONV (Q) = CCONV (Q)	00172400
1725	SFALL (Q) = CFALL (Q)	00172500
1726	SBRL (Q) = CBRRL (Q)	00172600
1727	SBKLOG (Q) = CBKLOG (Q)	00172700
1728	581 SNADIS (Q) = CNSADIS (Q)	00172800
1729	C	00172900
1730	C SET X TO 3 TO CALL CENTER OUTPUT, SET ITEMS TO 999 TO INDICATE END	00173000
1731	ITEMS = 999	00173100
1732	X = 3	00173200
1733	GO TO 560	00173300
1734	C	00173400
1735	4444 CONTINUE	00173500
1736	29999 CONTINUE	00173600
1737	C EXIT IF YEARUN EQ Y AS LAST YEAR OF RUN	00173700
1738	IF (YEARUN .EQ. Y) GO TO 6999	00173800
1739	YEAR = YEAR + 1	00173900
1740	C	00174000
1741	C SET TREND DEMANDS	00174100
1742	IF (TOMAND .LE. 0) GO TO 5555	00174200
1743	DO 5554 ITEM = 1, CRSES	00174300
1744	DO 5554 ITEM = 1, 3	00174400
1745	DEMAND (ITEM, ITEM) = DEMAND (ITEM, ITEM) + TOMAND	00174500
1746	5554 BDMAND (ITEM, ITEM) = BDMAND (ITEM, ITEM) + TOMAND	00174600
1747	5555 CONTINUE	00174700
1748	C	00174800
1749	C ZERO TOTALS FOR MULTI YEAR RUN	00174900
1750	DO 6998 I = 1, CRSES	00175000
1751	DO 6998 Q = 1, 4	00175100
1752	TUTIL (Q, I) = 0	00175200
1753	TCAP (Q, I) = 0	00175300
1754	TSETBK (Q, I) = 0	00175400
1755	TSDAYS (Q, I) = 0	00175500
1756	TNOSMO (Q, I) = 0	00175600
1757	TCONV (Q, I) = 0	00175700
1758	TFALL (Q, I) = 0	00175800
1759	6998 TNADIS (Q, I) = 0	00175900
1760	6999 CONTINUE	00176000
1761	RETURN	00176100
1762	END	00176200
1763		00176300
1764	SUBROUTINE NPRINT (X)	00176400
1765	C	00176500
1766	C SUBROUTINE TO PRINT COURSE, SCHOOL, AND CENTER TOTALS	00176600
1767	C THIS SUBROUTINE PRINTS FORMATTED OUTPUT AT A RATE OF 3 COURSES PER	00176700
1768	C PAGE. IT ALSO PRINTS TOTALS FOR A SCHOOL WHENEVER A NEW SCHOOL CODE	00176800
1769	C IS ENCOUNTERED IN THE DATA STREAM. IT ALSO PRINTS CENTER TOTALS AT	00176900
1770	C THE END OF A YEAR. SEPARATE OUTPUT FORMATS ARE PROVIDED FOR EACH YEAR	00177000
1771	C WHENEVER THE MODEL INVOLVES MULTIPLE YEAR RUNS.	00177100
1772	C	00177200
1773	C	00177300
1774	IMPLICIT INTEGER*2 (A-Z,8)	00177400
1775	C	00177500
1776	C COMMON FOR CLASS DATA MATRIX	00177600
1777	C	00177700
1778	REAL*4 LEN, NOSHOW, NOSHPL, BKLGPL, BPOOL, NADIS, FAIL, CDP	00177800
1779	REAL*4 TOMAND, SETBAK	00177900
1780	C	00178000
1781	COMMON /DATA/ CDP (176), CRSRUN (176), CONV (3,176), LEN (3,176)	00178100
1782	COMMON /DATA/ CAP (3,176), BCAP (3,176), CHGWR (2,176)	00178200
1783	COMMON /DATA/ OFFSET (176), DEMAND (3,176), BDMAND (3,176)	00178300
1784	COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSHPL (176)	00178400
1785	COMMON /DATA/ BAKLOG (176), NOSHOW (176), BKLGPL (176)	00178500
1786	COMMON /DATA/ BRLG (176), TOMAND, SETBAK	00178600
1787	C	00178700
1788	INTEGER*4 JND, PNCG, SCHOOL	00178800
1789	REAL*4 PAOB, PFALL	00178900

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

--END-- FLOWCHARTS

CARD NO

CONTENTS

1790	REAL*8 NAME1, NAME2, CATNO1	00179000
1791	C	00179100
1792	COMMON /TEXT/ JND (176), NAME1 (176), NAME2 (176), CATNO1 (176)	00179200
1793	COMMON /TEXT/ CATNO2 (176), PNEC (176), TYPE (176), PAOR (176)	00179300
1794	COMMON /TEXT/ PFAIL (176), PRTY (176), SCHOOL (176)	00179400
1795	C	00179500
1796	REAL*4 TFAIL, TNADIS	00179600
1797	INTEGER*4 TSDAYS, TCAP, TUTIL	00179700
1798	C	00179800
1799	COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBK (5, 176)	00179900
1800	COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHO (5, 176)	00180000
1801	COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)	00180100
1802	C	00180200
1803	C COMMON FOR SCHOOL AND CENTER TOTALS	00180300
1804	C	00180400
1805	INTEGER*4 SUTIL, CUTIL, SCAP, CCAP, SSDAYS, CSDAYS, TFAIL, TNADIS	00180500
1806	INTEGER*4 PASS, SBKLOG, CBKLOG, SBKL, CBKL	00180600
1807	REAL*4 AOR, PCTUTL, PCTNSH, PCTPAS, PCTPL, PCTSB, PCTNDS, PLEN	00180700
1808	C	00180800
1809	COMMON /T/ SUTIL (5), SCAP (5), SSDAYS (5), SSETBK (5), SNOSHO (5)	00180900
1810	COMMON /T/ CUTIL (5), CCAP (5), CSDAYS (5), CSETBK (5), CNOSHO (5)	00181000
1811	COMMON /T/ SBKL (5), SBKLOG (5), SCONV (5), SFAIL (5), SNADIS (5)	00181100
1812	COMMON /T/ CCONV (5), CBKL (5), CBKLOG (5), CFAIL (5), CNADIS (5)	00181200
1813	COMMON /T/ PCTUTL (5), PCTNSH (5), PCTNDS (5), TNADIS (5)	00181300
1814	COMMON /T/ AOR (5), PASS (5), PCTPAS (5), PCTPL (5), PCTSB (5)	00181400
1815	COMMON /T/ TFAIL (5), PLEN (5), BKL (5), SPLAT (4), YEAR2D	00181500
1816	C	00181600
1817	C COMMON FOR COMMUNICATION BETWEEN SUBROUTINES	00181700
1818	C	00181800
1819	INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5, WHERE	00181900
1820	REAL*4 TEM, TEM1, TEM2, TEM3, TEM4, TEM5, BLEN	00182000
1821	C	00182100
1822	COMMON DUMMY, BLEN, SCAP, BCAP, LAST, COURSE	00182200
1823	COMMON BR1, BR2, BR3, BR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5	00182300
1824	COMMON ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEM5	00182400
1825	COMMON YEAR, CRSES, Q, W, WROFF, INIT, WHERE, NEGFLG, AOBSON	00182500
1826	COMMON TRACEF, RLSPLC, ENDFLG, PREFLG, VRFLG, YEARUN, PRINTF	00182600
1827	C	00182700
1828	DATA PAGE /1/, PAGER /4/	00182800
1829	IF (PRINTF .GT. 4) RETURN	00182900
1830	C	00183000
1831	I = ITEMS	00183100
1832	C	00183200
1833	C X IS 1 FOR COURSE PRINT, 2 FOR SCHOOL PRINT, 3 FOR CENTER PRINT	00183300
1834	IF (X .EQ. 3) GO TO 900	00183400
1835	IF (X .EQ. 2) GO TO 500	00183500
1836	C	00183600
1837	C BEGIN INDIVIDUAL COURSE PRINT - CHECK IF WE HAVE PRINTED 3 ON THIS PAGE	00183700
1838	C	00183800
1839	IF (PAGER .LE. 3) GO TO 4445	00183900
1840	WRITE (4,1000) YEAR, PAGE	00184000
1841	C	00184100
1842	WRITE (4, 1001) SCHOOL (1)	00184200
1843	C	00184300
1844	PAGER = 1	00184400
1845	PAGE = PAGE + 1	00184500
1846	4445 CONTINUE	00184600
1847	C	00184700
1848	PAGER = PAGER + 1	00184800
1849	C	00184900
1850	C	00185000
1851	4999 CONTINUE	00185100
1852	C	00185200
1853	C NOW PRINT OUT INDIVIDUAL COURSE SUMMARY	00185300
1854	C	00185400
1855	WRITE (4, 2000) CDP (1), NAME1 (1), NAME2 (1)	00185500
1856	WRITE (4,2001)	00185600
1857	WRITE (4,2002) YEAR2D, YEAR2D, YEAR2D, YEAR2D	00185700
1858	C	00185800
1859	WRITE (4, 2003) JND (1), CATNO1 (1), CATNO2 (1), PNEC (1),	00185900
1860	1 TYPE (1), PRTY (1)	00186000
1861	C	00186100
1862	WRITE (4, 2004) TCONV (1,1), TCONV (2,1), TCONV (3,1), TCONV (4,1)	00186200
1863	1, TCONV (5,1)	00186300
1864	C	00186400
1865	WRITE (4, 2005) TCAP (1,1), TCAP (2,1), TCAP (3,1), TCAP (4,1),	00186500
1866	1 TCAP (5,1)	00186600
1867	C	00186700
1868	WRITE (4, 2006) PAOR (1), PFAIL (1), BKL (1), BAKLOG (1),	00186800
1869	* (TUTIL (1,1), PCTUTL (1,1), Q = 1, 5)	00186900
1870	C	00187000
1871	WRITE (4, 2007) SPLAT (1), SPLAT (2), SPLAT (3),	00187100
1872	1 (TNOSHO (1,1), PCTNSH (1,1), Q = 1, 5)	00187200
1873	C	00187300
1874	WRITE (4, 2008) TBKLOG (1,1), BKL (1,1), Q = 1, 5)	00187400
1875	C	00187500
1876	WRITE (4, 2009) CONV (1,1), CONV (2,1), CONV (3,1),	00187600
1877	* (TSDAYS (1,1), AOR (1,1), Q = 1, 5)	00187700
1878	C	00187800
1879	WRITE (4, 2010) PLEN (1), PLEN (2), PLEN (3)	00187900
1880	C	00188000
1881	WRITE (4, 2011) CAP (1,1), CAP (2,1), CAP (3,1),	00188100
1882	* (PASS (1,1), PCTPAS (1,1), Q = 1, 5)	00188200
1883	C	00188300
1884	WRITE (4, 2012) BCAP (1,1), BCAP (2,1), BCAP (3,1),	00188400
1885	* (TFAIL (1,1), PCTPL (1,1), Q = 1, 5)	00188500
1886	C	00188600
1887	WRITE (4, 2013) DEMAND (1,1), DEMAND (2,1), DEMAND (3,1),	00188700
1888	* (TSETBK (1,1), PCTSB (1,1), Q = 1, 5)	00188800
1889	C	00188900
1890	WRITE (4, 2014) BORAND (1,1), BORAND (2,1), BORAND (3,1),	00189000
1891	* (TNADIS (1,1), PCTNDS (1,1), Q = 1, 5)	00189100
1892	C	00189200
1893	WRITE (4, 2015) OFFSET (1), CMGWR (1,1), CMGWR (2,1)	00189300
1894	C	00189400
1895	GO TO 4444	00189500
1896	C	00189600
1897	C	00189700
1898	C SCHOOL TOTALS ROUTINE	00189800
1899	C	00189900
1900	500 WRITE (4, 1000) YEAR, PAGE	00190000
1901	J = 1	00190100

TABLE V-15 (CONTINUED)

TAEQ REPORT NO. 29

08/19/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

CARD NO

CONTENTS

1902	PAGE = PAGE + 1	00190200
1903	PAGER = 4	00190300
1904	C	00190400
1905	WRITE (6, 1001) SCHOOL (3)	00190500
1906	WRITE (6, 7001) SCHOOL (3)	00190600
1907	C	00190700
1908	C	00190800
1909	C ENTRY FOR PTC TOTALS	00190900
1910	C FROM HERE ON SAME ROUTINE IS USED FOR SCHOOL AND CENTER TOTALS PRINT	00191000
1911	C ROUTINE. YEAR DATA HAS BEEN C ENWRITTEN INTO SCHOOL STORAGE AREAS.	00191100
1912	C	00191200
1913	560 CONTINUE	00191300
1914	C	00191400
1915	C	00191500
1916	C	00191600
1917	C PRINT ROUTINE	00191700
1918	C PRINT SCHOOL AND CENTER TOTALS	00191800
1919	C	00191900
1920	WRITE (6, 7002)	00192000
1921	WRITE (6, 7003) YEAR20, YEAR20, YEAR20, YEAR20	00192100
1922	WRITE (6, 7004)	00192200
1923	WRITE (6, 7005) (SCOMV (Q), Q = 1, 5)	00192300
1924	WRITE (6, 7006) (SCAP (Q), Q = 1, 5)	00192400
1925	WRITE (6, 7007) (ISUTL (Q), PCTUTL (Q)), Q = 1, 5)	00192500
1926	WRITE (6, 7008) (ISMSHD (Q), PCTNSH (Q)), Q = 1, 5)	00192600
1927	WRITE (6, 7009) (ISSDAYS (Q), ADB (Q)), Q = 1, 5)	00192700
1928	WRITE (6, 7010)	00192800
1929	WRITE (6, 7011) (IPASS (Q), PCTPAS (Q)), Q = 1, 5)	00192900
1930	WRITE (6, 7012) (IPAIL (Q), PCTPL (Q)), Q = 1, 5)	00193000
1931	WRITE (6, 7013) (ISSETBA (Q), PCTSB (Q)), Q = 1, 5)	00193100
1932	WRITE (6, 7014) (ISNADIS (Q), PCTNDS (Q)), Q = 1, 5)	00193200
1933	WRITE (6, 7015)	00193300
1934	C	00193400
1935	GO TO 4444	00193500
1936	C	00193600
1937	C	00193700
1938	C HEADER FOR CENTER ANNUAL TOTALS	00193800
1939	C	00193900
1940	560 WRITE (6, 1000) YEAR, PAGE	00194000
1941	WRITE (6, 8001)	00194100
1942	8001 FORMAT (1MO, T42, '***** TOTALS FOR FLEET TRAINING CENTER *****')	00194200
1943	1000, '///')	00194300
1944	GO TO 560	00194400
1945	C	00194500
1946	4444 CONTINUE	00194600
1947	C	00194700
1948	C	00194800
1949	C	00194900
1950	C OUTPUT FORMATS FOR COURSE, SCHOOL & CENTER PRINTOUTS	00195000
1951	C	00195100
1952	1000 FORMAT (1ML, T49, 'TPF MODEL -- FISCAL YEAR ', 14, ' SUMMARY', T123,	00195200
1953	' PAGE ', 13)	00195300
1954	C	00195400
1955	1001 FORMAT (1, ' ', T58, ' SCHOOL CODE ', 4)	00195500
1956	C	00195600
1957	1000 FORMAT (1, ' ', A4, 5X, ZAB)	00195700
1958	C	00195800
1959	1001 FORMAT (1, ' ', T78, ' QUARTERLY PROJECTIONS')	00195900
1960	C	00196000
1961	2002 FORMAT (1, JND CATALOG NO NEC TYPE PRY', T40, ' 1 QTR FY ',	00196100
1962	' 12, ' 1 2 QTR FY ', 12, ' 1 3 QTR FY ', 12, ' 1 4 QTR FY ', 12,	00196200
1963	' 1 ANNUAL TOTAL ')	00196300
1964	C	00196400
1965	2003 FORMAT (1X, A4, 2X, AB, A2, 2X, A4, 4X, A2, 4X, A2,	00196500
1966	1 T42, '----- ----- ----- ----- ')	00196600
1967	C	00196700
1968	2004 FORMAT (1X, T42, 'NUMBER CONVENINGS ', 4 (15, ' ', 6X, ' ')),	00196800
1969	' 16, ' ', 6X, ' ')	00196900
1970	C	00197000
1971	2005 FORMAT (1, P ADD PFALL BACKLOG STU LENGTH',	00197100
1972	' T42, 'COURSE CAPACITY ', 4 (15, ' ', 6X, ' ')),	00197200
1973	' 16, ' ', 6X, ' ')	00197300
1974	C	00197400
1975	2006 FORMAT (1X, F5.1, F6.1, '8 INIT', 2X, 15, 14, ' WKS',	00197500
1976	' T42, 'UTILIZATION ', 4 (15, ' ', 6X, ' ')),	00197600
1977	' 16, ' ', 6X, ' ')	00197700
1978	C	00197800
1979	2007 FORMAT (1X, T19, 3 (4X, A2),	00197900
1980	' T42, 'NO SHOWS ', 4 (15, ' ', 6X, ' ')),	00198000
1981	' 16, ' ', 6X, ' ')	00198100
1982	C	00198200
1983	2008 FORMAT (1, '---SCHEDULE DATA--- FY FY+1 FY+2',	00198300
1984	' T42, 'ENROLL-STUDENTS/WKS', 4 (15, ' ', 6X, ' ')),	00198400
1985	' 16, ' ', 6X, ' ')	00198500
1986	C	00198600
1987	2009 FORMAT (1, ANNUAL CONVENINGS', 316,	00198700
1988	' T42, 'STUDENT DAYS / AOB', 4 (15, ' ', 6X, ' ')),	00198800
1989	' 16, ' ', 6X, ' ')	00198900
1990	C	00199000
1991	2010 FORMAT (1, COURSE LENGTH DYS', 3F6.1,	00199100
1992	' T10, ' ', T67, ' ', T74, ' ', T81, ' ', T88, ' ', T95, ' ', T102, ' ',	00199200
1993	' T109, ' ', T116, ' ', T124, ' ', T131, ' ')	00199300
1994	C	00199400
1995	2011 FORMAT (1, COURSE CAPACITY ', 316,	00199500
1996	' T42, 'TOTAL PASS ', 4 (15, ' ', 6X, ' ')),	00199600
1997	' 16, ' ', 6X, ' ')	00199700
1998	C	00199800
1999	2012 FORMAT (1, BUPERS SEATS ', 316,	00199900
2000	' T42, 'TOTAL FAIL ', 4 (15, ' ', 6X, ' ')),	00200000
2001	' 16, ' ', 6X, ' ')	00200100
2002	C	00200200
2003	2013 FORMAT (1, ANNUAL DEFAND ', 316,	00200300
2004	' T42, 'ACADEMIC SETBACK ', 4 (15, ' ', 6X, ' ')),	00200400
2005	' 16, ' ', 6X, ' ')	00200500
2006	C	00200600
2007	2014 FORMAT (1, BUPERS DERAND ', 316,	00200700
2008	' T42, 'ADM-ACAD DISENROLL', 4 (15, ' ', 6X, ' ')),	00200800
2009	' 16, ' ', 6X, ' ')	00200900
2010	C	00201000
2011	2015 FORMAT (1, OFFSET / CHG WEEK', 316,	00201100
2012	' T42, '----- ----- ----- ----- ')	00201200
2013	C	00201300

TABLE V-15 (CONTINUED)

611 V-165

TAEG REPORT NO. 29

INPUT LISTING

AUTODELOW CHART SET - FINAL

-KEND- FLOWCHARTS

```

00000000-----*,//)
C
0001 FORMAT (//////IX,T17,'SCHOOL CODE ',A4,' SUMMARY')
0002 FORMAT (/IX,T59,'QUARTERLY PROJECTIONS')
C
0003 FORMAT (IX,T37,'| 1 QTR FY ',I2,' | 2 QTR FY ',I2,' | 3 QTR
    *FY ',I2,' | 4 QTR FY ',I2,' | ANNUAL TOTAL |')
C
0004 FORMAT (IX,T17,'-----|-----|-----|
    *-----|-----|-----|)
C
0005 FORMAT (IX,T17,'NUMBER OF CONVENINGS',I6,' | ',I7X,' | ',I6,' | ',I7X,
    *'| ',I6,' | ',I7X,' | ',I6,' | ',I7X,' | ',I7,' | ',I7X,' | ')
C
0006 FORMAT (IX,T17,'COURSE CAPACITY',I5X,' | ',I6,' | ',I7X,' | ',I6,' | ',
    *I7X,' | ',I6,' | ',I7X,' | ',I6,' | ',I7X,' | ',I7,' | ',I7X,' | ')
C
0007 FORMAT (IX,T17,'UTILIZATION',T37,' | ',I6,' | ',F6.1,' | ',I6,' | ',
    *F6.1,' | ',I6,' | ',F6.1,' | ',I6,' | ',F6.1,' | ',I6,' | ',F6.1,' | ',
    *F6.1,' | ')
C
0008 FOR AT (IX,T17,'NO SHOWS',T37,' | ',I6,' | ',F5.1,' | ',I6,' | ',
    *F5.1,' | ',I6,' | ',F5.1,' | ',I6,' | ',F5.1,' | ',I7,' | ',F5.1,'
    *'| ')
C
0009 FORMAT (IX,T17,'STUDENT DAYS / AOB | ',I6,' | ',F6.1,' | ',I6,' | ',
    *F6.1,' | ',I6,' | ',F6.1,' | ',I6,' | ',F6.1,' | ',I7,' | ',
    *F6.1,' | ')
E
0010 FORMAT (IX,T37,' | ',I7X,' | ',I7X,' | ',I7X,' | ',I7X,' | ',I7X,' | ',I7X,
    *'| ',I7X,' | ',I7X,' | ',I7X,' | ')
C
0011 FORMAT (IX,T17,'TOTAL PASS',T37,' | ',I6,' | ',F5.1,' | ',I6,' | ',
    *F5.1,' | ',I6,' | ',F5.1,' | ',I6,' | ',F5.1,' | ',I7,' | ',F5.1,'
    *'| ')
C
0012 FORMAT (IX,T17,'TOTAL FAIL',T37,' | ',I6,' | ',F5.1,' | ',I6,' | ',
    *F5.1,' | ',I6,' | ',F5.1,' | ',I6,' | ',F5.1,' | ',I7,' | ',F5.1,'
    *'| ')
C
0013 FORMAT(IX,T17,'ACADEMIC SETBACK | ',I6,' | ',F5.1,' | ',I6,' | ',
    *'| ',F5.1,' | ',I6,' | ',F5.1,' | ',I6,' | ',F5.1,' | ',I7,' | ',
    *F5.1,' | ')
C
0014 FORMAT (IX,T17,'NON-ACADEMIC DISENROLL',I6,' | ',F5.1,' | ',I6,' | ',
    *'| ',F5.1,' | ',I6,' | ',F5.1,' | ',I6,' | ',F5.1,' | ',I7,' | ',
    *F5.1,' | ')
C
0015 FORMAT (IX,T17,'-----|-----|-----|
    *-----|-----|-----|)
C
      RETURN
      END
      SUBROUTINE CATOUT IXI
      IMPLICIT INTEGER(I-A-Z,S)
C
C COMMON FOR CLASS DATA MATRIX
C
      REAL*4 LEN, NOSHMO, NOSHPL, BKLGPL, BPOL, NADIS, FAIL, CDP
      REAL*4 TOWAND, SETBAX
C
      COMMON /DATA/ CDP (176), CRSRUM (176), CONV (13-176), LEN (13-176)
      COMMON /DATA/ CAP (13-176), BCAP (13-176), CMGKX (12-176)
      COMMON /DATA/ OFFSET (176), DEMAND (13-176), BDMAND (13-176)
      COMMON /DATA/ BPOL (176), FAIL (176), NADIS (176), NOSHPL (176)
      COMMON /DATA/ BKLOG (176), NOSHOM (176), BKLGPL (176)
      COMMON /DATA/ BKLG (176), TOWAND, SETBAX
C
      INTEGER*4 JND, PNRC, SCHOOL
      REAL*4 PAOR, PFAIL
      REAL*8 NAME1, NAME2, CATNO1
C
      COMMON /NAME/ JND (176), NAME1 (176), NAME2 (176), CATNO1 (176)
      COMMON /TEXT/ CATNO2 (176), PNRC (176), TYPE (176), PAOR (176)
      COMMON /TEXT/ PFAIL (176), PRTY (176), SCHOOL (176)
C
      REAL*4 PFAIL, TNADIS
      INTEGER*4 TSODAYS, TCAP, TUTIL
C
      COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), SSETBK (5, 176)
      COMMON /TOTALS/ TSODAYS (5, 176), PFAIL (5, 176), TNOSHO (5, 176)
      COMMON /TOTALS/ TNADIS (5, 176), TRKLOG (5, 176), TCONV (5, 176)
C
C COMMON FOR SCHOOL AND CENTER TOTALS
C
      INTEGER*4 SUTIL, CUTIL, SCAP, CCAP, SSODAYS, CSODAYS, IPAIL, INADIS
      INTEGER*4 PASS, SBKLOG, CBKLOG, SBKLCBKL
      REAL*4 AOB, PCTUL, PCTNSH, PCTPAS, PCTFL, PCTSB, PCTNDS, PLEN
C
      COMMON /T/ SUTIL (5), SCAP (5), SSODAYS (5), SSETBK (5), SNOSHO (5)
      COMMON /T/ CUTIL (5), CCAP (5), CSODAYS (5), CSETBK (5), CNOSHO (5)
      COMMON /T/ SBKLS (5), SBKLOG (5), SCONV (5), SPAIL (5), SNADIS (5)
      COMMON /T/ CCONVIS (5), CBKLS (5), CBKLOG (5), CPAIL (5), CNADIS (5)
      COMMON /T/ PCTUL (5), PCTNSH (5), PCTNDS (5), INADIS (5)
      COMMON /T/ AOB (5), PASS (5), PCTPAS (5), PCTFL (5), PCTSB (5)
      COMMON /T/ IPAIL (5), PLEN (5), BKL (5), SPLAT (4), YEAR2D
C
C COMMON FOR COMMUNICATION BETWEEN SUBROUTINES
C
      INTEGER*4 ITEM, ITEM1, ITEM2, ITEM3, ITEM4, ITEMS, WHERE
      REAL*4 TEM, TEM1, TEM2, TEM3, TEM4, TEM5, ALEN
C
      COMMON DUMMY, SCONV, ALEN, SCAP, ABCAP, LAST, COURSE
      COMMON SR1, SR2, SR3, SR4, TEM, TEM1, TEM2, TEM3, TEM4, TEM5
      COMMON ITEM, ITEM1, ITEM2, ITEMS, ITEM4, ITEMS
      COMMON YEAR, CRSES, Q, W, XROFF, INIT, WHERE, NEGLG, AOBCON
      COMMON TRACEF, RLSPG, ENOPLG, PREPLG, YRPLG, YEARUN, PRINTF
C
C IS 1 FOR COURSE OUTPUT, 2 FOR SCHOOL, 3 FOR CENTER (LAST)

```

TABLE V-15 (CONTINUED)

TAEG REPORT NO. 29

04/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-END- FLOWCHARTS

CARD NO

CONTENTS

2126	C ITEMS CONTAINS COURSE POINTER	00212600
2127	C	00212700
2128	IF (PRINTF .GT.X) RETURN	00212800
2129	I = ITEMS	00212900
2130	IF (X.EQ. 1) GO TO 1	00213000
2131	C	00213100
2132	WRITE (11, 5001) YEAR	00213200
2133	5001 FORMAT ('1', T2, 'TPP MODEL -- FISCAL YEAR ', 14, ' SUMMARY')	00213300
2134	C	00213400
2135	IF (X.EQ. 2) GO TO 5000	00213500
2136	C	00213600
2137	C CRT ROUTINE FOR CENTER TOTALS - ACTUAL DATA OUTPUT IN SCHOOL ROUTINE	00213700
2138	WRITE (11, 5001)	00213800
2139	6001 FORMAT (' ', T22, '00 TOTALS FOR FLEET TRAINING CENTER '0' /)	00213900
2140	WRITE (11, 6002)	00214000
2141	6002 FORMAT ('0' PTC - NORVA SUMMARY' /)	00214100
2142	GO TO 15000	00214200
2143	C	00214300
2144	C	00214400
2145	C OUTPUT FORMAT FOR CRT DISPLAY, COMPATABLE WITH OUTPUT FORMAT PROGRAM	00214500
2146	C FORMAT - ALWAYS 25 LINES OF OUTPUT, 1 FOR FIRST LINE, BLANK FOR DATA	00214600
2147	C LINES, / FOR FIRST LINE, * FOR END OF DATA	00214700
2148	C	00214800
2149	1 WRITE (9, 4001) COP (1), NAME1 (1), NAME2 (1)	00214900
2150	WRITE (9, 4002) CONV (1,1), CONV (2,1), CONV (3,1), BKLGI (1)	00215000
2151	WRITE (9, 4003) PLEN (1), PLEN (2), PLEN (3), BAKLOG (1)	00215100
2152	WRITE (9, 4004) SCHOOL (1), JND (1), CATNO1 (1), CATNO2 (1),	00215200
2153	* PNEG (1), CAP (1,1), CAP (2,1), CAP (3,1)	00215300
2154	WRITE (9, 4005) BCAP (1,1), BCAP (2,1), BCAP (3,1), CHGWR (1,1)	00215400
2155	WRITE (9, 4006) DEMAND (1,1), DEMAND (2,1), DEMAND (3,1),	00215500
2156	* CHGWR (2,1)	00215600
2157	WRITE (9, 4007) PAOB (1), PFAIL (1), TYPE (1), PRTY (1),	00215700
2158	* BDMAND (1,1), BDMAND (2,1), BDMAND (3,1), OFFSET (1)	00215800
2159	WRITE (9, 4008) SPLAT (1), SPLAT (2), SPLAT (3)	00215900
2160	WRITE (9, 4009) YEAR2D, YEAR2D, YEAR2D, YEAR2D	00216000
2161	WRITE (9, 4010)	00216100
2162	WRITE (9, 4011) TCONV (1,1), TCONV (2,1), TCONV (3,1), TCONV (4,1)	00216200
2163	1, TCONV (5,1)	00216300
2164	WRITE (9, 4012) TCAP (1,1), TCAP (2,1), TCAP (3,1), TCAP (4,1),	00216400
2165	1 TCAP (5,1)	00216500
2166	WRITE (9, 4013) (ITUTL (Q,1), PCTUTL (Q,1), Q = 1, 5)	00216600
2167	WRITE (9, 4014) (ITNSHO (Q,1), PCTNSH (Q,1), Q = 1, 5)	00216700
2168	WRITE (9, 4015) (ITBKLOG (Q,1), BKL (Q,1), Q = 1, 5)	00216800
2169	WRITE (9, 4016) (ITSDAYS (Q, 1), AOB (Q,1), Q = 1, 5)	00216900
2170	WRITE (9, 4017)	00217000
2171	WRITE (9, 4018) (IPASS (Q), PCTPAS (Q,1), Q = 1, 5)	00217100
2172	WRITE (9, 4019) (IPFAIL (Q), PCTFL (Q,1), Q = 1, 5)	00217200
2173	WRITE (9, 4020) (ITSETBK (Q,1), PCTSB (Q,1), Q = 1, 5)	00217300
2174	WRITE (9, 4021) (ITNADIS (Q), PCTNDS (Q,1), Q = 1, 5)	00217400
2175	WRITE (9, 4022)	00217500
2176	RETURN	00217600
2177	C	00217700
2178	C	00217800
2179	C CRT ROUTINE FOR SCHOOL AND CENTER TOTALS, ENTRY IS 15000 FOR CENTER	00217900
2180	C	00218000
2181	C	00218100
2182	5000 WRITE (11, 5002) SCHOOL (1)	00218200
2183	5002 FORMAT (1X, T33, 'SCHOOL CODE ', 44 /)	00218300
2184	C	00218400
2185	WRITE (11, 5003) SCHOOL (1)	00218500
2186	5003 FORMAT (' ', 44, 2X, 'SCHOOL SUMMARY' /)	00218600
2187	C	00218700
2188	C ENTRY CENTER TOTALS	00218800
2189	C	00218900
2190	15000 WRITE (11, 4009) YEAR2D, YEAR2D, YEAR2D, YEAR2D	00219000
2191	WRITE (11, 4010)	00219100
2192	WRITE (11, 5004) SCONV (1), SCONV (2), SCONV (3), SCONV (4), SCONV (5)	00219200
2193	WRITE (11, 5005) SCAP (1), SCAP (2), SCAP (3), SCAP (4), SCAP (5)	00219300
2194	WRITE (11, 5006) (ISUTL (Q), PCTUTL (Q,1), Q = 1, 5)	00219400
2195	WRITE (11, 5007) (ISNSHO (Q), PCTNSH (Q,1), Q = 1, 5)	00219500
2196	WRITE (11, 4015) (SBKLOG (Q), BKL (Q,1), Q = 1, 5)	00219600
2197	WRITE (11, 5008) (ISSDAYS (Q), AOB (Q,1), Q = 1, 5)	00219700
2198	WRITE (11, 4017)	00219800
2199	WRITE (11, 5009) (IPASS (Q), PCTPAS (Q,1), Q = 1, 5)	00219900
2200	WRITE (11, 5010) (IPFAIL (Q), PCTFL (Q,1), Q = 1, 5)	00220000
2201	WRITE (11, 5011) (ISSETBK (Q), PCTSB (Q,1), Q = 1, 5)	00220100
2202	WRITE (11, 5012) (ISNADIS (Q), PCTNDS (Q,1), Q = 1, 5)	00220200
2203	WRITE (11, 4022)	00220300
2204	RETURN	00220400
2205	C	00220500
2206	C	00220600
2207	C FORMATS FOR 80 COLUMN CRT OUTPUT	00220700
2208	C	00220800
2209	4001 FORMAT ('1', A4, 5X, Z4B, 4X, '---SCHEDULE DATA--- FY FY+1 FY+2	00220900
2210	*2 CRS BAKLOG')	00221000
2211	C	00221100
2212	4002 FORMAT (' ', T31, 'ANNUAL CONVENINGS', 15, 217, 4X, '0 STU', 15)	00221200
2213	C	00221300
2214	4003 FORMAT (' SCHL JND CATALOG NO NEC COURSE LENGTH DYS', F5, 1,	00221400
2215	* 2F7.1, 4X, '0 WRS', 15)	00221500
2216	C	00221600
2217	4004 FORMAT (' ', 2 (A4, 1X), 4B, A2, 1X, A4, 4X, 'COURSE CAPACITY',	00221700
2218	* 317)	00221800
2219	C	00221900
2220	4005 FORMAT (' ', T31, 'BUPERS CAPACITY', 317, 3X, 'FY+1 WK', 14)	00222000
2221	C	00222100
2222	4006 FORMAT (' P AOB PFAIL TYPE PRTY ANNUAL DEMAND', 2X, 317,	00222200
2223	* 3X, 'FY+2 WK', 14)	00222300
2224	C	00222400
2225	4007 FORMAT (' ', F5, 1, F6, 1, '0', 3X, 2 (A2, 5X), 'BUPERS DEMAND',	00222500
2226	* 2X, 317, 3X, '0-FSET', 15)	00222600
2227	C	00222700
2228	4008 FORMAT (1X, T4B, 3 (5X, A2), / 1X, T33, 'QUARTERLY PROJECTIONS')	00222800
2229	C	00222900
2230	4009 FORMAT (' ', 12X, '1 1 OR FY', 13, '1 2 OR FY', 13,	00223000
2231	'1 3 OR FY', 13, '1 4 OR FY', 13, '1 ANNUAL TOTAL '1)	00223100
2232	C	00223200
2233	4010 FORMAT (' ', '-----[-----]-----[-----]-----[-----]	00223300
2234	'1 '-----[-----]-----[-----]-----[-----]	00223400
2235	C	00223500
2236	4011 FORMAT (' ', '0 CONVENINGS', 14, ' ', 5X, ' ', 14, ' ', 14,	00223600
2237	'1 5X, ' ', 14, ' ', 5X, ' ', 14, ' ', 14, ' ', 5X, ' ', 14,	00223700

TABLE V-15 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-KEND- FLOWCHARTS

CARD NO

CONTENTS

2238	2 10, ' 1, 5X, ' 1)	00223800
2239	C	00223900
2240	4012 FORMAT (' 1, 'CRS CAPACITY', 14, ' 1, 5X, ' 1, 14, ' 1,	00224000
2241	1 5X, ' 1, 14, ' 1, 5X, ' 1, 14, ' 1, 5X, ' 1,	00224100
2242	2 10, ' 1, 5X, ' 1)	00224200
2243	C	00224300
2244	4013 FORMAT (' 1, 'UTILIZATION', 14, ' 1, F5.1, 'E', 14, ' 1,	00224400
2245	1 F5.1, 'E', 14, ' 1, F5.1, 'E', 14, ' 1, F5.1, 'E',	00224500
2246	2 10, ' 1, F5.1, 'E')	00224600
2247	C	00224700
2248	4014 FORMAT (' 1, 'NO SHOWS', 14, ' 1, F5.1, 'E', 14, ' 1,	00224800
2249	1 F5.1, 'E', 14, ' 1, F5.1, 'E', 14, ' 1, F5.1, 'E',	00224900
2250	2 10, ' 1, F5.1, 'E')	00225000
2251	C	00225100
2252	4015 FORMAT (' 1, 'BAKLOG #/WKS', 14, ' 1, 12, 'WKS', 14, ' 1,	00225200
2253	1 12, 'WKS', 14, ' 1, 12, 'WKS', 14, ' 1, 12, 'WKS',	00225300
2254	2 10, ' 1, 12, 'WKS')	00225400
2255	E	00225500
2256	4016 FORMAT (' 1, 'STU DAYS/AOB', 14, ' 1, F5.1, ' 1, 14, ' 1,	00225600
2257	1 F5.1, ' 1, 14, ' 1, F5.1, ' 1, 14, ' 1, F5.1, ' 1,	00225700
2258	2 10, ' 1, F5.1, ' 1)	00225800
2259	C	00225900
2260	4017 FORMAT (' 1, 12X, ' 1, 5X, ' 1, 6X, ' 1, 5X, ' 1, 6X, ' 1, 5X,	00226000
2261	1 ' 1, 6X, ' 1, 5X, ' 1, 6X, ' 1, 7X, ' 1, 6X, ' 1)	00226100
2262	C	00226200
2263	4018 FORMAT (' 1, 'TOTAL PASS', 14, ' 1, F5.1, 'E', 14, ' 1,	00226300
2264	1 F5.1, 'E', 14, ' 1, F5.1, 'E', 14, ' 1, F5.1, 'E',	00226400
2265	2 10, ' 1, F5.1, 'E')	00226500
2266	C	00226600
2267	4019 FORMAT (' 1, 'TOTAL FAIL', 14, ' 1, F5.1, 'E', 14, ' 1,	00226700
2268	1 F5.1, 'E', 14, ' 1, F5.1, 'E', 14, ' 1, F5.1, 'E',	00226800
2269	2 10, ' 1, F5.1, 'E')	00226900
2270	C	00227000
2271	4020 FORMAT (' 1, 'SETBACK ACAD', 14, ' 1, F5.1, 'E', 14, ' 1,	00227100
2272	1 F5.1, 'E', 14, ' 1, F5.1, 'E', 14, ' 1, F5.1, 'E',	00227200
2273	2 10, ' 1, F5.1, 'E')	00227300
2274	C	00227400
2275	4021 FORMAT (' 1, 'DISENROLL NA', 14, ' 1, F5.1, 'E', 14, ' 1,	00227500
2276	1 F5.1, 'E', 14, ' 1, F5.1, 'E', 14, ' 1, F5.1, 'E',	00227600
2277	2 10, ' 1, F5.1, 'E')	00227700
2278	E	00227800
2279	4022 FORMAT (' 1, '-----,	00227900
2280	'	00228000
2281	2 ' / ' / ')	00228100
2282	C	00228200
2283	SCHOOL AND CENTER CRT FORMATS	00228300
2284	C	00228400
2285	5004 FORMAT (' 1, '8 CONVENINGS', 15, ' 1, 5X, ' 1, 15, ' 1,	00228500
2286	1 5X, ' 1, 15, ' 1, 5X, ' 1, 15, ' 1, 5X, ' 1,	00228600
2287	2 10, ' 1, 5X, ' 1)	00228700
2288	E	00228800
2289	5005 FORMAT (' 1, 'CRS CAPACITY', 15, ' 1, 5X, ' 1, 15, ' 1,	00228900
2290	1 5X, ' 1, 15, ' 1, 5X, ' 1, 15, ' 1, 5X, ' 1,	00229000
2291	2 10, ' 1, 5X, ' 1)	00229100
2292	C	00229200
2293	5006 FORMAT (' 1, 'UTILIZATION', 15, ' 1, F5.1, 'E', 15, ' 1,	00229300
2294	1 F5.1, 'E', 15, ' 1, F5.1, 'E', 15, ' 1, F5.1, 'E',	00229400
2295	2 10, ' 1, F5.1, 'E')	00229500
2296	C	00229600
2297	5007 FORMAT (' 1, 'NO SHOWS', 15, ' 1, F5.1, 'E', 15, ' 1,	00229700
2298	1 F5.1, 'E', 15, ' 1, F5.1, 'E', 15, ' 1, F5.1, 'E',	00229800
2299	2 10, ' 1, F5.1, 'E')	00229900
2300	C	00230000
2301	14015 FORMAT (' 1, 'BAKLOG #/WKS', 15, ' 1, 12, 'WKS', 15, ' 1,	00230100
2302	1 12, 'WKS', 15, ' 1, 12, 'WKS', 15, ' 1, 12, 'WKS',	00230200
2303	2 10, ' 1, 12, 'WKS')	00230300
2304	C	00230400
2305	5008 FORMAT (' 1, 'STU DAYS/AOB', 15, ' 1, F6.1, ' 1, 15, ' 1,	00230500
2306	1 F6.1, ' 1, 15, ' 1, F6.1, ' 1, 15, ' 1, F6.1, ' 1,	00230600
2307	2 10, ' 1, F6.1, ' 1)	00230700
2308	C	00230800
2309	5009 FORMAT (' 1, 'TOTAL PASS', 15, ' 1, F5.1, 'E', 15, ' 1,	00230900
2310	1 F5.1, 'E', 15, ' 1, F5.1, 'E', 15, ' 1, F5.1, 'E',	00231000
2311	2 10, ' 1, F5.1, 'E')	00231100
2312	C	00231200
2313	5010 FORMAT (' 1, 'TOTAL FAIL', 15, ' 1, F5.1, 'E', 15, ' 1,	00231300
2314	1 F5.1, 'E', 15, ' 1, F5.1, 'E', 15, ' 1, F5.1, 'E',	00231400
2315	2 10, ' 1, F5.1, 'E')	00231500
2316	E	00231600
2317	5011 FORMAT (' 1, 'SETBACK ACAD', 15, ' 1, F5.1, 'E', 15, ' 1,	00231700
2318	1 F5.1, 'E', 15, ' 1, F5.1, 'E', 15, ' 1, F5.1, 'E',	00231800
2319	2 10, ' 1, F5.1, 'E')	00231900
2320	C	00232000
2321	5012 FORMAT (' 1, 'DISENROLL NA', 15, ' 1, F5.1, 'E', 15, ' 1,	00232100
2322	1 F5.1, 'E', 15, ' 1, F5.1, 'E', 15, ' 1, F5.1, 'E',	00232200
2323	2 10, ' 1, F5.1, 'E')	00232300
2324	C	00232400
2325	RETURN	00232500
2326	END	00232600
2327	BLOCK DATA	00232700
2328	C	00232800
2329	INITIAL VALUES FOR PARAMETERS IN COMMON STORAGE	00232900
2330	C	00233000
2331	IMPLICIT INTEGER*2 (A-Z,8)	00233100
2332	REAL*4 LEN, NOSHOW, NOSMPL, BKLGPL, BPOOL, NADIS, FAIL, EDP	00233200
2333	REAL*4 TDAND, SETBAK	00233300
2334	C	00233400
2335	COMMON /DATA/ CDP (176), CASRUN (176), CONV (3,176), LEN (3,176)	00233500
2336	COMMON /DATA/ CAP (3,176), RCAP (3,176), CMGR (12,176)	00233600
2337	COMMON /DATA/ OFFSET (176), DEMAND (3,176), BDMAND (3,176)	00233700
2338	COMMON /DATA/ BPOOL (176), FAIL (176), NADIS (176), NOSMPL (176)	00233800
2339	COMMON /DATA/ BAKLOG (176), NOSHOW (176), BKLGPL (176)	00233900
2340	COMMON /DATA/ BKLG (176), TDAND, SETBAK	00234000
2341	E	00234100
2342	DATA BKLG/176*0/, CASRUN /176*0/, BKLGPL, NOSMPL, BPOOL /528*0./	00234200
2343	C	00234300
2344	QUARTERLY AND ANNUAL COURSE TOTALS ACCUMULATION	00234400
2345	REAL*4 TFAIL, TNADIS	00234500
2346	INTEGER*4 TSDAYS, TCAP, TUTIL	00234600
2347	C	00234700
2348	COMMON /TOTALS/ TCAP (5, 176), TUTIL (5, 176), TSETBR (5, 176)	00234800
2349		00234900

TABLE V-15 (CONTINUED)

TAEG REPORT NO. 29

08/15/75

INPUT LISTING

AUTOFLOW CHART SET - FINAL

-REND- FLOWCHARTS

CARD NO	****	CONTENTS	****
2350		COMMON /TOTALS/ TSDAYS (5, 176), TFAIL (5, 176), TNOSHO (5, 176)	00235000
2351		COMMON /TOTALS/ TNADIS (5, 176), TBKLOG (5, 176), TCONV (5, 176)	00235100
2352	C		00235200
2353		DATA TCAP /880*0/, TUTIL /880*0/, TSETBK /880*0/	00235300
2354		DATA TNADIS /880*0/, TBKLOG /880*0/, TCONV /880*0/	00235400
2355		DATA TSDAYS /880*0/, TFAIL /880*0/, TNOSHO /880*0/	00235500
2356	C		00235600
2357	C	COMMON FOR COURSE ACTIVE MATRIX ELEMENTS	00235700
2358	C		00235800
2359		REAL** ACTCTR	00235900
2360		COMMON /RUN/ ACTIVE (250), ACTCTR (250), ACTUTL (250), ACTNEG (250)	00236000
2361	C		00236100
2362		DATA ACTIVE /250*0/, ACTCTR /250*0/, ACTUTL, ACTNEG /500*0/	00236200
2363	C		00236300
2364	C	COMMON FOR SCHOOL AND CENTER TOTALS	00236400
2365	C		00236500
2366		INTEGER** SUTIL, CUT, SCAP, CCAP, SSDAYS, CSDAYS, IFAIL, INADIS	00236600
2367		INTEGER** PASS, SBK, G, CBKLOG, SBKL, CBKL	00236700
2368		REAL** AOB, PCTUTL, PCTNSH, PCTPAS, PCTFL, PCTSB, PCTNDS, PLEN	00236800
2369	C		00236900
2370		COMMON /T/ SUTIL (5), SCAP (5), SSDAYS (5), SSETBK (5), SNOSHO (5)	00237000
2371		COMMON /T/ CUTIL (5), CCAP (5), CSDAYS (5), CSETBK (5), CNOSHO (5)	00237100
2372		COMMON /T/ SBKL (5), SBKLOG (5), SCONV (5), SFAIL (5), SNADIS (5)	00237200
2373		COMMON /T/ CCONV (5), CBKL (5), CBKLOG (5), CFAIL (5), CNADIS (5)	00237300
2374		COMMON /T/ PCTUTL (5), PCTNSH (5), PCTNDS (5), INADIS (5)	00237400
2375		COMMON /T/ AOB (5), PASS (5), PCTPAS (5), PCTFL (5), PCTSB (5)	00237500
2376		COMMON /T/ IFAIL (5), PLEN (5), BKL (5), SPLAT (4), YEAR20	00237600
2377	C		00237700
2378		DATA SPLAT // ** ,3* ' /	00237800
2379	C		00237900
2380		END	00238000

TABLE V-15 (CONTINUED)

UNCLASSIFIED

Security Classification

DOCUMENT CONTROL DATA - R & D

(Security classification of title, body of abstract and indexing annotation must be entered when the overall report is classified)

1. ORIGINATING ACTIVITY (Corporate author)		2a. REPORT SECURITY CLASSIFICATION	
International Business Machines Corp., Civil/Space Sys., Federal Systems Division, Cape Kennedy Facility, 7900 N. Astronaut Blvd., Cape Canaveral, FL 32920		UNCLASSIFIED	
3. REPORT TITLE		2b. GROUP	
DESIGN OF TRAINING SYSTEMS - PROGRAM MAINTENANCE MANUAL DATA BASE, ETE, SCRR, AND TPF MODELS		N/A	
4. DESCRIPTIVE NOTES (Type of report and inclusive dates)			
5. AUTHOR(S) (First name, middle initial, last name)			
Harold J. Bellamy James D. Staley Kenneth V. Branch Ronald E. Yanko			
6. REPORT DATE		7a. TOTAL NO. OF PAGES	7b. NO. OF REFS
September 1975		612	0
8a. CONTRACT OR GRANT NO.		9a. ORIGINATOR'S REPORT NUMBER(S)	
N61330-73-C-0097		TAEG REPORT NO. 29	
b. PROJECT NO.		9b. OTHER REPORT NO(S) (Any other numbers that may be assigned this report)	
c.			
d.			
10. DISTRIBUTION STATEMENT			
Approved for Public Release; Distribution is Unlimited.			
11. SUPPLEMENTARY NOTES		12. SPONSORING MILITARY ACTIVITY	
		Training Analysis and Evaluation Group, Orlando, FL	
13. ABSTRACT			
This report contains detailed information on the three Design of Training Systems (DOTS) models and the DOTS data base. It consists of a single volume containing a description and macro flow, detailed logic flows and program listings for the Educational Technology Evaluation model (ETE), the System Capabilities Requirements and Resources (SCRR) model, the Training Process Flow (TPF) model and the DOTS data base. Control logic, input/output record formats, and temporary and permanent data files are described for each subsystem (the three models and the data base). The information contained in this volume is intended for use by programmers tasked with installing or modifying the DOTS programs.			

DD FORM 1473

(PAGE 1)

S/N 0102-014-8800

616

UNCLASSIFIED

Security Classification

14 KEY WORDS	LINK A		LINK B		LINK C	
	ROLE	WT	ROLE	WT	ROLE	WT
Training Management Systems Computer Based Models Training Resource Evaluation Modeling Interactive Training Data Base Educational Technology Evaluation						